Development of Maintenance Form Oracle Banking Corporate Lending Release 14.5.3.0.0 [Nov] [2021]



Contents

1.	Preface	3
1	1.1 Audience	3
1	1.2 Related Documents	3
2.	Introduction	3
2	2.1 How to use this Guide	3
3.	Overview of Maintenance Screen	4
4.	Screen Development	4
4	4.1 Header Information	4
4	4.2 Preferences	6
4	4.3 Data Sources	7
4	4.4 Data Blocks	12
4	4.5 Screens	14
4	4.6 Field Sets	16
4	4.7 LOV	20
4	4.8 Attaching Call forms	23
	4.9 Adding Summary	
4	4.10 Amendable fields Maintenance	
5.	Generation and Deployment of files	
6.	Generated Units	
6	6.1 Front End Units	
	6.1.1 Language xml	
	6.1.2 SYS JavaScript File	
	6.1.3 Release Type Specific JavaScript File	
6	6.2 Data Base Units	
	6.2.1 Static Scripts	
	6.2.2 System Packages	
	6.2.3 Hook Packages	34
6	6.3 Other Units	24
0	6.3.1 Xsd	
7.		
	7.1 Extensibility in JavaScript Coding	
	7.1 Extensionity in JavaScript Coding	
/	7.2 Extensionity in Backend Counig 7.2.1 Functions in Hook Packages	
	0	
	7.2.2 Flow of control through Hook packages	
	7.2.3 By passing Base Release Functionality	

1. Preface

This document describes Maintenance Screens in FLEXCUBE and the process of designing a simple Maintenance form using Oracle FLEXCUBE Development Workbench for Universal Banking

1.1 Audience

This document is intended for FLEXCUBE Application developers/users that use development Workbench to develop various FLEXCUBE components.

To Use this manual, you need conceptual and working knowledge of the below:

Proficiency	Resources
FLEXCUBE Functional Architecture	Training programs from Oracle
	Financial Software Services.
FLEXCUBE Technical Architecture	Training programs from Oracle
	Financial Software Services.
FLEXCUBE Screen Development	04-Development_WorkBench
-	_Screen_Development-I.docx
Working knowledge of Web based applications	Self Acquired
Working knowledge of Oracle Database	Oracle Documentations
Working knowledge of PLSQL & SQL Language	Self Acquired
Working knowledge of XML files	Self Acquired

1.2 Related Documents

<u>04-Development_WorkBench_Screen_Development-I.docx</u> <u>05-Development_WorkBench_Screen_Development-II.docx</u>

2. Introduction

2.1 How to use this Guide

The information in this document includes:

- <u>Chapter 2 , "Introduction"</u>
- Chapter 3, "Overview of Call Form"
- Chapter 4 , "Screen Development"
- Chapter 5 , "Generated Units"
- <u>Chapter 5</u>, "Extensible Development"

3. Overview of Maintenance Screen

Maintenance Function Id's are used for storing maintenance data which are required for processing of any contracts, batches or for any other maintenance which are dependent on this

Example: Customer maintenance screen

If any customer wants to use the service of a bank, details about the customer will have to be maintained in the system .This will be maintenance data which will be required for other maintenances (creating account for the customer) as well as for transaction processing (debiting of customer account)

Business logic for a maintenance function id would be provided by the Development Workbench generated files .Most of the cases, system provided logic would be sufficient .Extra validations can be coded in the hook packages by the developer.

4. Screen Development

Design and development of a Maintenance function id is similar to any other function Ids. This section briefs the steps in designing a Maintenance screen. STDCINF is sample function id used for demonstration in this document

For detailed explanation, refer the document: <u>4-Development_WorkBench</u> <u>Screen_Development-I.docx</u>

4.1 Header Information

Provide the header information as shown in the figure.

ACLE FLEXCUBE Development Workb	ench for Universal Banking	DEMOUSER
owser .		Windows Options Sign Out
ction Generation		- ×
		2 2 1 7 9 4
Action None -	Function Type Parent	Function Category Maintenance -
Function Id	Parent Function	Header Template None
Save XML Path	Parent Xml	Footer Template None ~
Otalues O	g 12.1: Providing Header Information	

- For new screen select action As New.
- Enter Function ID \rightarrow STDCIFD
- Function Type \rightarrow Parent
- Function Category → Maintenance
- Parent Function Id \rightarrow None
- Parent Xml \rightarrow None
- Header Template \rightarrow None (Only for Process flow screens)
- Footer Template \rightarrow Maint Audit

RACLE FLEXCUBE Development Workbend	th for Universal Banking	DEMOUSER Windows Options Sign Out
nction Generation		
Action New ·	Function Type Parent	Euction Category Maintenance - Sove (CTSL + S)
Function Id STDCIFD	Parent Function	Function Category Maintenance Header Template None
Save XML Path D1R4DTOOL	Parent Xml	Footer Template None +
ListOffalues DataBlocks Screes FieldSets Califorms Califorms LaunchForms Summary		

User can save work at any point in time. Click the save icon on top right for the same .In order to work again with it select action as Load and load radxml from the hard disk path

Browser -	nent Workbench for Universa	i Banking	Windows	Options	MOUSER Sign Out
Function Generation					- 3
Action New • Function Id STDCIFD Save XML Pain DNRADTOXL	Action New Action New Function Type Parent Function Id STDC:FD Parent Struct Parent Struct Parent Xm Par	Function Category Maintenance + Header Template None +		17 W 4	
Search Preferances DalaSource LustOrialves Screens FriedSista Actions Califorms LaunchForms Summary	Er	O% of DownLoadFile from 10.184.132.100 Completed			

Fig 12.3: Saved File Information page

Note the following while providing header information for Maintenance screen

i) Naming Convention:

The third letter of the function id has to be D. Ideally the function id name should have 8 characters.

ii) Footer Template

Make sure that the master data source has the audit columns if footer template is provided as Maint log.

Refer <u>04-Development_WorkBench_Screen_Development-I.docx</u> for detailed explanation

4.2 Preferences

- Details entered in Preferences are used in generating INCS for SMTB_MENU, SMTB_FUNCTION_DESCRIPTION and SMTB_ROLE_DETAILS.
- **Control String** → Developer needs to select the actions which should be available for this screen in FLEXCUBE.

Action New Function Type Parent Function Id STDCIFD Parent Function Save XML Path DIRADTOOL Preferences Preferences DataStocks DataSt	Browser -	pment Workbench for Universal Banking			Window		EMOUS Sign 0	
Action New Function Type Parent Function Type Parent Function Category Maintenance Function Id STDCIFD Parent Function Header Template None Header Template None save XML Path D/RADTOOL Preferences Footer Template None Image: Control Stripping Required Preferences Image: Control Stripping Required Module Description Static Maintenance Image: Control Stripping Required Module Static Maintenance Image: Control Stripping Required Image: Control Stripping Required Field Log Required SVN Repository URL Choose Block Image: Choose Field Image: Control Stripping Image: Control Stripping Excel Export Required Image: Choose Field Image: Choose Field Image: Control Stripping Image: Control Stripping Function Module Module Module Description	unction Generation						- 47 6	-
Function Id STDCIFD Parent Function Header Template None Save XML Path D/RADTOOL Parent Xmt Footer Template None Image: Control String Image: Cont	Action New *	Function 1	Type Parent	•	Function Category Maintenance	_		
Preferences Module ST Image: Control String DataStores U Logging Required Module Description Static Maintenance DataStores I ListOfValues Auto Authorization Branch Program Id DataStores I ank Modifications Process Code Screens I Field Log Required SVN Repository URL CallForms I field Log Required Transaction Block CallForms Excel Export Required Transaction Block Summary Excel Export Required Transaction Field				T	A STORE ST			
Preferences Image: Head Office Function Module Strice DataSource Logging Required Module Description Static Maintenance DataSource Image: Auto Authorization Branch Program Id Static Maintenance DataSource Image: Auto Authorization Branch Program Id Image: Auto Authorization Screens Image: Auto Authorization Process Code Image: Auto Authorization FieldSets Image: Auto Autorization Process Code Image: Auto Autorization CallForms Image: Auto Autorization Process Code Image: Autorization CallForms Image: Autorization Multi Branch Access Image: Autorization Block Image: Autorization Block LaunchForms Excel Export Required Transaction Field Image: Autorization Summary Excel Export Required Transaction Field Image: Autorization Control String Function Id Module * Module Description	Save XML Path DIRADTOOL	Parent	Xml		Footer Template None	•		
DataSource Incluie DataSource Incluie ListOfValues Incluie DataBlooks Incluie DataBlooks Incluie Screens Incluie FieldSets Incluie Actions Field Log Required Screens Incluie Califorms Multi Branch Access Califorms Multi Branch Access Summary Excel Export Required Transaction Field Incluie Name Name	arch	Preferences					1	9
Function Id Module Module Module Description	DataSource ListOfValues DataBlocks Screens FieldSets CallForms CallForms LaunchForms	 Uogging Req. Auto Authoriza Tank Modifica Field Log Req. Multi Branch A 	uired Bion Bions Quired Rocess	Module Description Branch Program Id Process Code SVN Repository URL Transaction Block Name Transaction Field	Static Maintenance Choose Block			
		Europhian Id			Hadula Dasseintian	Control Stri	19 + -	
STDCIFD BT Fill Static Maintenance		New York Contract of the Contr	βт					

Note the following points while providing details in Preferences screen

i) Control String

REVERSE, ROLLOVER, CONFIRM, LIQUIDATE, HOLD operations are not applicable for maintenance screens.

ii) Defining Browser Menu Tree

Browser menu tree will be defined in the script generated for *smtb_function_description*.

The following labels has to be maintained for generation of proper script Main Menu: LBL_{function id}_MAIN_MENU Sub Menu 1: LBL_{function id}_SUB_MENU_1 Sub Menu 2: LBL_{function id}_SUB_MENU_2 Description: LBL_{function id}_DESC *Example: For STDCIFD, following labels has to be maintained* LBL_STDCIFD_MAIN_MENU, LBL_STDCIFD_SUB_MENU_1, LBL_STDCIFD_SUB_MENU_2, LBL_STDCIFD_DESC

Refer <u>Development_WorkBench_Screen_Development-I.docx</u> for detailed explanation on preferences

4.3 Data Sources

- Right Click on Data Sources; click on Add. Add table window gets opened.
- If user knows the exact table name, he can enter name directly; else go to List Of values to get the list of tables available. Select the required table from the list.

Browser .	lopment Workbench for Universal Banking	DEMOUSER Windows Options Sign Out
Function Generation		- ×
Action New • Function Id STDC/FD Save XML Path D1RADTO	Function Type Parent Parent Function L Parent Xm	Function Category Maintananaa • Header Temptale Hone • Fooler Temptate None •
Search	AddTable	<u>×</u>
Preferences DalaSource ListOfvalues DalaBlocks	Table Name FT X	arent Relation Type *
FieldSals Actions CallForms LaunchForms Summary	Search Reset	
	Table Name * STTM_CUSTOMER STTM_CUSTOMER_ALTERNATE_BRANCH STTM_CUSTOMER_ALTERNATE_BRANCH STTM_CUSTOMER_CAT STTM_CUSTOMER_INAM_DETAIL STTM_CUSTOMER_NAM_MASTER STTM_CUSTOMER_PARAM STTM_CUSTOMER_PRE_IMAGE STTM_CUSTOMER_SOURCE_DETAILS STTM_CUSTOMER_SRO_DETAILS STTM_CUSTOMER_SRNO STTM_CUSTOMER_INUSED STTM_CUSTOMER_VINUSED STTM_CUSTOMER_VINUSED	

Fig 12.5: Adding Data Sources for the Function id

- Select Master as Yes if added data source is Master Data Source for the screen. Every function id should have one master data source..
- **Primary Key columns** (i.e. Pk Cols) and **Primary Types** (i.e. Pk Types) are mandatory. If it is already maintained in user schema in STTB_PK_COLS it will populated automatically otherwise user needs to enter values without fail. If user misses Pk cols and Pk Types package generation will fail. *Note: Master Data Source cannot have any parent.*

ORACLE FLEXCUBE Development Workbe	nch for Universal Banking - Windows Internet Explorer	-	And Ann Manual State				6		x
ORACLE' FLEXCUBE Develop	oment Workbench for Universal Banking						DEM	OUSE	R
Browser -					Windows	Opti	ons	Sign Ou	t
Function Generation									- ×
					L. L	. ×	= 1	V 🕲	4
Action New -	Function Type Parent	•		Function Category Maint	enance 👻				
Function Id STDCIFD	Parent Function			Header Template None	-				
Save XML Path D:RADTOOL	Parent Xml			Footer Template None	, .	•			
Search	Data Source Details						4) ^
 Preferences DataSource STTL_CUSTOMER ListOVAlues DataBlocks Screens FieldSets Actions CallForms LauchForms Summary 	Data Source Master Relation Type Multis Record PK Cots • USTOMER No • PK Types • VARCHAR2 Upload Table	0	Parent Relation Where Clause Default Order By Type	Normal Mandatory	•	10.0			

Fig 12.6: Providing master Data Source Properties

• Right Click on Added Table (STTM_CUSTOMER) to add fields to the table. Popup window gets opened with available columns in data source. Select the required fields and click ok. Selected will get added to the Data Source Tree.

CRACLE FLEXCUBE Development Workbenc	h for Universal Banking - Windows Internet Explorer		ergenet, Allerson Streams 1	the state of the s				٥	23
ORACLE FLEXCUBE Developm	ent Workbench for Universal Banking					D	EMO	USE	R
Browser -				Window	vs (Option:	s Si	gn Out	
Function Generation									- ×
						×	= V	9	4
Action New -	Function Type Parent	•		Function Category Maintenance	•				
Function Id STDCIFD	Parent Function			Header Template None 💌					
Save XML Path D:RADTOOL	Parent Xml			Footer Template None	•				
Search	Data Source Details						+	- 🧳	^
Preferences DataSource The ListONalues DataBlocks DataBlocks DataBlocks CaliForms CaliForms Summary DataBlocks DataBlock	Data Source Master Relation Type Multi Record PK Cols USTOMER_NO PK Types Upload Table	n n	Parent Relation Where Clause Default Order By Type	Normal Mandatory					

Fig 12.7: Including Data Source Fields for the Data Source

Function Generation Action New • Function Id STDOIFD	Function Type: Parent						
Function Id STDCIFD	Function Type Parent					-	
Function Id STDCIFD	Function Type Parent						17 91 9
					Function Category Maintenance •		
	Parent Function				Header Templals None •		
Save XML Path DoRADTOOL	Parent Xmt				Foolsr Template Nons	•	
Select F	ields		×				+ - 9)
Preferances DalaSource STIM_CUSTOMER DalaSource STIM_CUSTOMER DustaBlocks DalaBlocks DalaBloc							
	CUSTOMER NO	VARCHAR2				2	
	CUSTOMER_TYPE	CHAR				20	
	CUSTOMER_NAME1	VARCHAR2			Normal •		
FieldSats	ADDRESS_LINE1	VARCHAR2		10230	T Mandalory		
	ADDRESS_LINE3	VARCHAR2					
CaunchForms [1]	ADDRESS_LINE2	VARCHAR2					
Summary	ADDRESS_LINE4	VARCHAR2					
2	COUNTRY	VARCHAR2					MOUSER Sign Out
8	SHORT_NAME	VARCHAR2					
2	NATIONALITY	VARCHAR2	H				
	LANGUAGE	VARCHAR2					
		10 10 1					
		Ok Cancel					

Fig 12.7: Selecting Data Source Fields for the Data Source

Data Source Field Properties:

Only max length can be modified by the developer in data source field properties. Rest will be defaulted from table definition

	ment Workbench for Unive	rsal Banking						
A CONTRACTOR OF				Win	dows	Options	Sign O	
unction Generation							17 6	
					Las		VV	
Action New Action New Function Id STDC/FD Save XML Path D/RADTOOL Parent Function Save XML Path D/RADTOOL Parent Xml Colore Strm_CUSTOMER_NO CUSTOMER_NO CUSTOMER_NO CUSTOMER_NAME1 ADDRESS_ILNE1 COUNTRY NATIONALITY LANGUAGE DataBlocks Screens Field Stats Actions Califorms Caliform Califor Caliform Califo	-		ce •					
Function Id STDCIFD		Parent Function		Header Template None	•			
Save XML Path DIRADTOOL		Parent Xml	Data Type Upload Table Column Not Required in Upload Tables Operties for Data Source Fields					
arch	Data Source Field	Details				Refr	rsh 🗕 G	9
Browser - Vindows Options Sign Out								
		1						
	COUNTRY NATIONALITY LISIONalues DataBlocks Screens FieldSets Actions CallForms LiandForms	Action New Action New Action New Action Id STDCIFD Action Id STDCIFD Action Id STDCIFD Action Type Parent Parent Function Parent Xml Data Source Field Details CustomER CustomER						
	E:- 10 7 J)		1-				

Data model of a single function id would include multiple tables .All the tables needs to added in the function id. Note the following while adding child data sources

Adding Child Data Source:

- Select Multi Record value as Yes if child data source is Multi record table.
- Child Data Source should always be associated with a parent.
- Relation is mandatory between parent and child. While giving relation, parent data source should come in left side of the relation.

RACLE FLEXCUBE Developm	ent Workbench for Universal Banking				DE	MOUS	SER
rowser .				Windows	Options	Sign (Out
action Generation							-
					× =	19	9
Action New -	Function Type Parent	•		Function Category Maintenance -			
Function Id STDCIFD	Parent Function			Header Template None -			
Save XML Path D:IRADTOOL	Parent Xml			Footer Template None •			
arch	Data Source Details					+ -	9
Preferences Preferences GalaSource GalaSource GalaCourse RELATIONSHIP GalaSource RELATIONSHIP GalaSource Screens FieldSets CallForms CallForms Summary Summary	Data Source Master Relation Type Multi Record PK Cols • GROUP_ID-CUSTOMER_NO PK Types • VARCHAR2-VARCHAR2 Upload Table		Parent Relation Where Clause Default Order By Type	STTM_CUSTOMER STTM_CUSTOMER CUSTOMER_NO = S			

Fig 12.7: Providing properties for Child Data Source

Note: A data source cannot be parent to itself.

Note the following while adding data sources:

- i) If the data source is designed with relation type as 1: N with its parent, then it should have at least one more Pk col than its parent (assuming relationship is based on Pk cols).
- ii) Master data source needs to have the audit columns if footer template is Maint audit; but those should not be added to data source fields as system will handle it

Refer <u>Development_WorkBench_Screen_Development-I.docx</u> for detailed explanation on data sources.

4.4 Data Blocks

• Block Name should start with BLK_<short Name equivalent to data source but not exactly same as Data Source name>.

Add Block		×
Block Name	BLK_CUSTOMER	
	Ok Cancel	
Fig 12 9.	Creating a new Data Block	

- Select Parent block if added block is not Master Block.
- Select Multi Record (Yes/No) based on this value, available data sources will displayed in data source available text area.

ACCE FLEACOBE Develop	DRACLE' FLEXCUBE Development Workbench for Universal Banking DEMOUSER							ER
rowser 🗸				Windows	Optio	ns S	ign Ou	ıt
action Generation					. ×	I	· 🧃	_ × \$
Action New Function Id STDCIFD Save XML Path D/RADTOOL	Block Properties	Function Type Parent Parent Function Parent Xml	Heade	n Category Maintenance Template None Template None Template None Template None Template None Template None Template None)	+ -	× 9	>
Preferences Preferences TTM_CUSTOMER TM_CUSTOMER DataBlocks DataBlocks CUSTOMER Screens Actions Culfforms LaunchForms Summary	Block Title Parent	CUUSTOMER	XSD Node Annotation Master Block We v Block Type Normal Datasource Added					

• Select the required data source and click move button to attach Data Source to the block

ORACLE FLEXCUBE Development Workbench for Universal Banking - Windows Internet Explorer										
ORACLE FLEXCUBE Develop	ORACLE FLEXCUBE Development Workbench for Universal Banking DEMOUSER						R			
Browser -						Windows	Optic	ins S	ign Ou	t
Function Generation										- ×
							×	= 1	7 🧐	4
Action New 👻		Function Type Parent	•		Function Category	Maintenance 👻				
Function Id STDCIFD		Parent Function			Header Template	None 🔻				
Save XML Path D:\RADTOOL		Parent Xml			Footer Template	None -				
Search	Block Properties							4 -	x 9	^
 Preferences DataSource STTM_CUSTOMER STTM_CUST_GROUP ListOValues DataBlocks BLK_CUSTOMER Screens FieldSets Actions CallForms LaunchForms Summary 	Block Name Block Title Parent Relation Type Block PK Fields	BLK_CUSTOMER	P≢ ▼ Available	XSD Node Annotatio Master Block Typ Block Typ Dataso STTM_CUSTOMER	n k Yes V d No V					

Fig 12.10: Attaching Data Sources to Data Block

Adding multi record data source to data block:

User on selecting Multi record Yes in data block properties all the data sources with multi record Yes will be populated. *Multi Data Source once used to one block won't available for reuse where as single record data source can be used in multiple blocks*

Select Block Fields:

- Right click on added block. Select Fields window will get opened. Developer needs to check the right side check box to add the required fields.
- **Field Name**: It should not be the same as column name .Special characters are also not allowed in the field name (including underscore and space)
- Label Code: It will be automatically populated based on field name.

rowser - notion Generation Action New -							
					Windows	Options	Sign Out
Action New -							
Action New -						😸 🗶 🔳	77 🧃
		Function Type Parent	*		Function Category Mainlenance		
Function Id STDCIFD		Parent Function			Header Templale None -		
Save XML Pain DORADTOOL		ParentXml			Fooler Template None	•	
irch	Select Fields & Add UI Fields				×	+	- 🔊 🕻
	DataSource fields UI Fields	1				-	
Preferences	DataSource lields Of Fields	,			omer		
I is STTM_CUSTOMER	Datasource STT	M_CUSTOMER -			-	<u> </u>	
STTM_CUST_GROUP ListOfValues	Column Name	Field Name	Label Code	^	• •		
DalaBlocks	CUSTOMER_NO	CUSTNO	LBL_CUSTNO		nal 👻		
BLK_CUSTOMER	CUSTOMER_TYPE	CUSTTYPE	LBL_CUSTTYPE				
Screens FieldSels	CUSTOMER_NAME1	CNAME	LBL_CNAME		led		
Actions	ADDRESS_LINE1	ADDR1	LBL_ADDR1				
CallForms	COUNTRY	CNTY	LBL_CNTY				
LaunchForms		NLTY	LBL_NLTY				
		LANG	LBL_LANG				
	V						
	£1.						
				-			
				Ok C	Cancel		


Fig 12.11: Adding Block Fields to Data Block

Refer <u>Development_WorkBench_Screen_Development-I.docx</u> for detailed explanation on data blocks and block field properties

4.5 Screens

- Right click on Screens node to add a new screen
- Screen Name should start with CVS_<Name>...
- By default screen are divided into 3 parts.
- One Main Screen is Mandatory.
- Tabs can be defined on any of the screen portions as required
- User can add sections to tabs.
- Each section can be divided into partitions.

ORACLE FLEXCUBE Development Workber	ench for Universal Banking - Windows Internet Explorer					х
ORACLE' FLEXCUBE Develop	opment Workbench for Universal Banking		D	ЕМО	JSE	R
Browser .	Wind	ows	Options	s Sig	n Out	(
Function Generation					-	- ×
			×	14	4	4
Action New -	Function Type Parent Function Category Maintenance	е 🔻				
Function Id STDCIFD	Parent Function Header Template None					
Save XML Path D:\RADTOOL	Parent Xml Footer Template None	•				
Search	Screen Details		-	- Aï	J 🌖	^
Preferences DataSource ListOfvAlues DataBlocks DataBlocks CVS_MAIN ListOfvAlueR DataBlock DataB	Screen Name CVS_MAIN Screen Screen Titte LBL_CUST Screen Size Small Exit Button Type Default Cancel			+	-	
POTER FOOTER FoldSets CallForms LaunchForms Summary	Argument Name Source Block Source Field Argument Value Target Block Target Field	eld	Acti	ve	~	



ORACLE FLEXCUBE Develop	nent Workbench for Universal Banking		Windows	DEN Options	IOUSE Sian Out	
Function Generation					_	
Action New + Function Id STDCIFD Save XML Path D:RADTOOL	Function Type Parent Parent Parent Parent Parent Xml	Function Category Maini Header Template None Fooler Template None	enance 💌			
Search	Tab Details		Dependent	Fields 🕀	- 🛛 🧐	
Preferences DataSource ListOfvalues DataBlocks CVS_HAIN HEADER	Screen Name CVS_MAIN Tab Name TAB_MAIN Tab Label Tab Type Add Section	×				
TAB_HEADER TAB_HEADER TAB_MANN FOOTER TAB_FOOTER FieldSels Actions	Section Name SEC_CUST Ok Cancel					
Califorms LaunchForms Summary						
	Fig 12.12: Creating new section in TAB MAIN in th					

Fig 12.13: Creating new section in TAB_MAIN in the body of screen CVS_MAIN

.

	t Workbench for Universal Banking						
					DEI	NOUSER	R
Browser -				Windows	Options	Sign Out	
Function Generation						-	
				:	× =	77 🧐	4
Action New -	Fund	tion Type Parent 👻		Function Category Maintenance 👻			
Function Id STDCIFD	Parent	Function		Header Template None 🔻			
Save XML Path D:\RADTOOL	P	arent Xml		Footer Template None 🔹			
Search S	Section Details					- 🛯 🌍	1
Preferences DataSource LittOValues DataBlocks Screens Screens Screens	Section Name SEC_CUST Section Label LBL_SECT Partition Details	1	☑ Visible ☑ Collapse			+-	
	Partition SI No		Partition Name	Width Sub-pa	rtitiono		
TAB_HEADER	1 PAIL	RT1		50 v	Tuuona		
🖃 🚞 TAB_MAIN		RT2		50 🗸			
E SEC_CUST						-	
TAB_FOOTER FieldSets Actions LaunchForms Summary			itions for the Sectic				

4.6 Field Sets

A group of fields can be grouped together in a Field set which can be placed together in the screen

- Field Set Name should start with FST_<>.
- Select the Block adding to field set.
- All fields available to the block will be displayed in to the data block fields text area. Move fields from data block fields to Field set fields.
- The order of fields in *field set fields* will reflect in the screen as well

	ent Workbench for Universal Banking			DEMOUSER
Browser .			Wir	ndows Options Sign Out
Inction Generation				-
				🖫 🗶 🗏 7 🧐 🖕
Action New -	Function Type Parent		Function Category Maintenan	ice 🔻
Function Id STDCIFD	Parent Function		Header Template None	•
Save XML Path D:\RADTOOL	Parent Xml		Footer Template None	-
arch	Fieldset Properties			- 🛛 🌍
 Preferences DataSource ListOVAlues DataBlocks Screens FieldSets FST_CUST1 FST_CUST2 Actions CallForms LaunchForms Summary 	Fieldset Name Fieldset Label Data Block Multi Record View Type Fieldset Height CUSTNO C	Screen Portion Tab Name Section Name Partition Name Number Of Rows	VS_MAIN	 ☐ Horizontal Fieldset ☐ ReadOnly ☐ Navigation Button ☑ Visible



Browser -	ent Workbench for Universal Banking	DEMOUSE Windows Options Sign Ou
unction Generation		- · · · · · · · · · · · · · · · · · · ·
Action New Function Id STDCIFD Save XML Path D:RADTOOL earch	Function Type Parent Parent Function Parent Xml Fieldset Properties	Function Category Maintenance Header Template None Footer Template None Kone Kon
 Preferences JataSource JataSlource JataBlocks Screens FieldSets FST_CUST1 FST_CUST2 Actions CallForms LaunchForms Summary 	Fieldset Name Fieldset Label Data Block Multi Record View Type Fieldset Height Data Block Fields NLTY NLTY NLTY	Screen Name Screen Portion Tab Name Partition Name Number Of Rows Visible Visi

• Select the screen portion (Header/Body/Footer) where this field set has to be placed. Select remaining details like tab, section and partition.

ORACLE FLEXCUBE Development Workbenc	h for Universal Banking - Windows Internet Explorer	- Are Manual Real		
ORACLE FLEXCUBE Developm	ent Workbench for Universal Banking			DEMOUSER
Browser -			Window	s Options Sign Out
Function Generation				_ ×
				🔚 🗶 🗏 🎸 🧃 🔿
Action New -	Function Type Parent	Fur	ction Category Maintenance	•
Function Id STDCIFD	Parent Function		ader Template None 🔻	
Save XML Path D:\RADTOOL	Parent Xml		ooter Template None	•
Search	Fieldset Properties	~		- 🛯 🌍 🤺
aarch Fieldset Properties Preferences DataSource ListON/alues DataBlocks Greens Fieldsets Fieldset Label Data Block BLK_CUSTOMER BLK_CUSTOMER LaunchForms LaunchForms Summary Data Block Fields CNTY LANG		Screen Name Screen Portion Tab Name Section Name Partition Name PART1 Number Of Rows FieldSet Fields CUSTNO CUSTNO CUSTNO CUSTYPE ADDR1	Subpartition Name	Horizontal Fieldset ReadOnly Navigation Button Visible

Fig 12.15: Providing details where Field Set has to be placed

Once fields are added to field set, developer can check the preview of the designed screen. Right click on Screen Name and click on Preview.

🔶 Main		
🗗 New 🖾 Enter Query		
Customer No		
Name		
Туре		
Address		
Maker	Date Time:	
Checker		
	Date Time:	Exit
Mod No	Record Status	
mourto	Authorization Status	
l		

Fig 12.16: Preview of the designed Screen

Adding Multi entry block to field set.

- On selecting a multiple block, Multi Record Property will be defaulted to Yes..
- In case of Multi record, View type can be either Single or Multiple (By Default).

◆ Main		×
🖹 New 🦻 Enter Query		
Customer No Name Type Address		
I≪ 1 of 1 🕨 🕨	Go to Page	+ - =
Group Id	Customer No Relation	
•		•
Maker Checker	Date Time: Date Time:	Exit
Mod No	Record Status Authorization Status	
1		

Below image shows a multiple view multi record field set



• For multi record single view navigation button should be checked.

	mont Morthborgh for I	niversal Banking					DEMOUR
	ment Workbench for U	niversai Bañking					DEMOUS
rowser -						Windo	ws Options Sign O
nction Generation							
							🔚 🗶 🗏 7 🔮
Action Load -		Function Type Parent 👻			Fur	ction Category Maintenance	-
Function Id STDCIFD		Parent Function			He	ader Template None 👻	
Save XML Path STDCIFD_RAI	BROWSE	Parent Xml			F	ooter Template Maint Audit	•
arch	Fieldset Proper	ties					- AI C
늘 Preferences	Fieldset Nar	ne FST_CUST2	S	creen	Name CVS_MAIN	•	🔲 Horizontal Fieldse
DataSource	Fieldset La	el 🔀	Sc	reen F	Portion Body	•	ReadOnly
STTM_CUSTOMER	Vences Fieldset Name FST_ Source Fieldset Label CUSTOMER_NO Data Block BLK CUSTOMER_NAME1 View Type Sing ADDRESS_LINE1 Fieldset Height ANTIONALITY LANGUAGE			Tab	Name TAB_MAIN	•	Navigation Button
	Multi Reco	rd Yes 👻	Se	ection	Name SEC_GROUP	•	Visible
	CUSTOMER_TYPE Multi Record Yes CUSTOMER_TYPE Multi Record Yes Single				Name PART1	•	1.
					Rows		
STTM_CUST_GROUP		Data Block Fields			Field Set Fields	Subpartition Name	
GROUP_ID						Casparation name	
CUSTOMER_NO					GROUP_ID		
Carl RELATIONSHIP					CUST_NO	•	
ListOfValues					RELATION	-	
DataBlocks			44				
BLK_CUSTOMER DELK_GROUP			44				
Screens							
🖃 🧰 CVS_MAIN							
🗉 🚞 HEADER							
BODY							
EC_CUST							
B DOTER							
i DieldSets							
FST_CUST1							
EST_CUST2							
🗁 Astiana							

6 01

Fig 12.18: Properties for Single View Multi Record Field set

🔶 Main		×
🗗 New 🤄 Enter Query		
Customer No Name Type Address		1 of 1
Group Id Customer No Relation		
Maker Checker	Date Time: Date Time:	Exit
Mod No	Record Status Authorization Status	

Below figure shows the preview of a single view multi record field set

Fig 12.18: Preview for Single View Multi Record Field set

4.7 LOV

List Of values can be defined for the function id using LOV node

- To add LOV right click on List of Values Node. LOV Name should start with LOV_<name>.
 Example: LOV_COUNTRY.
- Enter valid query and click on populate button

nction Generation							- 77	_
						×	I 77	9
Action Load -	Function Type Paren	nt 👻		Function Cate	gory Maintenance 👻			
Function Id STDCIFD	Parent Function			Header Temp	late None 👻			
Save XML Path STDCIFD_RAL BROW	/SE Parent Xml			Footer Temp	late Maint Audit 👻			
rch List	Of Values Details						- 2	<u>ai</u> 167
DataSource	LOV Name * LOV_OCUNTRY LOV Query select country_code,descrip	tion from sttm_country whe	re auth_stat = 'A	' and record_stat = 'O'	2		Decid	- 1 -
DataBlocks							Popula	ate
Screens	Query Columns Data Type	Visible Reduc	tion Field	Reduction Field Type	Reduction/Colum	in Label		
FieldSets								-
Actions								
CallForms								
🚞 Summary								

LOV	Query	×
	select country_code,description from sttm_country where auth_stat = 'A' and record_stat = 'O'	
	Ok Cancel	

Fig 12.20: Providing LOV query

Function Generation												_ ×
									×	= 1	7 🤘	⇔
Action Load 👻	F	unction Type Parent	-			Funct	ion Category Maintenance	-				
Function Id STDCIFD	Pa	rent Function				Head	der Template None 👻					
Save XML Path STDCIFD_RAL	BROWSE	Parent Xml				Foo	ter Template Maint Audit	•				
Search	List Of Values Details									-	Aï 🗳	•
Preferences DataSourcestomER STTM_CUST_GROUP ListONalues ListOValues	LOV Name * LOV_OC LOV Query select co	CUNTRY puntry_code, description	from sttm_co	ountry where auth_stat =	= 'A' and record	1_stat = 'O']			Рор	ulate	
🗄 🧰 DataBlocks	Query Columns	Data Type	Visible	Reduction Field	Reductio	n Field Type	Reduction/Colu	mn La	bel		^	
Greens FieldSets	COUNTRY_CODE	VARCHAR2 -	Yes 👻	Yes 👻	TEXT	•	LBL_CNTRY		×=			
Actions CallForms	DESCRIPTION	VARCHAR2 -	Yes 🔻	Yes 🔻	TEXT	- (LBL_COUNTRYCD		* =		+	
Summary												

Fig 12.21: Providing LOV details

- Redn/Col Labels are mandatory. If user won't provide will get error on click of LOV button after deployment in FLEXCUBE
- After defining LOV go to block and corresponding field where the LOV has to be attached.

Block Field Properties to attach LOV to the field

- **Display Type:** Select display type as Lov.
- Lov Name: Select the required Lov name from the list of all defined LOV's.
- Click on return fields tab. The result fields maintained in the LOV query will be populated on click of *Default from Lov Definition* button

- Select the desired field (and its block)to which the result of the LOV query should be defaulted
- If return field is not required to be defaulted to any field in the screen, return field value can be left blank

Function Generation Image: State				
				🗵 🗏 🎸 🧐 🗧
Function Id STDCIFD	Parent Function		Header Template None 🔻	
Search	Block Field Properties			- R 🗔 🗐
DataSource	Field Label LBL_CNTY DataSource STTM_CUSTOMER Column Name COUNTRY Data Type Varchar2 Display Type Lov Item Type Database Item Parent Field Related Field LOV Name Fieldset Name	XSD Annotation Field Size Maximum Length Minimum Value Maximum Decimals TextArea Rows TextArea Columns Default Value Value Mask Id		Visible Read Only Calender Text Popup Edit Required Uppercase Only LOV Validation Required Input by LOV Only Not Required In Xsd
		Return Fields Related Field		
				ov Definition
	Query Column			*
	COUNTRY_CODE	BLK_CUSTOMER -	CNTY -	
	DESCRIPTION	BLK_CUSTOMER -	•	

Fig 12.22: Attaching LOV to a block Field

Use of Bind Variable

If the list of values should be based on any other field value from the screen, bind variables can be used.

Example:

Define lov as shown in below query; where clause should contain condition with '?'.

SELECT cust_ac_no, branch_code, ccy from sttms_cust_account where cust_no = ? and record_stat = 'O' and once_auth = 'Y' and ac_stat_de_post = 'Y'

In the block field, after selecting return fields, click on bind variables tab. Click on **Default from Lov Definition** button. New rows will be created depending on the number of bind variable provided in the LOV query. Select the bind filed in the screen (and its block) for the LOV. Data type of the field has also to be selected.

Action Land -	Function Type Parent	14	Function Category II	antanance -		
Function Id STOCHE	Parent Function		Header Template 14	one 💌		
Save XML Path D1R4DTOOL1	Parent Xml		Footer Template	aint Audit 💌		
earch	Block Field Properties				- a) 9	,
Preferences DataSource DataSource Lov_COUNTRY DLOV_ACCOUNT DataBlods DLOV_COUNTRY DataBlods DLOV_COUNTRY DLOV_ACCOUNTRY DLOVER CUSTNO CUSTNO CUSTNO COUNTRY HANE ADDRLN1 COUNTRY HANE COUNTRY CUSTNO CUS	Field Name CUSTNO Field Label UBL_CUSTNO XSD Tag CUSTNO Display Type Text Mem Type Database flam Parent Field Parent Field Related Field Related Field Max.Decimats LOV Name LOV_ACCOUNT Fieldset Name FST_OROUP		Data Type Vanthar2 M DataSource STTME_CUST MaxLength B Field Ste Colume Name CUSTOMER_ Default Value Preview Value Accessivey Code TentArea Cols Max val Mass Id Off Live LOV Name Image Source	GROUP Popup Edit Regd GROUP Required Visible Catender Tent Select Multiple Uppercase Only ELOV Validation Regd Hist Reg In Xad Report Parameter Read Only		
FieldSets FieldSets California California LaunchiForms Summary	Custom Attributes Event Bind Variables Bind Variables Mapping Biock Name BLK_CUSTOMER	Return Fields	Bind Variable CUSTNO	7.00 M		

Fig 12.23: Defining bind variable for the LOV

4.8 Attaching Call forms

Maintenance Call forms can be attached to a maintenance screen. Refer the document <u>14-</u> <u>Development of Call Form.docx</u> for developing call forms

Attaching Call forms

- Add button to block to launch call form on button click.
 - Right click on Block
 - Select Add fields. Select fields and Add UI field's window will be launched
 - Select UI Fields tab. Click add row button. Enter button name and click ok.
 - Select display type as button and enter field label.

Se	elect F	ields & Add	UI Fields							×	\$
ſ	DataS	ource fields	Ul Fields								
										- 1	
									+-	4	
				Field Na	me	_	_	Data Type		<u>^</u>	
	V	BTM_MIS						-			
										Ŧ	
								[Ok	Cancel	
				10.04 5				L			I

Fig 12.24: Defining Button field

• Add Call form details to Call form node

							I 7	9
Action Load 👻		Function Type Parent	-	Funct	ion Category Mair	ntenance 🔻		
Function Id STDCIFD		Parent Function		Head	ier Template Non	e 👻		
Save XML Path STDCIFD_RAI	BROWSE	Parent Xml		Foo	ter Template Mair	nt Audit 👻		
ch	Call Form Details							9
i Preferences								
STTM_CUSTOMER Description: STTM_CUST_GROUP				1	creen Arguments		Fields <mark>+</mark> -	3
ListOfValues	Function ID	Parent Data Block	Parent Data Source	Relation	Relation Type	Callform Screen	Display 1 4	*
DetaBlocks	MICCUSTM	BLK_CUSTOMER -	STTM_CUSTOMER -	TTM_CUSTOMER.COSTOMER_NO =	One To One 🔻	•	Button	
ADDR1 BLA BLA ADL ADL ADL ADL ADL ADL ADL ADL ADL A								
								-

Fig 12.25: Defining details of the Call form to be attached in call form node

- Add event to button.
 - On selecting event type as call form or launch form or sub screen button will be displayed on bottom of the screen.
 - If user needs to place button position in desired place on the screen, event type should be Normal .User has to write code in release specific JavaScript file to launch the screen

Function Generation						_ >
					🔚 🗶 🔳	🞸 🍯 🔿
Action Load 👻	Function Type	Parent	-	Function Categor	y Maintenance 🔻	
Function Id STDCIFD	Parent Function			Header Template	e None 🔻	
Save XML Path STDCIFD_RAI	BROWSE Parent Xm			Footer Templat	e Maint Audit 👻	
Search	Block Field Properties				- [u 🗖 🌶
Preferences DataSource STTM_CUSTOMER STTM_CUSTOMER DataBlocks DataBlocks CUSTNO CUSTNO CUSTNO CUSTNO CUSTNO CUSTNYPE CUAME ADDR1 CUSTN CUSTYPE CUAME ADDR1 CUSTYPE CUSTNS CUSTNS CUSTNS CUSTS CUST	Field Name • BTM_MIS Field Label DataSource Column Name • Data Type • Display Type Parent Field Related Block Related Block Related Field LOV Name Off Line LOV Name Fieldset Name Custom Attributes Events Related Field	→ → → + + + + + + + + + + + + +		MIS	Required Visible Read Only Calender Popup Ed Uppercass LOV Valid. Required Input by L0 Not Requi Report Pa	Fext t Required e Only attion DV Only red In Xsd rameter
Summary Summary						Ŧ
Fig 1	2.26: Defining event to	the butt	on such that call fo	orm is linked to	the button	

• Check the preview.

🔶 Main				×
🖹 New 🦻 <u>Enter Query</u>				
Customer No Name Type Address				
I≪ 1 of 1 ▶ ▶	Go to Page		+-==	
Group Id	Customer No	Relation	A	
<		III		
MIS Change Log				
Maker	I	Date Time:		
Checker		Date Time:	Exi	t
Mod No		cord Status tion Status		

Fig 12.27: Preview of the screen with the Call Form button

4.9 Adding Summary

1) Add entry in Preferences node for Summary screen

					X	I 7	7 🧐	
Action Load 👻	Function Ty	pe Parent 👻		Function Category Maintenance 🔻				
Function Id STDCIFD	Parent Functi	on		Header Template None 👻				
Save XML Path STDCIFD_RAI	ROWSE Parent X	ml		Footer Template Maint Audit	•			
arch P	Preferences						Ľ,	9
Preferences	Fead Office Fur	nction	Module	ST				
DataSource STTM CUSTOMER	🔽 Logging Requir	red	Module Description	Static Maintenance				
STIM_COSTOMER STIM_CUST_GROUP	Auto Authorizati	on	Branch Program Id					
ListOfValues	Tank Modificatio	ons	Process Code					
🗉 🧰 DataBlocks	Field Log Regu	ired	SVN Repository URL					
BLK_CUSTOMER	Multi Branch Ac		Transaction Block	Choose Block 🗸				
CUSTNO	Excel Export Re		Name					
	Excer Export Re	quirea	Transaction Field	Choose Field 🔹				
CNAME			Name					
					Control	String +		
Canal Lang					Control	uning 🛨		
DTM_MIS	Function Id		Module *	Module Description			^	
BLK_GROUP	STDCIFD	ST	*=	Static Maintenance				
CVS_MAIN	STSCIFD	ST	12	Static Maintenance				
FieldSets		Щ е т.			_		-	
Actions							*	
CallForms								
aunchForms								
Carl Summary								

- 2) Click on Summary Node.
 - Enter Summary title .Select label code from lov.
 - Select Data Block master block and summary blocks will be displayed. Select required block from drop down list.
 - Select Data Source for summary.
 - Select Summary Type.
 - Select Summary Screen size.
 - Enter if any where clause is required.
 - Enter Default order by if required.
 - Enter Multi Branch where clause if required.
 - Attach the fields required in the summary result grid
 - If the field is required as part of filtering, query has to be checked for the particular field
 - Provide the position of fields in Result grid and Summary Query set .

Action Load -		Function Type Parent Parent Function	-			Header	Category Maintenance				
	ROWSE Summary Details	Parent Xml				Footer	Template Maint Audit	•		[a 9
Preferences DataSource DataSourc	Title Data Blocks Data Source Summary Type Summary Screen Size	BLK_CUSTOMER STTM_CUSTOMER Summary Medium	× • •		Default Where Clause Default Order By Multi Branch Where Clause Main Summary Screen	└ WebSer Require	vices d		0		_
CNAME ADDR1 CONTY NLTY	Data Block Fields Cu	stom Buttons Fields Ordering Data Block Fields			Fields Selected	Query	LOV Name				
CANG					CUSTNO			•			
BLK_GROUP Screens					CNAME			-			
CVS_MAIN					CUSTTYPE			–			
i FieldSets					ADDR1			*			
CallForms			<	< □				_			
					NLTY			_			
CaunchForms					LANG						

Summary Preview

Right click on summary node and click on preview.

	auto Quesu C t Advence	d Search O Bee	et D Clear All							×
EX EXE	Advance Advance Advance Authorization Status Customer No	v search +5 Kes			Reco	ord Status	•			
Reco	rds per page 15 👻 📊	🛾 1 of 1 🕨 🔰		2						*
	Authorization Status	Record Status	Customer No	Name	Туре	Address	Country	Nationality	Language	
										E
										-
•									Þ	Ē
									Exit	

Fig 12.29: Summary Screen Preview

4.10 Amendable fields Maintenance

Amendable Fields

If user needs to modify data of a particular field on unlock, in Workbench developer has to maintain fields as amendable.

- Click ACTIONS node.
- Click on Amendables button next to the action for which the field has to be made amendable
- Select the fields in each block which user can modify for the selected action.

ndable DetailsQUERY		
Data Blocks	DataBlock Fields	;
JSTOMER ROUP	New Allowed Delete Allowed All I	Records 🔲 Mandatory
	Field Name	Amendable
	CUSTNO	
	CUSTTYPE	
	CNAME	
	ADDR1	
	CNTY	
	NLTY	
	LANG	
	BTM_MIS	
		Ok Cance

Fig 12.30: Maintaining amendable fields

5. Generation and Deployment of files

Generate Files

• Click on generate button select the required files to generate and click on Generate button.

ation		×	4	lela Data	Others	
Error Description Request successfully Processed		Error Code RD-SAVE-007	Menu Details Dalasource Details Dalasource Details Dolasource Details Dolasource Details Druction Call Forms Block Details Screen Delails Notification Details		Xsds Xsds Xsd Wih Annotations Screen Html Upload Table Trigger Upload Tables Definition	
		0% of DownLoadFile from 10.184	.132.100 Completed	nction Parameters	Archive Table Definition	
		File Download		X Hyb Levens		
		Do you want to open or sa	ve this file?			
		Name: RAD.ZIP Type: WinRAR ZIP archive From: 10.184.132.100 Open Save Cancel		ые Туре	Status	
					Generated 👻	
					Generaled *	
					Generated 💌	
					Generaled *	
STOCIFDCVS_MAINTAB_FOOTER html slpks_stdold_main.spc		While files from the Internet can be useful, some files can potentially harm your computer. If you do not trust the source, do not open or save this file. <u>What's the risk?</u>		ally	Generated 👻	
				x'	Generaled *	
	stpks_sldclfd_kernel.spc				Generated 👻	
	slpks_stdcifd_main.sql		SQL	-	Generaled *	
	stpks_sldclfd_kernel.sql		SOL		Generated 👻	
	CSTB_FIELD_LABELSSTDCIFD.INC		INC		Generaled +	
	CSTB_OTHER_LABELSSTDCIFD INC		INC		Generated 👻	
	CSTB_FID_CALLFORMSSTOCIFD.INC		INC		Generaled *	

Fig 12.30: Generation of Files

Deploy files

• Click on deploy button select the required files to deployed to server and click on deploy. On successful deployment status will be displayed as Deployed.


Front-End Files	System Packages	Hook Packages	M	leta Data	Others	^
Rad/ML Ø Screen Xml Ø System JS	Main Package Spec Main Package Body Notification Triggers Upload Package Spec Upload Package Body	Kernel Package Spec Kernel Package Body Cluster Package Spec Cluster Package Body Custom Package Spec Custom Package Body	Menu Details Datasource Details Ot Details Block Details Screen Details Amendable Details Call form Details Summary Details	Label Details Jelock PK Columns Function Call Forms Gateway Details Notification Details Function Parameter Purge Details	Upload Table Trigger	Ţ
	CSTB_FIELD_LABELSSTDCIFD.INC		INC		Deployed -	*
	CSTB_OTHER_LABELSSTDCIFD.INC		INC		Deployed -	
	CSTB_SUMMARY_INFOSTDCIFD.INC		INC		Deployed -	
;	STTB_AUDIT_PK_COLSSTDCIFD.INC		INC		Deployed -	
	CSTB_FID_DATA_BLOCKSSTDCIFD.INC		INC		Deployed -	
	CSTB_FID_DATA_SOURCESSTDCIFD.INC		INC		Deployed -	
	CSTB_FID_SCR_TABSSTDCIFD.INC		INC		Deployed -	=
0	CSTB_FID_SCREENSSTDCIFD.INC		INC		Deployed -	
1	SMTB_MENUSTDCIFD.INC		INC		Deployed -	
2	SMTB_ROLE_DETAILSTDCIFD.INC		INC		Deployed -	
3	SMTB_FUNCTION_DESCRIPTIONSTDCIFD.INC	;	INC		Deployed -	
4	SMTB_FCC_FCJ_MAPPINGSTDCIFD.INC		INC		Deployed -	
5	STDCIFD RAD.xml		RAD	DXMI	Generated ~	-

Fig 12.30: Deployment of Files

Testing

•

- Launch the screen from FLEXCUBE
- Try sample operations on the screen (NEW, MODIFY, QUERY etc)



6. Generated Units

The following units will be generated for a Maintenance screen.

Refer document <u>Development_WorkBench_Screen_Development-II.docx</u> for detailed explanation on the same

6.1 Front End Units

6.1.1 Language xml

This file is an XML markup of presentation details, for the designed Call Form specific to a language.

6.1.2 SYS JavaScript File

This JavaScript file mainly contains a list of declared variables required for the functioning of the screen

6.1.3 Release Type Specific JavaScript File

This file won't be generated by the Tool. It has to be manually written by the developer if he has to write any code specific in that release

6.2 Data Base Units

6.2.1 Static Scripts

The following static scripts generated are required for the proper functioning of a Call Form screen. Refer document on generated units for detailed explanation

i) Menu Details

Scripts for SMTB_MENU and SMTB_FCC_FCJ_MAPPING, SMTB_ROLE_DETAIL, SMTB_FCC_GCJ_MAPPING are required for the functioning of Maintenance screen

- ii) Lov Details
- iii) Amendable Details
- iv) Label details
- v) Screen Details
- vi) Block details
- vii) Data Source Details
- viii) Call form details
- ix) Summary Details

6.2.2 System Packages

The Main Package contains the basic validations and backend logic for the Maintenance function id. The Main package contains the mandatory checks required. It will also contain function calls to the other packages generated by Workbench.

The main package has the below stages for a maintenance form:

- Converting Ts to PL/SQL Composite Type
- Checking for mandatory fields
- Defaulting and validating the data
- Writing into Database
- Querying the Data from database

• Converting the Modified Composite Type again to TS

Each of these stages has a 'Pre' and 'Post' hooks in the Kernel, Cluster and Custom Packages. And these Hooks are called from the Main Package itself

Main Package has the system-generated code and should not be modified by the developer Kernel, Cluster and Custom Packages are the packages where the respective team can add business logic in appropriate functions using the Pre and Post hooks available

6.2.3 Hook Packages

Release specific packages will be generated based on the release type (KERNEL.CLUSTER or CUSTOM). Developer can add his code in the release specific hook package.

The Main Package has designated calls to these Hook Packages for executing any functional checks and Business validations added by the user. The structure for all the Hook Packages are the same, like:

Fn_Post_Build_Type_Structure Fn_Pre_Check_Mandatory Fn_Post_Check_Mandatory Fn_Pre_Default_and_Validate Fn_Post_Default_and_Validate Fn_Pre_Upload_Db Fn_Post_Upload_Db Fn_Pre_Query Fn_Post_Query

These Functions are called from the Main package using the Pre and Post Hooks available in the Main Package. The 3 Hook Packages namely Kernel, Cluster and Custom Packages have similar structure and are for the respective teams to work on.

6.3 Other Units

6.3.1 Xsd

Xsd 's will be generated if gateway operations are required for the particular function id. Maintenance for the same has to be done in *Actions* node

7. Extensible Development

Developer can add his code in hook packages and release specific JavaScript file.

7.1 Extensibility in JavaScript Coding

For release specific JavaScript coding, code has to be written in release specific JavaScript

file.

It follows the naming convention as : (Function Id)_(Release Type).js *Example: Code in STDCIFD_CLUSTER.js is exclusive to cluster release*

This JavaScript file allows developer to add functional code and is specific to release.

The functions in this file are generally triggered by screen events. A developer working in cluster release would add functions based on two categories:

- Functions triggered by screen loading events *Example: fnPreLoad_CLUSTER(), fnPostLoad_CLUSTER()*
- Functions triggered by screen action events *Example: fnPreNew_* CLUSTER (), *fnPostNew_* CLUSTER ()

7.2 Extensibility in Backend Coding

Release specific code has to be written in the Hook Packages generated.

7.2.1 Functions in Hook Packages

Different functions available in the Hook Package of a Maintenance Form are:

- 1) Skip Handler : Pr_Skip_Handler This can be used to skip the logic written in another release. *Example: logic written in KERNEL release can be skipped in CLUSTER release*
- 2) Fn_post_bulid_type_structure If any change has to be made in the field values obtained from the form befor start of processing, code can be written here
- 3) Fn_pre_check_mandatory
- 4) Fn_post_check_mandatory

Any extra mandatory checks on the field values from the screen can be written here.

- 5) Fn_pre_query
- 6) Fn_post_query

Any specific logic while querying can be written in these functions. It is called from fn_query of the main package

- 7) Fn_pre_upload_db
- 8) Fn_post_upload_dbAny logic while uploading data to tables can be written here .

9) Fn_pre_default_and_validate

10) Fn_post_default_and_validate

Any release specific logic for defaulting and validation can be written here . It is called from the fn_default_and_validate in the main package

7.2.2 Flow of control through Hook packages

The flow of control through the Hook Packages for a particular stage is as explained in the figure below





Fig 12.31: Flow of control through Hook Packages



7.2.3 By passing Base Release Functionality

There are auto generated functions like FN_SKIP_<RELEAE_TYPE> which would determine whether or not a particular hooks needs to be called.

Developer also has an option to bypass the base release hook if need be. For example if the validations written in *STPKS_STDCINF_KERNEL.FN_PRE_CHECK_MANDATORY* are not required or not suitable for the Cluster release, system provides an option to bypass the code written by Kernel team. Similarly a Custom release can also bypass the code written by Kernel and Custom Releases. This can be achieved by calling procedures

PR_SET_SKIP_<RELEASE_TYPE> and *PR_SET_ACTIVATE_<RELEASETYPE>*. These procedures will be made available in the main package and the development teams of Customization teams can use these procedures to skip and re-activate the hooks of parent release.

The Developer should avoid adding validations or Checks in the Pre Stage of any function, like Fn_Pre_Check_Mandatory, etc and should aim to add all the validations in the Fn_Post_Default_and_Validate.

For Example let us see the flow for the Mandatory Stage for STDCIFD:




Fig 12.31: Flow of control explaining skip logic in pacakges



Development of Maintenance Form [Nov] [2021] Version 14.5.3.0.0

Oracle Financial Services Software Limited Oracle Park Off Western Express Highway Goregaon (East) Mumbai, Maharashtra 400 063 India

Worldwide Inquiries: Phone: +91 22 6718 3000 Fax:+91 22 6718 3001 www.oracle.com/financialservices/

Copyright © 2007, 2021, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.