

# JD Edwards EnterpriseOne

---

**Deploying JD Edwards  
EnterpriseOne on Oracle Cloud  
Infrastructure on Linux with DBS  
Learning Path**

1.0



Copyright © 2025, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

# Contents

<b>Preface</b>	<b>i</b>
<hr/>	
<b>1 Introduction</b>	<b>1</b>
Overview	1
Before You Begin	1
<b>2 Planning Your Deployment</b>	<b>9</b>
Minimum Resource Requirements	9
Understanding Port Restrictions	10
Creating a Pre-Installation Worksheet	11
Generating Secure SHell (SSH) Key Pairs on Your Local System	13
<b>3 Performing Setup Tasks in Oracle Cloud Infrastructure</b>	<b>15</b>
Logging into Oracle Cloud Infrastructure	15
Creating a Compartment	15
Creating a Group	16
Creating a User	16
Adding Users to Groups	17
Creating a Policy	18
Creating a Virtual Cloud Network	19
Creating Rules for a VCN Security List	20
<b>4 Creating Linux Instances in Oracle Cloud Infrastructure</b>	<b>23</b>
Creating the Linux Instance for the One-Click Provisioning Server	23
Creating Linux Instances as VMs in Oracle Cloud Infrastructure	30
<b>5 Creating Volume Storage</b>	<b>33</b>
Using Volume Storage	33
<b>6 Configuring the Linux Servers</b>	<b>35</b>
Performing Common Setup for All Linux Servers	35

Setting Up the Enterprise Server	46
Setting Up the WebLogic Server	47
<b>7 Configuring the Database</b>	<b>51</b>
Creating DB Systems in Oracle Cloud Infrastructure	51
Setting Up a DB System	57
Setting Up a DB System with RAC	66
<b>8 Preparing the Microsoft Windows Deployment Server</b>	<b>77</b>
Creating a Windows VM in Oracle Cloud Infrastructure	77
<b>9 Configuring the Microsoft Windows Deployment Server</b>	<b>81</b>
Logging in to the Windows VM	81
Running Commands to Change Microsoft Windows Settings	86
<b>10 Using the One-Click Provisioning Server</b>	<b>97</b>
Configure CA Certificates for One-Click UI (Optional)	97
Accessing the JD Edwards Provisioning Console	98
Configuring the Server Manager Account	100
Configuring the Server Manager Account	100
<b>11 Creating a Deployment Plan</b>	<b>105</b>
Orchestrating a Quick Start Deployment Plan	105
Orchestrating Using Quick Start Mode	105
Orchestrating an Advanced Deployment Plan	128
Orchestrating Using Advanced Mode	128
<b>12 Deploying JD Edwards EnterpriseOne</b>	<b>155</b>
Deploying an Orchestration	155
Deploying an Orchestration	155
Orchestrating an Advanced Deployment Plan by Adding Web Servers and Enterprise Servers Post Deployment	160
<b>13 Saving and Reusing Deployment Plans</b>	<b>163</b>
Exporting an Orchestration	163

---

Importing an Orchestration	165
<b>14 Configuring JD Edwards Components Post Deployment</b>	<b>169</b>
Deployment Server	169
Standalone Deployment Server	173
Development Client	175
CA Certificates	175
<b>15 Accessing the Provisioned Servers</b>	<b>177</b>
Performing Post Provisioning Tasks	177
Accessing the JD Edwards EnterpriseOne Servers Using Their Public IP Addresses	180
<b>16 Troubleshooting Your One-Click Deployment</b>	<b>187</b>
Troubleshooting	187
Regenerating and Reinstalling Self-Signed Certificates for One-Click Provisioning	193
<b>17 Performing Basic Administration</b>	<b>201</b>
Starting and Stopping Services	201
Configuring the Public IP Address as an Internal Hostname on Client Machine	201
<b>18 Considering Optional Administrative Tasks</b>	<b>203</b>
Understanding JD Edwards EnterpriseOne Security	203
Configuring AIS Server Depending on How You Manage Users	203
Updating the Java.security File (Optional)	204
Using the Linux Logical Volume Manager (LVM) to Manage Free Disk Space	205
<b>19 Upgrading Your One-Click Provisioned Environment</b>	<b>213</b>
Upgrade Learning Path	213



# Preface

Welcome to the JD Edwards EnterpriseOne documentation.

## Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

## Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

## Related Information

For additional information about JD Edwards EnterpriseOne applications, features, content, and training, visit the JD Edwards EnterpriseOne pages on the JD Edwards Resource Library located at:

<http://learnjde.com>

## Conventions

The following text conventions are used in this document:

Convention	Meaning
<b>Bold</b>	Boldface type indicates graphical user interface elements associated with an action or terms defined in text or the glossary.
<i>Italics</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<b>Monospace</b>	Monospace type indicates commands within a paragraph, URLs, code examples, text that appears on a screen, or text that you enter.
<b>&gt; Oracle by Example</b>	Indicates a link to an Oracle by Example (OBE). OBEs provide hands-on, step-by-step instructions, including screen captures that guide you through a process using your own environment. Access to OBEs requires a valid Oracle account.



# 1 Introduction

## Overview

This learning path describes how to deploy JD Edwards EnterpriseOne Release 9.2 using One-Click Provisioning on the Oracle Cloud Infrastructure with Linux using an Oracle Database. It is important to note that this document is primarily concerned with the basic requirements for an installation of JD Edwards EnterpriseOne on the Oracle Cloud Infrastructure. It is not intended as a blueprint for operations in environments such as Development, Test, or Production.

Upon completion of this learning path, you will have a working deployment of JD Edwards EnterpriseOne on Linux in Oracle Cloud Infrastructure with a database running in DB Systems (DBS). This process includes the post-installation tasks and the administration of your deployment.

### Oracle Support

You can accelerate your provisioning to Oracle Cloud Infrastructure and streamline your process with Oracle Support by entering a planning Service Request (SR) before you start the provisioning process on Oracle Cloud Infrastructure (OCI). Details on how to open the Service Request are on “My Oracle Support, E1: OCI: How to Open A Service Request (SR) For An Oracle Cloud Infrastructure Planning Session” (Doc ID [2348382.1](#)).

### Oracle Cloud Infrastructure User Interface

The user interface for the Oracle Cloud Infrastructure is constantly evolving. As a result, the screens depicted in this tutorial may not exactly coincide with the current release. This tutorial is routinely updated to include any functional changes to the JD Edwards EnterpriseOne implementation process on the Oracle Cloud Infrastructure. When such updates are made, any differences between the screens in the tutorial and the user interface are reconciled.

## Before You Begin

This section provides information and resource requirements critical to understand prior to using One-Click Provisioning on Oracle Cloud Infrastructure.

## Fundamentals

You can use the Oracle Cloud Infrastructure (also called "IaaS" - Infrastructure as a Service) to deploy JD Edwards EnterpriseOne using the JD Edwards EnterpriseOne One-Click Provisioning Server. This server features a web-based JD Edwards Provisioning Console interface that enables the provisioning of a fully functional suite of interconnected servers within Oracle Cloud Infrastructure. The required core servers are the Database Server (either as an Oracle Cloud Infrastructure Compute instance, as an Oracle Cloud Infrastructure database service, or as an Oracle Autonomous Database), the Enterprise Server, the HTML Web Server, and the Application Interface Service (AIS) Server. The One-Click Provisioning Server includes the JD Edwards Server Manager Console (SMC). One-Click Provisioning will also deploy the required Deployment Server into a Microsoft Windows environment.

All servers running in the Oracle Cloud Infrastructure are virtual machines (VMs) that are functionally equivalent to their non-VM physical on-premises machine counterparts.

For all servers you should use the highest version available that is specified in the Oracle Certifications for JD Edwards EnterpriseOne for One-Click Provisioning.

The following servers can be deployed by One-Click Provisioning:

- One or more Database Servers either in Compute or as an Oracle Cloud Infrastructure database service
- One or more Enterprise Servers
- One or more Standard JAS Servers (as standalone instances within WebLogic, not clustered)
- One or more Dedicated HTML Servers (as standalone instances within WebLogic, not clustered)
- One or more AIS Servers (as standalone instances within WebLogic, not clustered)

**Note:** One-Click Provisioning for Oracle Cloud Infrastructure only supports the deployment of each JD Edwards EnterpriseOne server in a separate VM. You cannot combine all the servers into a single VM instance or server, nor can you combine multiple servers into a single VM instance.

Prior to deploying the web components using One-Click, users must separately install their own licensed version of WebLogic Server. This learning path includes the prerequisites for WebLogic setup for use with JD Edwards EnterpriseOne.

One-Click provisioning can only deploy this machine into a Microsoft Windows Server:

- A single Deployment Server

**Note:** For Linux systems, to maintain optimal performance, the Microsoft Windows environment must reside in the same Availability Domain (AD) in an Oracle Cloud Infrastructure Region as the companion Linux-based servers. You must have a Deployment Server to apply ESUs (updates), perform Package Builds and commit to future upgrades.

**Note:** For Cloud implementations, it is imperative that you reuse the SSH key created for your Oracle Compute Cloud Service account for all deployments of JD Edwards EnterpriseOne. Otherwise, any subsequent SSH key creation may cause any previously provisioned instances to be orphaned.


## Standard JAS and Dedicated HTML for AIS Servers

Beginning with One-Click Provisioning based on JD Edwards Tools Release 9.2.5, the JD Edwards EnterpriseOne One-Click architecture for HTML and AIS Servers introduces the concept of Standard JAS and Dedicated HTML for AIS Servers.

Using Quick Start Mode, users are required to select a single HTML Server that is dedicated to a specific AIS Server.

Using Advanced Mode, in addition to configuring additional Dedicated HTML and AIS server pairs, users can add a Standard JAS Server that is not dedicated to an AIS Server. A Standard JAS Server functions as a traditional HTML Server handling all non-AIS requests. To scale by pathcode, multiple pairs of HTML and AIS servers can be configured. Likewise, multiple Standard JAS Servers can be configured for use with or without load balancers. Using one or more Standard JAS Servers is recommended for Production environments.

The following diagram depicts the architecture and following that is a description of the characteristics of each Standard JAS, Dedicated HTML, and AIS server.



- **Standard JAS Server**

■ **Note:** The Standard JAS Server can only be deployed using the Advanced Mode.

Referencing the architecture diagram, the Standard JAS Server is JAS 1 and has these characteristics:

- Can be load balanced (using LBaaS or other)
- Configured for one-way communication to a specific Enterprise Server (ENT 1)
- Configured with one-way communication to an AIS Server (AIS 1)

- Not paired with an AIS Server to perform AIS runtime
- Not configured to communicate with the Dedicated HTML Server for AIS (HTML\_AIS 1)

- **AIS Server**

Referencing the the pod architecture diagram, the AIS Server is AIS 1 and has these characteristics:

- Can be load balanced (using LBaaS or other)
- Paired with a Dedicated HTML Server for AIS (HTML\_AIS 1)
- Configured for two-way communication with both an Enterprise Server (ENT 1) and, for AIS runtime, to the Dedicated HTML Server for AIS (HTML\_AIS 1)

- **Dedicated HTML Server for AIS**

**Note:** The Quick Start mode can only deploy a single Dedicated HTML Server for AIS. You must use the Advanced Mode to deploy a Standard HTML Server.

Referencing the the pod architecture diagram, the Dedicated HTML Server for AIS is HTML\_AIS 1 and has these characteristics:

- Cannot be load balanced (using LBaaS or other)
- Paired to a specific AIS Server (AIS 1)
- Configured for one-way communication with an Enterprise Server (ENT 1)
- Configured for two-way communication with a specific AIS Server (AIS 1) for AIS runtime.

## Standalone Deployment Server


You can use Advanced Mode to install a Standalone Deployment Server, which is usually defined as part of the required workflow during Quick Start mode. Using this optional flow you can provision Deployment Server by itself without having to orchestrate any other server. However, you must ensure that you know the exact host name of the core JD Edwards EnterpriseOne servers that are, or will be, in the same environment as the Standalone Deployment Server. These core servers include the Database Server, Enterprise Server, HTML Server, and AIS Server. It is not necessary that of any of these core JD Edwards EnterpriseOne servers exists at the time of orchestrating the Standalone Deployment Server. At any time prior or subsequent to the deployment of a Standalone Deployment Server, you can orchestrate the core JD Edwards EnterpriseOne servers. After you have deployed a Standalone Deployment Server, you must ensure that you perform the procedures in the OBE of this Learning Path entitled: ***Performing Post Installation for the Standalone Deployment Server.***

## Server Manager Console Centralized Configuration

As part of One-Click Provisioning, Centralized Configuration in the Server Manager Console is enabled automatically. One-Click adds the server group specific INI settings when provisioning individual servers. Post provisioning, the administrator is responsible for applying the group changes on the Centralized Configuration enabled environments.

## Process Flow

The following is a process flow diagram for One-Click Provisioning on Oracle Cloud Infrastructure.



## Supported Software Versions

The following table lists the supported software versions for Oracle and Microsoft components running on Oracle Cloud Infrastructure:

Supported Software Versions	
Operating System	
- Provisioning Server	Oracle Enterprise Linux 9.6
- Oracle Database Server in Compute	Oracle Enterprise Linux 9.6
- Oracle Database Server in DB Systems	Oracle Enterprise Linux 8.10 (Oracle 26ai: current, subject to change)
- Oracle Autonomous Database	Autonomous Transaction Processing on Dedicated Exadata Infrastructure - Version 26ai
- Enterprise Server	Oracle Enterprise Linux 9.6
- Oracle WebLogic Server	Oracle Enterprise Linux 9.6
- Deployment Server	Microsoft Windows Server 2022
Oracle Database	Oracle 19C (Compute Database)  Oracle 26ai (Database System, Oracle Autonomous Database)
Oracle WebLogic Server	14.1.1.0
Oracle WebLogic Server Patches for 14.1.1.0	p28186730, p38412913  Tip: You can verify your patch level running this command from the <OH>/OPatch location on your WebLogic Server:  <code>./opatch lspatches</code>
Java Development Kit (JDK) (Required for Oracle WebLogic Server)	Version 1.8.0 up to Update 471
Load Balancer (Optional)	OCI Load Balancer
JD Edwards EnterpriseOne One-Click System	Tools Release 9.2.26.1 64-bit  ESU up to JN21495

UDO up to UDO\_9.2\_10719 + UN26\_UDO\_Bundle

Planner JN21409

Data Pack is DP0289201

## Prerequisite Knowledge and Skills

You must have a fundamental understanding of the Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at the sites:

- [Oracle Cloud Infrastructure](#)

## Prerequisite Tools and Resources

You must obtain the PuTTY tool (<http://www.putty.org>) for generating SSH key pairs on the client machine that you will use to connect to any Linux server deployed by One-Click Provisioning.



# 2 Planning Your Deployment

## Minimum Resource Requirements

The table below specifies the minimum resource requirements to install and run JD Edwards On-Premises using an Oracle database (Linux and Microsoft Windows) or a Microsoft SQL Server database (Microsoft Windows). Your environment may require additional resources based on transaction volumes, number of users, availability requirement, integrations, and business requirements.

**Note:** For implementation of JD Edwards EnterpriseOne on Oracle Cloud Infrastructure, users can choose any Shape Series that provides:

- x86-compatible processors (such as Intel and AMD). Support for RISC (reduced instruction set) processors (such as ARM) is specifically excluded.
- Minimum of 2 OCPUs
- Minimum of 30 GB memory per OCPU

**Note:** Within the **Specialty and previous generation** shape series, only these shapes are supported:

- VM.Standard2.2
- VM.Standard2.4
- VM.Standard2.8
- VM.Standard2.16
- VM.Standard2.24

JD Edwards EnterpriseOne Server Type	Minimum Recommended			Notes
	CPU	Memory (GB)	Storage Volume (GB)	
<b>Required JD Edwards Components</b>				
One-Click Provisioning Server	2	30	100	Includes Server Manager
Deployment Server	2	30	210 GB* for all four (4) pathcodes	Using One-Click, customers must install all four (4) path codes. There is no automated way to add additional path codes post deployment.

				* Storage volume space is in addition to that required by the Windows OS itself, which can be up to 45 GB. Therefore, the minimum recommended storage volume size is 256 GB.
Database Server	2	30	50 GB for a single pathcode and shared data	20 GB is required for each additional pathcode. These numbers are for demo data only and should be adjusted for expected required business data space.
Enterprise Server	2	30	75	
WebLogic Server	-	-	30	For the OS and WebLogic Server
<ul style="list-style-type: none"> <li>• HTML Server for Web Client</li> </ul>	2	30	20	Per Web Instance
<ul style="list-style-type: none"> <li>• HTML Server for AIS Server</li> </ul>	2	30	20	Per Web Instance
<ul style="list-style-type: none"> <li>• AIS Server</li> </ul>	2	30	20	Per Web Instance
<b>Optional JD Edwards Components</b>				
Business Services Server (BSSV)	2	30	50	Per Web Instance
Transaction Server for Real Time Events (RTE)	2	30	50	Per Web Instance
Application Development Framework Server (ADF)	2	30	50	Per Web Instance
One View Reporting (OVR) Server / BI Publisher Server (BIP)	2	30	50 GB is required for a single pathcode	10 GB is required for each additional pathcode
Development Client	2	30	100	Per each Development Client installation

**Note:** Optional components are not deployed by One-Click. However the Web Components can be manually added through Server Manager and the Development Client can be added in a new Microsoft Windows instance using the traditional on-premise methodology.

## Understanding Port Restrictions

This section provides an overview of the restricted ports that cannot be defined or used while creating any web component or server, or both. You should be aware of the restricted ports that cannot be defined or used while creating any web component or server, or both.

The specific port restrictions for any One-Click Provisioning deployment of JD Edwards EnterpriseOne are grouped as follows:

- One-Click Provisioning Console for JD Edwards
- All Internet Browsers
- Google Chrome and Mozilla Firefox Browsers

### One-Click Provisioning Console for JD Edwards

- Any port below 1024 is restricted.

### All Internet Browsers

The following are restricted ports enforced by the rules of any internet browser:

- 2049
- 4045
- 6000

### Google Chrome and Mozilla Firefox Browsers

In addition to the above mentioned restricted ports for any internet browser, the Google Chrome and Mozilla Firefox browsers block specific ports which they deem as unsafe to use on HTTP/HTTPS protocol. These restricted ports are:

- 3659, // apple-sasl / PasswordServer
- 6665, // Alternate IRC [Apple addition]
- 6666, // Alternate IRC [Apple addition]
- 6667, // Standard IRC [Apple addition]
- 6668, // Alternate IRC [Apple addition]
- 6669, // Alternate IRC [Apple addition]

**Note:** It may be possible to configure Chrome and/or Firefox to change these restrictions.

## Creating a Pre-Installation Worksheet

Machine	IP Address
Provisioning Server and Server Manager (same machine)	https://___.___.___.__:3000 where <b>https</b> is the only supported browser protocol, and  where <b>3000</b> is always the port, which you must include as part of the address
Machine	Hostname
Database Server in Compute or a DB System	

Autonomous Database (ADB)	ADB Admin User Password: _____  ADB WALLET: _____  Auth Token of User: _____  Tenancy: _____  Username: _____  Region: _____  Bucket: _____
HTML Server	
AIS Server	
Deployment Server	Hostname: _____  Location Name: _____

**Note:**

Do not use a fully qualified domain name for host names; you should only specify the first node of the domain name.

**For the Database, Enterprise, and Deployment Servers**, machine names are limited to a maximum of 15 **lower-case** alphanumeric characters as limited by the JD Edwards EnterpriseOne database table and application design.

**For all servers**, you cannot use special characters in the name, such as an underscore “\_”. The user interface will enforce this restriction.

User Account	Password
oracle	These users do not have a login password. Access is through SSH Keys only, logging in using the username <b>opc</b> . Enter SSH Key names here.
jde920	
em_manager_user	
sys, system	
weblogic	

JDE	
jde_admin	
Initial Windows Machine Administrator (temporary)	
Site Key Passphrase	
Server Manager Console	
SQL DB User (SA)	
<p><b>Note:</b> This is only applicable to Oracle Cloud Infrastructure with Microsoft Windows and On-Premises Microsoft Windows with SQL Server database.</p>	
<p><b>Note:</b> The password for <b>any</b> Windows user on <b>any</b> Windows machine must not contain the \$ or ! characters; using these characters violates the Oracle password policy and will result in denied access.</p>	

## Generating Secure SHell (SSH) Key Pairs on Your Local System

This section outlines the requirement to generate SSH key pairs on your local system, which can be UNIX or Windows.

**Note:** All references to UNIX also apply to Linux.

If you already have an SSH key pair, you may use that to connect to your environment whether it is running On-Premises or in Oracle Cloud Infrastructure.

**Tip:** The best practice is to create at least two SSH keys, a primary and a backup, because if for any reason an SSH Key is no longer valid, access to the instance or machine would be lost with no means to recover the access. A user cannot access an instance or machine without using an SSH Key.

For instances in Oracle Cloud Infrastructure, it is recommended you use the Oracle Cloud Shell to interface with a Oracle Cloud Infrastructure instance. Oracle Cloud Shell is browser-based, does not require installation or configuration of

---

anything on your laptop, and works independently of your network setup. The below referenced Oracle documentation for generating SSH keys provides instructions for these options:

- Oracle Cloud Shell
- Apple MacOS
- Microsoft Windows 10
- Prior Microsoft Windows Versions
- SSH Keys for Linux

Refer to this Oracle tutorial that describes the process to generate an SSH key pair for Oracle Compute Cloud Service instances. Fundamentally, you can use these same procedures for On-Premises environments.

*Generate SSH keys*

# 3 Performing Setup Tasks in Oracle Cloud Infrastructure

## Logging into Oracle Cloud Infrastructure

### Supported Browsers

Oracle Cloud Infrastructure supports the latest desktop versions of Google Chrome, Microsoft Edge, Internet Explorer 11, Safari, Firefox, and Firefox ESR. Note that private browsing mode is not supported for Firefox, Internet Explorer, or Edge. Mobile browsers are not supported.

To sign in to Oracle Cloud at <https://cloud.oracle.com>, you need:

- User name and password
- Your cloud account name

When your tenancy is provisioned, Oracle sends an email to the default administrator at your company with the sign-in credentials and URL. This administrator can then create a user account for each person who needs access to Oracle Cloud Infrastructure. Check your email or contact your administrator for your credentials and account name.

### Signing In for the First Time

Links for signing in are also provided in your welcome email.

1. Open a supported browser and go to <https://cloud.oracle.com>.
2. Click **Sign In**.
3. Enter your **Cloud Account Name** and click **Next**.
4. Enter your user name and temporary password from your welcome email. You will be prompted to change your temporary password.

After you sign in, the Console Home page is displayed.

### About the Console URL

Alternatively, you can sign in directly to Oracle Cloud Infrastructure using the Console URL. When you sign up to use Oracle Cloud Infrastructure, you receive a customized URL for your organization. For example:

<https://console.us-ashburn-1.oraclecloud.com/?tenant=CompanyABC>

If you instead use the base URL (<https://console.us-ashburn-1.oraclecloud.com>), you are prompted to specify your tenant (or cloud account name) on the sign-in page, along with your user name and password.

## Creating a Compartment

This section shows you how to create a Compartment in Oracle Cloud Infrastructure. You must define a Compartment as part of core functionality in Oracle Cloud Infrastructure.

## Prerequisite

- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to [Get to Know the Console](#).
- You should have a fundamental understanding of Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site: [Oracle Cloud Infrastructure](#)
- You must have a subscription to Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to [Getting Started with Oracle Cloud](#).
- To access the Oracle Cloud Infrastructure Console, you must use a supported browser. See **Supported Browsers** in [Troubleshooting Signing In to the Console](#).

To create a Compartment for JD Edwards EnterpriseOne on Oracle Cloud Infrastructure, follow the steps in the [Creating a Compartment](#) section of the Oracle Cloud Infrastructure Documentation.

## Creating a Group

This section shows you how to create a Group in Oracle Cloud Infrastructure.

For additional information on using Groups in Oracle Cloud Infrastructure, refer to the section entitled: **Add a New Group in the Oracle Cloud Infrastructure Console** in [Adding Groups and Users for Tenancies Federated with Oracle Identity Cloud Service](#).

## Prerequisite

- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to [Get to Know the Console](#).
- You should have a fundamental understanding of Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site: [Oracle Cloud Infrastructure](#)
- You must have a subscription to Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to [Getting Started with Oracle Cloud](#).
- To access the Oracle Cloud Infrastructure Console, you must use a supported browser. See **Supported Browsers** in [Troubleshooting Signing In to the Console](#).

To create a group using the Oracle Cloud Infrastructure Console, follow the steps in the [Creating a Group](#) section of the Oracle Cloud Infrastructure Documentation.

## Creating a User

This section shows you how to create users in Oracle Cloud Infrastructure. For additional information on creating users in Oracle Cloud Infrastructure, refer to the topic **Create a User** in [Adding Users](#).

## Prerequisite

- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to [Get to Know the Console](#).
- You should have a fundamental understanding of Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site: [Oracle Cloud Infrastructure](#)
- You must have a subscription to Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to [Getting Started with Oracle Cloud](#).
- To access the Oracle Cloud Infrastructure Console, you must use a supported browser. See **Supported Browsers** in [Troubleshooting Signing In to the Console](#).

**Note:** You must perform this task as an Oracle Cloud Infrastructure user who has sufficient permissions to create and update resources within Oracle Cloud Infrastructure. For more information, refer to [Adding Users in Oracle Cloud Infrastructure Documentation](#).

**Note:** You must create a Domain before creating a User. Refer to [Creating an Identity Domain](#) in Oracle Cloud Infrastructure Documentation.

To create a User, see [Creating a User](#) in Oracle Cloud Infrastructure Documentation.

## Adding Users to Groups

This section tutorial shows you how to add users to groups in Oracle Cloud Infrastructure.

For additional information on using Groups in the Oracle Cloud Infrastructure, refer to the section entitled: [Managing "Managing Oracle Identity Cloud Service Users and Groups in the Oracle Cloud Infrastructure Console"](#) in [Oracle Cloud Infrastructure Documentation](#). For additional information on creating users in Oracle Cloud Infrastructure, refer to [Adding Users](#).

## Prerequisite

- You must have already created a user by following the process described in the preceding module "[Creating a User](#)" in this Learning Path.
- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to [Get to Know the Console](#).
- You should have a fundamental understanding of Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site: [Oracle Cloud Infrastructure](#)
- You must have a subscription to Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to [Getting Started with Oracle Cloud](#).
- To access the Oracle Cloud Infrastructure Console, you must use a supported browser. See **Supported Browsers** in [Troubleshooting Signing In to the Console](#).

To add users to the respective groups, see [Adding a User to a Group](#) in Oracle Cloud Infrastructure Documentation.

## Creating a Policy

This section describes the minimum setup IAM policies required to use JD Edwards EnterpriseOne Infrastructure Provisioning for Reference Architecture. The user who is running the Infrastructure Provisioning must have these policy settings for the group to which they belong. The tenancy administrator for Oracle Cloud Infrastructure is responsible for creating and assigning these requisite policies. If you are unsure of your policy settings you should check with the tenancy administrator.

**Note:** As described above, this procedure may only be necessary in certain regions or for certain classes of subscribers or users in Oracle Cloud Infrastructure.

For additional information on using policies in Oracle Cloud Infrastructure, refer to the documentation for Oracle Cloud Infrastructure in the *Managing Policies*.

### Prerequisite

- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to *Get to Know the Console*.
- You should have a fundamental understanding of Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site: *Oracle Cloud Infrastructure*
- You must have a subscription to Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to *Getting Started with Oracle Cloud*.
- To access the Oracle Cloud Infrastructure Console, you must use a supported browser. See **Supported Browsers** in *Troubleshooting Signing In to the Console*.

To create a policy using the Oracle Cloud Infrastructure Console, refer to *Creating a Policy* in Oracle Cloud Infrastructure Documentation.

In the Policy Builder section, click the **Customize/Advanced** button.

In the Policy Builder dialog, enter the following statements:

```
Allow group <group_name> to read announcements in tenancy
Allow group <group_name> to manage virtual-network-family in tenancy
Allow group <group_name> to manage load-balancers in tenancy
Allow group <group_name> to manage instance-family in tenancy
Allow group <group_name> to read app-catalog-listing in tenancy
Allow group <group_name> to manage volume-family in tenancy
Allow group <group_name> to manage file-family in tenancy
Allow group <group_name> to manage database-family in tenancy
Allow group <group_name> to manage autonomous-database-family in tenancy
Allow group <group_name> to manage keys in tenancy
```

```
Allow group <group_name> to manage dns in tenancy  
Allow group <group_name> to manage object-family in tenancy  
Allow group <group_name> to manage compartments in tenancy  
Allow group <group_name> to manage tag-namespaces in tenancy  
Allow group <group_name> to manage vaults in tenancy  
Allow group <group_name> to manage secret-family in tenancy
```

where **<group\_name>** is the name of group that you specified as described in the section of this Learning Path entitled "Creating a Group".

## Creating a Virtual Cloud Network

This section shows you how to create a Virtual Cloud Network (VCN) in Oracle Cloud Infrastructure using the Start VCN Wizard.

### Prerequisite

- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to *Get to Know the Console*.
- You should have a fundamental understanding of Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site: *Oracle Cloud Infrastructure*
- You must have a subscription to Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to *Getting Started with Oracle Cloud*.
- To access the Oracle Cloud Infrastructure Console, you must use a supported browser. See **Supported Browsers** in *Troubleshooting Signing In to the Console*.

Before you can launch an instance, you must have a Virtual Cloud Network (VCN) in Oracle Cloud Infrastructure. For more information refer to this topic: *Creating the VCN and Subnets to Use with Oracle Functions, if they don't exist already*.

Oracle JD Edwards recommends using the **Start VCN Wizard** to create a complete set of networking resources using the concept of regional networking, which includes route tables with private and public subnets across all Availability Domains (ADs) in your region.

On Virtual Cloud Networks in <your\_compartment>, click the **Start VCN Wizard** button.

On Create a VCN with Internet Connectivity - Configuration, complete these fields in the **Basic Information** and **Configure VCN and Subnets** sections:

### Basic Information

- VCN NAME
- COMPARTMENT

## Configure VCN and Subnets

- VCN CIDR BLOCK (see below Note)
- PUBLIC SUBNET CIDR BLOCK (see below Note)
- PRIVATE SUBNET CIDR BLOCK (see below Note)

**Note:** For CIDR block values, you can either use the example values or obtain the values from your network engineer.

## DNS RESOLUTION

In this section, ensure the following check box is selected:

- USE DNS HOSTNAMES IN THIS VCN

To create a VCN, see [Creating a VCN](#) in the Oracle Cloud Infrastructure Documentation.

# Creating Rules for a VCN Security List

This section shows you how to create rules for virtual cloud network (VCN) security list in Oracle Cloud Infrastructure for use with JD Edwards EnterpriseOne One-Click Provisioning.

## Prerequisite

- You must have created a Virtual Cloud Network as described in the preceding section of this Learning Path entitled: "[Creating a Virtual Cloud Network](#)".
- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to [Get to Know the Console](#).
- You should have a fundamental understanding of Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site: [Oracle Cloud Infrastructure](#)
- You must have a subscription to Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to [Getting Started with Oracle Cloud](#).
- To access the Oracle Cloud Infrastructure Console, you must use a supported browser. See **Supported Browsers** in [Troubleshooting Signing In to the Console](#).

You must create rules for the Public subnet that was automatically created by the workflow wizard when you created the VCN.

**Note:** If you have created a VCN using any other method, you must destroy that VCN and follow the documented procedure in this Learning Path.

Follow the below steps to create rules for a VCN security list:

1. Navigate to Networking > Virtual Cloud Networks
2. In the List Scope section, verify the correct COMPARTMENT is selected.
3. Click the link for the VCN you created and click on Subnet
4. On the list of subnets, click on the link to open the Public-subnet-`<vcn_name>` definition.
5. In Subnet Details, click on Security section and click on the link Default Security List for `<vcn_name>`.

6. On the Default Security List for <vcn\_name> page click on security rules, where default rules are displayed, for the default rule for Port 22, it is recommended to edit the rule to specify a Source CIDR range of 123.123.123.123/32.
7. On the Add Ingress Rules dialog, add rules for ports that should be open to the Private subnet as shown in the following table.

Stateless Check box (always unchecked)	Source CIDR	IP Protocol (always TCP)	Source Port Range (Always All)	Destination Port Range	Comment
	Public subnet (see Note 1)			3000	One-Click Provisioning Console
				3389	Remote Desktop Protocol (RDP)
				8998	Server Manager Console https (SSL)
				8999	Server Manager Console http (non-SSL)
				User-specified SSL port for each HTML instance using Provisioning Console	HTML Server
	Private subnet only (see Note 2)			User-specified SSL port for each AIS instance using Provisioning Console	AIS Server
				1521	Oracle Database Server
				1433	SQL Server Database Server
				User-specified port at installation	WebLogic Admin Console - https (SSL)
				User-specified port at installation	WebLogic Admin Console - http (non-SSL)
	Private subnet only (see Note 2)			5150	Required for One-Click Provisioning to validate ports over the network.
				5985	Deployment Server Used for the winrm port for communication between Provisioning Server and Deployment Server
				6017-6026	Enterprise Server These ports depend on release level of EnterpriseOne and user specification.
				14501-14520	JMX Port (required for Server Manager Agent communication)

**Note: Source CIDR.** In this form, the IP address value represented by **Source CIDR** (where CIDR means Classless Inter-Domain Routing) is a function of the VCN. This is the source IP address from where connection is allowed on a particular port. The syntax x.x.x.x/x provides an IP address range. For example, 10.0.0.0/16 means 10.0.0.1 to 10.0.255.255 (where /16 is the bit length of the subnet mask), while 0.0.0.0/0 means all IP addresses.

**Note:** It is recommended to not open any port for all IP addresses. Instead you should only open ports to specific Public IP addresses by either setting your VCN or by using the OCI function allowlist (formerly whitelist) to specify a CIDR (range of IP addresses). For example, to open an IP port for a range of addresses such as 123.123.123.123, add 123.123.123.123/32 as source CIDR for the port.

**Note: Private Network.** These ports should not use CIDR values that are open to the Internet. They should be specified on a Private Network for machine-to-machine communications. For example, 10.0.0.0/16. Ensure that your Private subnet is configured so that the ports list in the above table are open.

For details, see [Creating a Security List](#) in Oracle Cloud Infrastructure Documentation.

# 4 Creating Linux Instances in Oracle Cloud Infrastructure

## Creating the Linux Instance for the One-Click Provisioning Server

This section shows you how to create a Linux instance for the One-Click Provisioning Server for use by JD Edwards EnterpriseOne on Oracle Cloud Infrastructure. This instance includes the requisite Linux system.

### Background

Oracle Cloud Infrastructure Compute lets you provision and manage compute hosts, known as instances.

**Note:** While Oracle Cloud Infrastructure offers both Bare Metal and Virtual Machine instances, the current version of One-Click Provisioning for Oracle Cloud Infrastructure only supports Virtual Machine instances.

For additional information refer to [Creating an Instance](#) in the [Oracle Cloud Infrastructure Documentation](#).

### Creating a Linux Instance for the One-Click Provisioning Server


Use this procedure to create an instance for JD Edwards EnterpriseOne One-Click Provisioning Server.

1. On the **Oracle Cloud Infrastructure Console Home** page, click the navigation menu in the upper-left corner.
2. From the navigation menu, select **Marketplace > Applications**.
3. In the **Marketplace** page, under **All Applications**, using the Search to locate the listing for JD Edwards EnterpriseOne One-Click Provisioning Server Image.

**Tip:** To more easily locate this image, in the browser page, you can search for all or part of the complete listing title, which is "JD Edwards EnterpriseOne One-Click Provisioning Server".



4. Click on the **Marketplace listing** for JD Edwards EnterpriseOne JD Edwards EnterpriseOne One-Click Provisioning Server Image.
5. On the Marketplace listing for JD Edwards EnterpriseOne JD Edwards EnterpriseOne One-Click Provisioning Server, in the **COMPARTMENT** field, use the drop down list to select the compartment that you previously created in the OBE of this Learning Path entitled **Creating a Compartment**.
6. Also, on the **Launch Instance page**, you must review the **Terms of Use** and click the check box indicating you accept the terms.
7. Click the **Launch Instance** button to continue.



8. On the **Create Compute Instance** page, complete these fields:

o **Name**

**Note:** The system automatically populates this field. It is recommended that you change this name to a value that you might more easily recognize. You can change the name later. The name does not need to be unique because an Oracle Cloud Identifier (OCID) uniquely identifies the instance.

The name you enter here is the display name of the instance. This will be the host name of the JD Edwards EnterpriseOne JD Edwards EnterpriseOne One-Click Provisioning Server Image server.

For example, the One-Click Provisioning Server might be called **jdeprov**.

**Note: Special Naming Restrictions:** Ensure that the host name of the JD Edwards EnterpriseOne JD Edwards EnterpriseOne One-Click Provisioning Server Image instance contains only alphanumeric values. You cannot use special characters such as the dollar sign (\$), exclamation point (!), underscore (\_), vertical pipe (|), at sign (@), and so on, in the host name. Machine names are limited to a maximum of 15 lower-case alphanumeric characters. This is the character count which is supported by the JD Edwards EnterpriseOne database table and application design. Do not use a fully qualified domain name for host names. You should only specify the first node of the domain name. If the existing hostname does not conform to these requirements, the runtime of JD Edwards EnterpriseOne will fail. If a host name does not conform to these requirements, you should permanently change the host name for your system.

o **Create in Compartment**

Enter the name of the compartment in which you want to create the instance. By default, the currently selected Compartment is displayed.

The screenshot shows a form titled "Create Compute Instance". It has two input fields. The first field is labeled "Name" and contains the text "jdeprov". The second field is labeled "Create in compartment" and contains the text "JDE".


o **Configure placement and hardware**

Click on an availability domain (AD) to select it. You can only specify a single AD.

The screenshot shows a section titled "Select an availability domain for your instance". There are three buttons representing different availability domains. The first button is labeled "AD 1" with the identifier "IAUF:PHX-AD-1" and has a blue checkmark, indicating it is selected. The second button is labeled "AD 2" with the identifier "IAUF:PHX-AD-2". The third button is labeled "AD 3" with the identifier "IAUF:PHX-AD-3".


- **Image**

Because you already selected the image from Marketplace, the following image is automatically shown here. You should accept this value.



- **Shape**

Click the **Change Shape** button.



On Browse All Shapes, make the following selections:

- *Instance type*  
Virtual Machine
- *Shape series*

Supported shapes are those which meet the OCPU and memory requirements listed in the OBE of this Learning Path entitled: *Minimum Resource Requirements*

Click the **Select Shape** button to save your selections.

- **Configure networking**

Verify, and if necessary, set your network settings for the instance of JD Edwards EnterpriseOne JD Edwards EnterpriseOne One-Click Provisioning Server Image. These settings include:

- Network
- Subnet
- Subnet in <Compartment>

**Note:** Be sure to select this radio button: Assign a public IPV4 Address.

3 Networking  
Required

A [virtual network interface card \(VNIC\)](#) connects your instance to a [virtual cloud network \(VCN\)](#) and endpoints in and outside the VCN. Having a public IP address is required to make this instance accessible from the internet.

### Primary VNIC

VNIC name

Primary network

Select existing virtual cloud network

Create new virtual cloud network

Specify OCID

Virtual cloud network compartment  
WinrmUplift

Virtual cloud network  
myVcn

Subnet

Select existing subnet

Create new public subnet

Subnet compartment  
WinrmUplift

Subnet  
Public Subnet IAUF:US-ASHBURN-AD-1

- o **Advanced Options**

Expand the Advanced Options section and enter the Hostname. This value also appears as the Instance Name under the Basic Information section.

Advanced options

Use network security groups to control traffic

Let's you add this secondary VNIC to one or more network security groups (NSGs). You can configure this later if you're not sure whether to use NSGs. An NSG has a set of security rules that control allowed types of inbound and outbound traffic. The rules apply only to the resources in the group. Contrast this with a security list, where the rules apply to all the resources in any subnet that uses the list. [Learn more about security rules.](#)

DNS record

Assign a private DNS record

Do not assign a private DNS record

Hostname  
Instance\_name

Fully qualified domain name  
Instance\_name.sub07220705290.myvcn.oraclevcn.com

Launch options

Let Oracle Cloud Infrastructure choose the best networking type  
Allow Oracle Cloud Infrastructure to choose the [networking type](#), depending on the instance shape and operating system image.

Paravirtualized networking  
For general purpose workloads such as enterprise applications, microservices, and small databases.

Hardware-assisted (SR-IOV) networking  
For low-latency workloads such as video streaming, real-time applications, and large or clustered databases. Does not support live migration.

- o **Add SSH Keys**

You must add the SSH keys that you previously created for use with JD Edwards EnterpriseOne JD One-Click Provisioning Server Image.

You can either click the **Choose SSH key file** option to select a file with your public (.pub) key from your computer, or choose the **Paste SSH keys** option to paste the key.

**Add SSH keys**

Generate an [SSH key pair](#) to connect to the instance using a Secure Shell (SSH) connection, or upload a public key that you already have.

Generate a key pair for me

Upload public key file (.pub)

Paste public key

No SSH keys

SSH public key

Drop a file or select one  
Select or drop files here

File upload Clear

rKey.pub 397 B x

- **Configure boot volume**

#### **One-Click with a Compute or DB Systems (DBS) Database**

You must specify a value of 100 GB. This size is required to support the install of the Provisioning Server with Pristine data (50 GB) with the remainder for use by a customer's normal data set. Further, you must enable this extended boot volume size as described below in the task [Enabling the Custom Boot Volume Size](#).

#### **One-Click with an Autonomous Database (ADB)**

You must specify a value of 150 GB. This size is required to support the install of the Provisioning Server with Pristine data (50 GB) with the remainder for use by a customer's large data set. Further, you must enable this extended boot volume size as described below in the task [Enabling the Custom Boot Volume Size](#).


Optionally you can choose to enable encryption using the checkbox for **Use In-Transit Encryption**.

- **Show Advanced Options**

You do not need to set any Advanced Options.

- Click the **Create** button to create the Oracle Cloud Infrastructure instance for JD Edwards EnterpriseOne JD Edwards EnterpriseOne One-Click Provisioning Server Image.

**Note:** After the instance is created, the system assigns a **Public IP address**. Make a note of this address because you will need it to connect to the instance using the SSH keys in order to complete the first-time configuration of the One-Click Provisioning Server Image for JD Edwards EnterpriseOne as described in the following section.



## Enabling the Custom Boot Volume Size

If you followed the recommendation in this Learning Path and specified a Custom Boot Volume Size when you created the Linux instance for the Provisioning Server, you must run the following command (as root) to complete the resize functionality.

```
sudo /usr/libexec/oci-growfs -y
```

**Note:** It is good practice to ensure that the latest utilities are installed on your operating system image.

**Note:** The utility `oci-growfs` expands the root filesystem of the instance to its configured size. This command must be run as root. For additional information, refer to this Oracle documentation: <https://docs.oracle.com/en-us/iaas/Content/Compute/References/oci-growfs.htm>

## Setting Up the Provisioning Server

**Note:** Before executing any scripts on the Provisioning Server, you must run a mandatory patch as described in the MOS document: E1: OCI: Additional One-Click server deployment is failing on existing TLS-enabled SMC (Doc ID 3010098.1).

Use this procedure to set up the One-Click Provisioning Server.

- Connect to Provisioning Server Instance with public IP address and private key using Putty.

2. Run the following command:

```
sudo ./prepareProvisionPrime.sh
```

**Note:** You can safely ignore access or permission errors in the console output during script execution. Such errors do not affect the successful execution of the script.

**Note:** The Provisioning Server will reboot after running prepareProvisionPrime.sh script.

3. Upon completion of the reboot, run the following command:

```
sudo ./setupProvisionPrime.sh
```

**Note:** Do not reboot the Provisioning Server after running above setup command until you change password for Server Manager Console and WebLogic Server.

## Creating Linux Instances as VMs in Oracle Cloud Infrastructure

This section shows you how to create Linux instances as virtual machines (VMs) in the Compute Service of Oracle Cloud Infrastructure.

### Background

Oracle Cloud Infrastructure Compute enables you to provision and manage compute hosts, known as instances.

**Note:** While Oracle Cloud Infrastructure offers both Bare Metal and Virtual Machine instances, the current version of One-Click Provisioning for Oracle Cloud Infrastructure only supports Virtual Machine instances.

For additional information refer to [Creating an Instance](#) in the [Oracle Cloud Infrastructure Documentation](#).

In preparation for JD Edwards EnterpriseOne One-Click Provisioning, you must create Linux VM instances in Oracle Cloud Infrastructure Compute for each of these core JD Edwards EnterpriseOne servers:

- **Oracle Database Server**

**Note:** A Linux VM instance is required for this server if you are installing your own Oracle database (Bring Your Own License - BYOL) in Oracle Cloud Infrastructure Compute. Otherwise, you can use Oracle Database Services.

- **Enterprise Server**

- **WebLogic Server**

**Note:** The image in the Marketplace for Oracle Cloud Infrastructure for the JD Edwards EnterpriseOne One-Click Provisioning Server includes the requisite Linux image.

**Note:** For best performance, Oracle strongly recommends creating VMs for all JD Edwards components within the same Availability Domain (AD).


## Prerequisite

- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to [Get to Know the Console](#).
- You should have a fundamental understanding of Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site: [Oracle Cloud Infrastructure](#)
- You must have a subscription to Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to [Getting Started with Oracle Cloud](#).
- To access the Oracle Cloud Infrastructure Console, you must use a supported browser. See **Supported Browsers** in [Troubleshooting Signing In to the Console](#).

## Creating Linux Instances as VMs

With these exceptions, the procedure for creating a Linux instance as a VM is specified in the section: [Creating the Linux Instance for the One-Click Provisioning Server](#):

- Supported shapes are those which meet the OCPU and memory requirements listed in the section of this Learning Path entitled: [Minimum Resource Requirements](#).
  - Instead of having the requisite Operating System version automatically selected when you are installing from a Marketplace image for the Provisioning Server, you must manually select a specific image that is certified with JD Edwards EnterpriseOne. Refer to the [Supported Software Versions](#) section of this Learning Path for the supported release of Oracle Linux.
1. On Create Compute Instance, in the **Image** section, click the **Change Image** button.



2. On Browse All Images:

- o In the **Image name** column, click the **Oracle 9 Linux** checkbox.
- o In the **Image build** column, use the pull-down to select the latest build.

**Select an image**

<input type="radio"/>	▶ Oracle Autonomous Linux 8	Oracle	Free	Shielded instance, BM Confidential computing
<input type="radio"/>	▶ Oracle Autonomous Linux 9	Oracle	Free	Shielded instance, BM Confidential computing
<input type="radio"/>	▶ Oracle Linux 10	Oracle	Free	Shielded instance, Confidential computing, BM Confidential computing
<input type="radio"/>	▶ Oracle Linux 6.10	Oracle	Free	BM Confidential computing
<input type="radio"/>	▶ Oracle Linux 7.9	Oracle	Free	Shielded instance, Confidential computing, BM Confidential computing
<input type="radio"/>	▶ Oracle Linux 8	Oracle	Free	Shielded instance, Confidential computing, BM Confidential computing
<input checked="" type="radio"/>	▼ Oracle Linux 9	Oracle	Free	Shielded instance, Confidential computing, BM Confidential computing

**Compatible shapes** [View compatible shapes](#)

Image build  
2025.0916-0

<input type="radio"/>	▶ Oracle Linux 9 Minimal	Oracle	Free	BM Confidential computing
<input type="radio"/>	▶ Oracle Linux Cloud Developer 8	Oracle	Free	BM Confidential computing

Page 1 of 1 (1 - 10 of 10 total items) Items per page 25

# 5 Creating Volume Storage

## Using Volume Storage

This section provides an overview to using volume storage in Oracle Cloud Infrastructure for use by JD Edwards EnterpriseOne with One-Click Provisioning.

To understand your volume storage options in Oracle Cloud Infrastructure, refer to this link: [Overview of Block Volume](#).

### Using Storage: Block Volume and Boot Volume

Oracle Cloud Infrastructure supports two types of volumes:

- **Block Volumes**

This storage is used to expand the storage capacity of Compute instances, to provide durable and persistent data storage that can be migrated across Compute instances, and to host large databases in Compute. To use this volume type you must create, attach, and connect the volume.

- **Boot Volumes**

Instances that are created on the Oracle Cloud Infrastructure are allocated a fixed default amount of storage, called the Boot Volume. This default storage amount must be expanded to meet the requirements of JD Edwards Enterprise servers. These storage amount requirements are specified in the section of this Learning Path entitled [Minimum Resource Requirements](#).

Selecting between boot volume or block volume storage is the responsibility of your system architect. For JD Edwards EnterpriseOne, at a minimum, you must create sufficient storage for these machines:

- Provisioning Server
- Database Server
- Enterprise Server
- WebLogic Server
- Deployment Server
- Development Client

### Block Volume Storage

If you choose to use block volume storage, you must complete the following steps:

- [Creating a Block Volume](#)
- [Attaching a Volume](#)
- [Connecting a Volume](#)

**Note:** This section contains instructions for both Linux and Microsoft Windows environments.

### Boot Volume Storage

If you choose to use boot volume storage, refer to the steps in the following document:

- [Boot Volumes](#)

# 6 Configuring the Linux Servers

## Performing Common Setup for All Linux Servers

This section describes the setup tasks that must be performed on each Linux-based server that will be deployed by JD Edwards EnterpriseOne One-Click Provisioning, excluding the One-Click Provisioning Server, which does not require manual setup. The remaining Linux servers used by JD Edwards EnterpriseOne may include a Compute Oracle Database Server. If you are using DB Systems instead of a Compute Oracle Database Server, you must perform the setup described in the Learning Path *Deploying JD Edwards EnterpriseOne on Oracle Cloud Infrastructure on Linux with DBaaS (DB Systems)*.

### Prerequisite

You must have created a Linux VM for each server that will be deployed by the JD Edwards EnterpriseOne One-Click Provisioning Server for the Oracle Cloud Infrastructure. At a minimum, this includes the Compute Database Server (except if you are using DBaaS - DB Systems), Enterprise Server, and WebLogic Server. Refer to the section "[Creating Linux Instances as VMs on the Oracle Cloud Infrastructure](#)" in this Learning Path.


### General

Use the following general steps to confirm the completion of the common setup that is required for each VM instance that you created in Compute to support JD Edwards EnterpriseOne on the Oracle Cloud Infrastructure.

1. Ensure that the `/u01` mount point is created and mounted. This should have been done when you created Block Volume storage. Use this command to verify that the volume is mounted on `/u01`:

```
df -h
```

The returned results should be similar to this:



```
opc@bmjdedbsvr:~  
[opc@bmjdedbsvr ~]$ sudo mkdir /u01  
[opc@bmjdedbsvr ~]$ sudo mount /dev/sdb /u01  
[opc@bmjdedbsvr ~]$ df -h  
Filesystem      Size  Used Avail Use% Mounted on  
/dev/sda3       38G   1.1G   35G   4% /  
tmpfs           14G     0    14G   0% /dev/shm  
/dev/sda1       543M  280K  543M   1% /boot/efi  
/dev/sdb        79G   56M   75G   1% /u01  
[opc@bmjdedbsvr ~]$
```

2. Ensure that the proper permissions are set on the `/u01` mount using this command:

```
sudo chmod 770 /u01
```

3. Ensure that the host name for the server contains only alphanumeric values. Special characters are not allowed, with the exception of a hyphen “\_”, which is allowed. Special characters are not allowed except a hyphen (-). Refer to **Special Naming Restrictions** in the section "[Creating Linux Instances as VMs in Oracle Cloud Infrastructure](#)" in this Learning Path.
4. Edit the `sshd_config` file using this command:

```
sudo vi /etc/ssh/sshd_config
```

5. Verify the following settings in the `/etc/ssh/sshd_config` file:

- a. Contains this setting:

```
ClientAliveInterval 3600
```

Ensure that the setting exists, is set properly to 3600, and is not commented out.

- b. Has the SSH connection over IPv6 **disabled** by having this setting:

```
AddressFamily inet
```

Ensure that the setting exists, is set properly to `inet` (not `any`), and is not commented out.

6. Edit the `sudoers` file using this command:

```
sudo vi /etc/sudoers
```

7. Verify that the `/etc/sudoers` file either does not contain this setting or this setting is disabled in the file:

```
Defaults requiretty
```

8. You must disable IPv6 using the following command:

```
sudo vi /etc/sysctl.conf
```

Ensure that the `/etc/sysctl.conf` file has these settings to disable IPv6 protocol:

```
net.ipv6.conf.default.disable_ipv6=1
```

```
net.ipv6.conf.all.disable_ipv6=1
```

9. Optionally, you can choose to edit the `bash.profile` to set the user default language for output to prevent unreadable characters from being inserted into messages and logs.

```
sudo vi /root/.bash_profile
```

Add this setting:

```
LANG="C"
```

## Enable Inbound Ports in the Firewall for Compute Instances

You must enable inbound ports in the firewall service for the Compute instance of each Linux server to enable the functionality of the Provisioning Server to provision each Linux server.

1. For each JD Edwards EnterpriseOne server, repeat this command as necessary to specify open ports in the firewall:

```
sudo firewall-cmd --zone=public --add-port=<PORT>/tcp --permanent
```

where `<PORT>` is the port number that must be open. These port numbers are listed in the following table.

Linux Server Firewall Port List	
Component	Inbound Ports to Open

Oracle Database	22  5150  <DB_PORT>  14502-14510
Enterprise Server	22  5150  6017-6022  14502-14510
Web Server	22  5150  <WLS_ADMIN_PORT> <b>See Note: 1</b>  <SSL_ACCESS_PORT> <b>See Note 2</b> <SSL_ACCESS_PORT-1> <b>See Note 3</b>  14502-14520

**Note: 1** This is the Admin Port on which the Admin Server is running. This value is set by the user while creating a WebLogic domain.

**Note: 2** This SSL port must be opened to enable the Server Manager Console to complete the tasks.

**Note: 3** This port number is equal to the value of the SSL port minus one. This port must be opened to enable the Server Manager to complete the provisioning tasks. For example, if you have specified the port value as 8081 in the One-Click Provisioning Console, you must open 8080 port (8081-1). Also, you must open a port for each of the WebLogic Servers on Oracle Cloud Infrastructure. For example, if you have the following environments and server combinations, you should open eight ports: four ports for SSL for the port numbers specified by using the Provisioning Console, and four ports for non-SSL. The value of the ports for non-SSL should be the value of the SSL port minus one.

- DV HTML
- PD HTML
- DV AIS
- PD AIS

2. After all the ports are opened in the firewall for each server, use these commands to reload the firewall:

```
sudo systemctl stop firewalld  
  
sudo systemctl start firewalld
```

## Disable SELINUX and Reboot Machines

After you have configured the firewall, use this procedure to disable SELINUX and reboot the machine for the changes to take effect.

1. Use this command to check the status of Security Enhanced Linux (SELINUX):

```
sudo getenforce
```

If the returned status is either **Enforcing** or **Permissive**, you must temporarily disable the extra security restriction provided by SELINUX by modifying this file:

```
/etc/selinux/config
```

Edit the `/etc/selinux/config` file using this command:

```
sudo vi /etc/selinux/config
```

Ensure that `SELINUX=` is set to this value:

```
SELINUX=disabled
```

2. When you change any security settings, for example if you disable SELINUX as described in the preceding step, you must reboot the machine using this command:

```
sudo shutdown -r now
```

3. If you reboot to enable the security settings, after the reboot is complete, run `sudo getenforce` to confirm that the status of SELINUX is **Disabled**.

**Note:** As a recommended best practice, after you have successfully completed JD Edwards EnterpriseOne One-Click Provisioning, you should reactivate SELINUX by changing the setting to either of the following: **SELINUX=Enforcing** or **SELINUX=Permissive**

## Set Up Users and Groups

By default, the Oracle Cloud Infrastructure has a predefined **opc** user and **opc** group. Perform these tasks to set up additional users and groups on each Linux server:

1. Create the **dba** and **oracle** groups using these commands:

```
sudo groupadd -g nnnn dba
```

```
sudo groupadd -g nnnn oracle
```

where `nnnn` is the ID value with which the group will be created. You must use a free value that ideally should be above 1000. You can determine used group IDs with the `id` command.

2. Create the **oracle** user and add it to the **oracle** group using this command:

```
sudo useradd -d /home/oracle -m -s /bin/bash oracle
```

**Note:** This step is not required for DB Systems because this database is already set up by default.

3. Add the **opc** user to the **oracle** group and the **oracle** user to the **dba** group and the **oracle** group using these commands:

```
sudo usermod -a -G oracle opc
```

```
sudo usermod -a -G oracle oracle
```

```
sudo usermod -a -G dba oracle
```

4. Set `/u01` as owned by the **oracle** group using this command:

```
sudo chgrp oracle /u01
```

## Install Requisite YUM Packages

You must install a specific set of packages from the YUM repository onto each Linux-based server (excluding the One-Click Provisioning Server) in the JD Edwards EnterpriseOne environment. The additional servers include:

- **Compute Oracle Database Server**
- **Enterprise Server**
- **WebLogic Server**

**Note:** Ensure that you have enabled your YUM repository. For Linux instances that are provisioned in Oracle Cloud Infrastructure, this is generally set to enabled by default. This functionality is required to install YUM packages that are prerequisites to set up each JD Edwards EnterpriseOne server. If you had not pre-enabled your YUM repository before you ran One-Click to set up the JD Edwards EnterpriseOne servers, then you must enable it and manually install and/or update all required YUM packages as listed below.

The following lists are the required packages sorted alphabetically. You can create a script to install the packages one at a time, or all at once. In either case, be sure to confirm that when each command executes, the command returns either of these results:

Complete

or

Nothing to do

**Note:** If you choose to run all the YUM packages at once, using a single command, you may encounter errors. For example, a package may not install as expected due to dependency or other technical issues with the package or library. Further, this behavior is unpredictable and can vary according to system conditions. The resolution of such errors is the responsibility of your system administrator and is beyond the scope of this document. If you need help for resolving YUM issues, your Linux Admin should open a service request with the Oracle Linux support team. Additionally, various Linux OS images may be delivered with some of these packages already installed by default. You can use the complete list shown below for each server to cross-check which packages may already be installed and those that you will need to manually install.

**Note:** It is recommended that you run YUM install commands as the root user. For example: `sudo su yum install -y bind-utils`

## Compute Oracle Database Server

Ensure the VM instance for the Compute Oracle Database Server contains these YUM packages:

**Note:** For users who have set up servers using a previous version of Linux, the package names below with strikethrough are not required for OL9.6, while the names in **bold** are new requirements.

~~bind-utils~~

~~bc.x86\_64~~

~~binutils.x86\_64~~

~~compat-libcap1.x86\_64~~

~~compat-libstdc++-33.x86\_64~~

~~compat-openssl10.x86\_64~~

~~gcc.x86\_64~~

~~elfutils-libelf.x86\_64~~

```
fontconfig.x86_64
gcc-c++.x86_64
glibc.i686
glibc.x86_64
glibc-devel.x86_64
ksh.x86_64
libaio.x86_64
libaio-devel.x86_64
libasan.x86_64
liblsan.x86_64
libgcc.x86_64
libns1.x86_64
libstdc++.x86_64
libstdc++-devel.x86_64
libX11.x86_64
libXau.x86_64
libxcb.x86_64
libXext.x86_64
libXi.x86_64
libXtst.x86_64
libvirt-libs.x86_64
libXrender.x86_64
libxcrypt-compat.x86_64
libibverbs.x86_64
librdmacm.x86_64
make.x86_64
policycoreutils.x86_64
policycoreutils-python-utils.x86_64
sysstat.x86_64
smartmontools.x86_64
unzip.x86_64
```

`zip.x86_64`

## Enterprise Server

**Note:** Usually, the order in which you run YUM updates is not a factor. However, there is a known dependency on the installation order for certain packages, therefore you should install packages in the order shown below. If other dependencies arise, they should be resolved by your Linux administrator.

Ensure that the VM instance for the Enterprise Server contains these YUM packages:

**Note:** For users who have set up servers using a previous version of Linux, the package names below with strikethrough are not required for OL9.6, while names in **bold** are new requirements.

```
binutils.x86_64
compat-libcap1.x86_64
compat-libstdc++-33.i686
compat-libstdc++-33.x86_64
compat-openssl11.x86_64
elfutils-libelf-devel.x86_64
file
gcc.x86_64
gcc-c++.x86_64
glibe.i686
glibc.x86_64
glibc-devel.i686
glibc-devel.x86_64
ksh.x86_64
libaio.i686
libaio.x86_64
libaio-devel.i686
libaio-devel.x86_64
libasan.x86_64
liblsan.x86_64
libns12.x86_64
libns12-devel.x86_64
```

```
libgcc.i686
libgcc.x86_64
libnsl.x86_64
libstdc++.i686
libstdc++.x86_64
libstdc++-devel.x86_64
libX11.i686
libX11.x86_64
libXau.i686
libXau.x86_64
libxcb.i686
libxcb.x86_64
libXext.i686
libXext.x86_64
libXi.i686
libXi.x86_64
libXtst.i686
libXtst.x86_64
make.x86_64
ncompress
oracle-database-preinstall-19c.x86_64
sysstat.x86_64
unixODBC.x86_64
unixODBC-devel.x86_64
unzip.x86_64
zlib.i686
zlib.x86_64
zip.x86_64
zlib-devel.i686
zlib-devel.x86_64
nss-softokn-freebl.x86_64
```

~~nss-softokn-freebl.i686~~

## WebLogic Server

Ensure that the VM instance for the WebLogic Server contains these YUM packages:

**Note:** For users who have set up servers using a previous version of WebLogic Server, the package names below with strikethrough are not required for the currently supported version, while two (2) names in red are new requirements.

~~bind-utils~~

~~glibc.i686~~

~~glibc.x86\_64~~

~~glibc-devel.x86\_64~~

~~ksh.x86\_64~~

~~libnsl.x86\_64~~

~~net-tools~~

~~unzip.x86\_64~~

~~zip.x86\_64~~

~~zlib-devel.x86\_64~~

## Edit the resolv.conf File to Specify the DNS Domain Name

You must ensure that the search setting in the `/etc/resolv.conf` file specifies the DNS domain name of the Availability Domain to which all JD Edwards EnterpriseOne servers belong. While logged in as the root user (the owner of the `resolv.conf` file), you must add a line with the following syntax to the `resolv.conf` file:

```
$ vi /etc/resolv.conf
```

```
search <DNS_Domain_Name> <subnet1> <subnet2> <subnet3>.<DNS_Domain_Name>
```

Generally each Availability Domain contains at least three subnets. You must include an exact search string for each of those subnets.

For example, your subnets can look like this:

The screenshot displays the Oracle Cloud console interface. On the left, a green hexagonal logo with 'VCN' is shown with the status 'AVAILABLE'. Below it, a sidebar lists 'Resources' including Subnets (3), Route Tables (1), Internet Gateways (1), Dynamic Routing Gateways (0), Security Lists (1), DHCP Options (1), and Local Peering Gateways (0). The 'COMPARTMENT' dropdown is set to 'EnterpriseOne\_BM'. The main content area shows 'Subnets in EnterpriseOne\_BM Compartment' with a 'Create Subnet' button and a 'Sort by: Created Date (Desc)' dropdown. Three subnets are listed:

Subnet Name	CIDR Block	Virtual Router MAC Address	Availability Domain	DNS Domain Name	Subnet Access
Public Subnet IAUF:PHX-AD-3	10.0.2.0/24	...	IAUF:PHX-AD-3	sub06220506332.testdnsvcn.oraclevcn.com	Public Subnet
Public Subnet IAUF:PHX-AD-2	10.0.1.0/24	...	IAUF:PHX-AD-2	sub06220506331.testdnsvcn.oraclevcn.com	Public Subnet
Public Subnet IAUF:PHX-AD-1	10.0.0.0/24	...	IAUF:PHX-AD-1	sub06220506330.testdnsvcn.oraclevcn.com	Public Subnet

Using the above example, assuming that your JD Edwards EnterpriseOne Servers are running in the Phoenix Availability Domain, you would edit your `/etc/resolv.conf` file to add a line with a search setting similar to the setting provided below to include all the three domains:

```
search testdnsvcn.oraclevcn.com sub06220506330.testdnsvcn.oraclevcn.com sub06220506331.testdnsvcn.oraclevcn.com sub06220506332.testdnsvcn.oraclevcn.com
```

## Change the Maximum Transmission Unit (MTU) Setting

The recommended MTU setting is 1500. Use this procedure to check, and if necessary change, the current MTU setting.

1. Run this command to check current value of MTU:

```
ifconfig
```

2. If the MTU is not set to 1500, then run below commands to set MTU value:

```
sudo sed -i -e "\$a ifconfig ens3 mtu 1500 up" /etc/rc.d/rc.local
```

```
sudo sed -i -e "\$a ifconfig ens3 mtu 1500 up" /etc/rc.local
```

```
sudo chmod +x /etc/rc.d/rc.local
```

3. Reboot the machine to enable this change.

# Setting Up the Enterprise Server

This section shows you how to set up the Enterprise Server for JD Edwards EnterpriseOne on the Oracle Cloud Infrastructure.

## Prerequisite

You must have created a Linux VM for the Enterprise Server as described in the module of this Learning Path entitled: *Creating Linux Instances as VMs on the Oracle Cloud Infrastructure*.

The Linux VM for the Enterprise Server must be allocated with storage volume space, the amount of which is specified in the module of this Learning Path Entitled: **Before You Begin**.

You must have performed the functions described in the module of this Learning Path entitled: **All Servers Common Setup**.

## Setting Up the Enterprise Server

1. Ensure you have performed all the tasks described in the module of this Learning Path entitled: *Common Setup for Linux Servers* including the steps to create groups and users as well as assigning proper permissions to `/u01`.
2. Use this command to ensure that the `/u01` mount point has proper permissions to allow the One-Click Provisioning process to subsequently create requisite folders:

```
sudo chmod 770 /u01
```

3. Create the **oneworld** group using this command:

```
sudo groupadd -g nnnn oneworld
```

where *nnnn* is the ID value with which the group will be created. You must use a free value which ideally should be above 1000. You can determine used group IDs with the `id` command.

4. Create the **jde920** user and make the KornShell the default shell (using the `-s` switch with `/bin/ksh`), using this command:

```
sudo useradd -d /home/jde920 -m -s /bin/ksh jde920
```

**Note:** This specific user, with access to `ksh`, is required in order to start and stop the Enterprise Server.

5. Add the **jde920** user to the **oracle** and **oneworld** group using these commands:

```
sudo usermod -a -G oracle jde920
```

```
sudo usermod -a -G oneworld jde920
```

6. Ensure that there is sufficient available storage for the Enterprise Server, YUM packages, and the archive (compressed and extracted). For Production environments, this space should be allocated as a Block Volume. You should have already created and attached the requisite Block Storage if you followed the instructions in the

modules of this Learning Path entitled: **Create Additional Block Volumes for Linux Instances** and **Attach the Block Volumes for Linux Instances**.

Use this command to view your available storage space on /u01:

```
df -h
```

where you should have allocated sufficient size when you created the VM instance for the Enterprise Server in the amount specified in the *Before You Begin* section of this Learning Path.

7. Edit the `/etc/sysctl.conf` file:

```
sudo vi /etc/sysctl.conf
```

8. Ensure that this setting exists:

```
kernel.sem = 1250 32000 100 1024
```

9. Update `.bash_profile` of the **root**, **opc**, and **oracle** users with below export values.

**Note:** This setting is required on the Oracle database target machine, which is the Enterprise Server, in order to enable the installation of the Oracle database client.

```
sudo vi /root/.bash_profile
export CV_ASSUME_DISTID=OL7
```

```
sudo vi /home/opc/.bash_profile
export CV_ASSUME_DISTID=OL7
```

```
sudo vi /home/oracle/.bash_profile
export CV_ASSUME_DISTID=OL7
```

## Setting Up the WebLogic Server

This section shows you how to set up the WebLogic Server for JD Edwards EnterpriseOne on the Oracle Cloud Infrastructure.

### Prerequisite

- You must have created a Linux VM for the WebLogic Server.
- The Linux VM for the WebLogic Server must be allocated with storage volume space, the amount of which is specified in the module of this Learning Path Entitled: **Before You Begin**.
- You must have performed the functions described in the module of this Learning Path entitled: **All Servers Common Setup**.
- If you are installing WebLogic Server in a Compute instance, complete sections 1 through 4.
- If you have installed WebLogic Server using an image provided by Oracle Cloud Infrastructure, complete sections 1 through 5.

## General

The following general prerequisites are required for the Oracle WebLogic Server:

1. Ensure you have performed all the tasks described in module of this Learning Path entitled: *Performing Common Setup for All Linux Servers* including the steps to create groups and users as well as assigning proper permissions to `/u01`.
2. Use this command to ensure that the `/u01` mount point has proper permissions to allow the One-Click Provisioning process to subsequently create requisite folders:

```
sudo chmod 770 /u01
```

3. Ensure the user with which Oracle WebLogic Server was installed is part of the **oracle** group. Use this command to verify:

```
groups username
```

## Install Oracle WebLogic Server and a JDK

You must manually pre-install Oracle WebLogic Server (WebLogic Server) and a JDK for use by WebLogic Server.

**Note:** For the JDK installation, you must ensure that it is installed under the `/u01` mount point. Further you must ensure that the JDK is installed by the same user that has been or will be used to install WebLogic Server. For example, if you use the **oracle** user to install the JDK, you must use the **oracle** user to install WebLogic Server, or vice versa depending on the order you install these products.

Customers can then use JD Edwards One-Click Provisioning to deploy the JD Edwards EnterpriseOne web components into the pre-installed WebLogic Server domain. Refer to the Oracle Certifications for JD Edwards EnterpriseOne One-Click Provisioning on OCI for details on supported versions of WebLogic Server.

The complete list of prerequisites are below:

- Compute instance must have a supported version of WebLogic Server pre-installed. The password must be 8 to 30 characters long, must contain at least one number, and optionally any number of either the Pound Sign (#) or Underscore (\_) special characters.

**Note:** The password for any WebLogic Server user *cannot* contain these special characters: Dollar Sign (\$) Exclamation Mark (!) Ampersand (&) Using any of the above special characters violates the Oracle Cloud password policy and will result in denied access.

- Compute instance must also have a supported JDK version installed.
- WebLogic Server must be defined with at least one domain.
- WebLogic Server must be in a running state and able to connect to the Admin Console.
- WebLogic Server must have a running Node Manager process for the existing domain.
- WebLogic Server must be installed as a user that is part of the **oracle** group.

## Post Installation of WebLogic Server

After you have installed WebLogic Server, prior to using the Provisioning Console for JD Edwards EnterpriseOne, you must manually configure WebLogic Node Manager to disable SSL. Otherwise the provisioning will fail.

1. Locate the `nodemanager.properties` file which is typically found in this location:

```
<ORACLE_HOME>/user_projects/domains/<DOMAINNAME>/nodemanager/nodemanager.properties
```

2. Edit the `nodemanager.properties` file so set this property to disable SSL:

```
SecureListener=false
```

3. Save the `nodemanager.properties` file.
4. You must set the listen address must be set exactly same as value of **ListenAddress** property of `nodemanager.properties` file. You must set the listen port 5556, which is non-secure (instead of 5557, which is secure ) in both Node Manager properties file and in node manager using the WebLogic Server user interface. For instructions refer to this procedure: [Changing the Oracle HTTP Server Listen Ports](#).
5. Restart the WebLogic Node Manager for the setting to take effect.

## Ensure WebLogic Server is Patch Current

Refer to the Oracle Certifications for One-Click for WebLogic Server to verify that the latest available patches are applied. Such patches can affect the ability of One-Click Provisioning to deploy web components into WebLogic Server.

## Configuring a WebLogic Server Instance Installed from the Marketplace of Oracle Compute Infrastructure

This section is only required if you have installed WebLogic Server from the Marketplace of Oracle Cloud Infrastructure.

The following describes feature support for an installation of WebLogic Server from the Marketplace for Oracle Cloud Infrastructure:

- **Standard or Enterprise Edition**

Both of these editions are supported.

- **Number of Nodes**

Only a single node is supported.

- **Load Balancer**

This feature is not supported by JD Edwards One-Click Provisioning.

After the WebLogic Server is installed from the Marketplace of Oracle Cloud Infrastructure, you must perform further configuration as described below.

1. Connect to your instance of WebLogic Server.
2. Access the WebLogic Admin Console.
3. Navigate to Environments, Machines.
4. Select the tab for Configuration, Node Manager.
5. Set Type as PLAIN.
6. Save the selection.
7. Log in to WebLogic Server instance and edit the `/etc/hosts` file to add these two lines:

```
<Private ip> localhost localhost.localdomain localhost4 localhost4.localdomain4
```

```
<Private ip> <FQDN> <short host name>
```

8. Run this command to enable root account:

```
sudo usermod -s /bin/bash root
```

# 7 Configuring the Database

## Creating DB Systems in Oracle Cloud Infrastructure

This section shows you how to create DB systems in Oracle Cloud Infrastructure.

If you are implementing your database in Compute, you should be using the Learning Path entitled: "Deploying JD Edwards EnterpriseOne on Oracle Cloud Infrastructure on Linux with Compute Database".

Oracle Cloud Infrastructure offers 1-node DB systems on either bare metal or virtual machines, and 2-node RAC DB systems on virtual machines. The Oracle Database environment that your deployed database provides in either type of infrastructure is nearly the same. A few differences exist in the underlying infrastructure components and in the supported capabilities. Awareness of these differences will help you choose an appropriate infrastructure when deploying a database. For further details, refer to *About Database Deployments in Oracle Cloud Infrastructure*.

### Prerequisites

- Refer to **Prerequisites** in this Oracle Cloud Infrastructure documentation: *Creating Bare Metal and Virtual Machine DB Systems*.
- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to *Using the Console*.
- You should have a fundamental understanding of Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site:

*Oracle Cloud Infrastructure*

- You must have a subscription to the Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to:

*Getting Started with Oracle Cloud*

- To access the Oracle Cloud Infrastructure Console, you must use a *supported browser*.

## Create DB Systems

Use this procedure if you choose to use DB systems for your Oracle database instead of creating an Oracle Cloud Infrastructure Compute instance for your Oracle database.


For additional information on completing the fields for creating a DB System, refer to the Oracle Cloud Infrastructure documented for *Creating Bare Metal and Virtual Machine DB Systems*.

With DB systems, you can choose either of these licensing models:


- License Included (subscription service)
- Bring Your Own License (BYOL)

1. On the Oracle Cloud Infrastructure Console Home page, click the navigation menu in the upper-left corner.

- From the navigation menu, in the **Oracle Database** section, select **Bare Metal, VM, and Exadata**.



- On the Bare Metal, VM, and Exadata page, in the left pane, ensure that **DB Systems** is selected.
- By default, the DB System launches in your current compartment and you can use the network and subnet resources in that compartment. Otherwise you can use the pull-down menu in the **List Scope** section to choose the compartment into which you want to create a DB System. Otherwise you can change the Compartment and assign network resources when you define DB System Information in the following steps.
- Click the **Create DB System** button.



6. The following steps describe the fields on these major sections of the Launch DB System form:

- o **DB System Information**
- o **Database Information**

**Note:** Refer to **Default Options for the Initial Database** in this Oracle Cloud Infrastructure documentation:  
*Creating Bare Metal and Virtual Machine DB Systems.*

7. On the Create DB System pane in the **DB System Information** section, complete the fields to provide basic information for the DB System.

**Note:** For use with JD Edwards EnterpriseOne, the following conditions apply:

- o **Select a shape type**

The supported shape type for a DB System is **Virtual Machine**.

- o **Shape**

Supported shapes are those which meet the OCPU and memory requirements listed in the section of this Learning Path entitled: *Minimum Resource Requirements*.

- o **Oracle Database software edition**

**Single (1) Node Database**

- Standard Edition
- Enterprise Edition
- Enterprise Edition High Performance
- Enterprise Edition Extreme Performance

**Two (2) Node RAC Database**

- Enterprise Edition Extreme Performance

- o **Available Storage (GB)**

The minimum recommended size for a JD Edwards EnterpriseOne database is shown in the resource table in the "Before You Begin" section of this Learning Path.

- o **Hostname Prefix**

**Note:** For JD Edwards Enterprise One-Click Provisioning, this host name can have a maximum of 15 alphanumeric *lowercase* characters (special characters such as hyphen (-) are not supported.) You must use this same DNS Hostname Prefix when creating an Orchestration using the JD Edwards EnterpriseOne Provisioning Console.

# Create DB System

**1 DB System Information**

2 Database Information

Provide basic information for the DB system

Select a compartment

JDEE\_TEST

jde (root)/JDEE\_TEST

Name your DB system

jde\_dbsystem

Select an availability domain

<b>AD-1</b> IAUF:PHX-AD-1 ✓	<b>AD-2</b> IAUF:PHX-AD-2	<b>AD-3</b> IAUF:PHX-AD-3
--------------------------------	------------------------------	------------------------------

Select a shape type

<b>Virtual Machine</b> ✓	<b>Bare Metal</b>	<b>Exadata</b>
--------------------------	-------------------	----------------

Select a shape

**VM.Standard2.4** Change Shape  
4 Available Core Count, 1 Node Count

Configure the DB system

Total node count  
1

Oracle Database software edition  
Enterprise Edition Extreme Performance

Choose Storage Management Software

**Oracle Grid Infrastructure**  
Uses Oracle's Storage Management solution. ✓

**Logical Volume Manager**  
Recommended for quick deployments using Logical Volume Manager.

8. On the Create DB System page in the **Database Information** section, complete all required fields. The following are required values for JD Edwards EnterpriseOne:

- o **Database Name**

Enter the value: **orcl**

- o **Database Version**

Select the latest supported database version as listed in the Supported Software Versions section of this Learning Path. For example, **19c**.

- o **PDB Name**

The PDB name can be any value. This can be the same or different than the service name that you set in the tnsnames.ora as prerequisite. That is, the service name must be set as JDEORCL for shared DB in tnsnames.ora.

For example, **JDEORCL**

**Note:** Other than the values specified above, there are no additional special requirements to support JD Edwards EnterpriseOne.

The screenshot shows the 'Create DB System' page in the Oracle Cloud console. The 'Database Information' section is active, and the following fields are highlighted with red boxes:

- Database name:** orcl
- Database image:** Oracle Database 19c
- PDB name:** JDEORCL

The 'Create administrator credentials' section is also visible, showing the following fields:

- Username:** sys
- Password:** (masked with dots)
- Confirm password:** (masked with dots)
- Use the administrator password for the TDE wallet

9. If all the required fields are completed with valid values, click the **Next** button to create the defined DB System.

## Setting Up a DB System

This section shows you how to set up a DB System that you created in the previous module "Creating a DB System in Oracle Cloud Infrastructure" of this Learning Path.

This section describes the general setup tasks that must be performed on the Oracle Cloud Infrastructure database service called DB System. If you are using a Linux-based VM in Oracle Cloud Infrastructure Compute for the Database Server, refer to the Learning Path "*Deploying JD Edwards EnterpriseOne on Oracle Cloud Infrastructure on Linux with Compute Database*".

This module includes the general setup for the primary node of a DB System. Additional setup is required for Real Application Cluster (RAC) and is described in a subsequent module "Setting Up a DB System with RAC" in this Learning Path. Further configuration is required after the One-Click Provisioning is complete. The configuration process is described in the module "Performing Post-Provisioning Tasks" of this Learning Path.

### Prerequisites

- You must have already created a DB System by following the process described in the preceding module "Creating a DB System in Oracle Cloud Infrastructure" of this Learning Path.
- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to *Using the Console*.
- You should have a fundamental understanding of the Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site:

*Oracle Cloud Infrastructure*

- You must have a subscription to Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to:

*Getting Started with Oracle Cloud*

- To access the Oracle Cloud Infrastructure Console, you must use a *supported browser*.

## Setting Up DB Systems with a Single Node

The following prerequisites are required for DB Systems (DBS):

1. Log in to the DBS machine as the **opc** user and use the following command to modify the entries in the `sshd_config` file:

```
$ sudo vi /etc/ssh/sshd_config
```

2. Ensure that the following entries exist in the `sshd_config` file:

```
ClientAliveInterval 3600
```

```
AddressFamily inet
```

3. While still logged in to the DBS machine as the **opc** user, use the following commands to add the `opc` user to the `oracle` group. Grant the required permission to the `/u01` file system:

```
$ sudo groupadd oracle
```

```
$ sudo usermod -a -G oracle opc
```

```
$ sudo usermod -a -G oracle oracle
```

```
$ sudo chmod 775 /u01
```

```
$ sudo chown oracle /u01
```

```
$ sudo chgrp oracle /u01
```

4. While still logged in to the DBS machine as the **opc** user, use the following commands to open the ports required for JD Edwards EnterpriseOne and One-Click Provisioning:

```
sudo iptables -I INPUT -p tcp -m tcp --dport 14502 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 14503 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 14504 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 14505 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 14506 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 14507 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 14508 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 14509 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 14510 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 1521 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 22 -j ACCEPT
```

```
sudo iptables -I INPUT -p tcp -m tcp --dport 5150 -j ACCEPT
```

```
sudo service iptables save
```

**Note:**

- Port numbers 14502 through 14510 are predefined Server Manager inbound ports.
- Port number 22 is the SSH port.
- Port 1521 is the Database Server listener port. If you have created a Database Server instance with a different port, then open that port instead of 1521.
- Port number 5150 is required to support the predefined One-Click Provisioning port.

- Determine the **Database Unique Name** by navigating to the DB Systems instance summary screen of the Oracle Cloud Infrastructure console. This value is displayed in the **Database Unique Name** field, as shown in the following screenshot.

The screenshot displays the Oracle Cloud Infrastructure console for a DBS instance named 'finaldbs'. On the left, there is a green hexagonal logo with 'DBS' in white, and below it, the status 'AVAILABLE'. The main content area is titled 'finaldbs' and contains several buttons: 'Scale Storage Up', 'Add SSH Keys', 'Apply Tag(s)', and 'Terminat...'. Below these buttons is a 'DB System Information' section with a 'Tags' tab. The information includes: Availability Domain: IAUF:PHX-AD-3, Shape: VM.Standard1.8, Compartment: EnterpriseOne\_BM, Oracle Database Software Edition: Enterprise Edition, Available Data Storage: 256 GB, Total Storage Size: 712 GB, Hostname Prefix: finaldbs, and SCAN DNS Name: finaldbs-scan... with a 'Show Copy' link. On the left side, there is a 'Resources' section with a sidebar showing 'Nodes (1)', 'Databases (1)' (selected), and 'Patches (1)'. Below this, the 'Databases' section shows a green square logo with 'DB' and the status 'AVAILABLE', along with a link to 'orcl' and fields for 'Database Home:' and 'Launched:'.

**Note:** In the above example, the value **orcl\_phx34r** is shown in the circled **Database Unique Name** field. In the subsequent examples in this module, this value is referred to as the site variable **< UNQNAME >**.

6. Add environment variables for the **oracle** user by editing the `/home/oracle/.bash_profile` using these commands:

```
$ sudo su - oracle
```

```
$ vi /home/oracle/.bash_profile
```

Typically, a properly completed `.bash_profile` will look like this:

```
export ORACLE_HOME=/u01/app/oracle/product_12.2.0.1/dbhome_1
```

```
export ORACLE_UNQNAME=ORCL_phx1mk
```

```
PATH=$ORACLE_HOME/bin:$PATH
```

```
export PATH
```

Use this command to execute the `.bash_profile` file for the variables to take effect:

```
$ source /home/oracle/.bash_profile
```

Note	
Value	Description
ORACLE_HOME	The <b>ORACLE_HOME</b> environment variable value is typically the software installation directory of your Oracle database, which by default is similar to this: <code>/u01/app/oracle/product/12.2.0.1/dbhome_1</code>
ORACLE_UNQNAME	Refer to Step 5.

7. Log in to the DBS machine as the **oracle** user and run these commands to get the value of the **SERVICE\_NAME**:

```
$ sudo su - oracle
```

```
$ sqlplus system/<DB_ADM_PWD>@<DB_UNIQUE_NAME>
```

```
sql> select name from v$services where PDB='JDEORCL';
```

**Note:** In the example commands above, the value used for the pluggable database name is **JDEORCL**. If the name of your pluggable database is different, adjust the name in the SQL query accordingly.

The value returned by this sequence of commands is the **SERVICE\_NAME**.

8. Make a TNS entry for the pluggable database in the `tnsnames.ora` file located in the `$ORACLE_HOME/network/admin` directory of the DB System. This entry is in addition to the existing entries in the `tnsnames.ora` file.

The TNS entry should be in this format:

```
TNS_NAME =
(DESCRIPTION =
(ADDRESS = (PROTOCOL = TCP) (HOST = DB_HOST) (PORT = DB_PORT))
(CONNECT_DATA =
(SERVER = DEDICATED)
(SERVICE_NAME = SERVICE_NAME)
)
)
```

Note	
Value	Description
TNS_NAME	<p>A net service name that is an alias to your pluggable database name. It can be any unique name not used as an alias in TNS name entries.</p> <p><b>Note:</b>                      For shared schema, the <b>TNS_NAME</b> must be <b>JDEORCL</b> and for non-shared schema it must be other than <b>JDEORCL</b>.</p>
DB_PORT	The database listener port. The default value is 1521.
DB_HOST	<p><b><u>DB System - Standalone</u></b></p> <p>For a Standalone DB System (no RAC), this value is the FQDN host name of the database node. To find the FQDN host name , use the following command:</p> <pre>\$ hostname -f</pre> <p>The returned results will be in this syntax:</p> <pre>jdedbs123 .sub01234567890.yourvcn.oraclevcn.com</pre> <p><b><u>DB System - RAC</u></b></p> <p>For a DB System with RAC, the value shown in the following screenshot is displayed in the <b>SCAN DNS Name</b> field in the Oracle Cloud Infrastructure console of the DB System.</p>

Note	
SERVICE_NAME	Refer to Step 7.

Database » DB Systems » DB System Details

# finaldbs

Scale Storage Up Add SSH Keys Apply Tag(s) Terminate

**DB System Information** Tags

Availability Domain: IAUF:PHX-AD-3  
Shape: VM.Standard1.8  
Compartment: EnterpriseOne\_BM  
Oracle Database Software Edition: Enterprise Edition  
Available Data Storage: 256 GB  
Total Storage Size: 712 GB  
Hostname Prefix: finaldbs  
**SCAN DNS Name: finaldbs-scan.sub0123456789.testdnsvcn.oraclevcn.com** [Hide](#) [Copy](#)

Resources

- Nodes (1)
- Databases (1)**
- Patches (1)
- Patch History (0)

## Databases

**DB** [orcl](#)  
Database Home:  
Launched: AVAILABLE

Following are two examples of a properly completed `tnsnames.ora` file.

### Example: DB System - Standalone

```
JDEORCL =  
  
(DESCRIPTION =  
  
(ADDRESS = (PROTOCOL = TCP)(HOST = jdedbs123.sub0123456789.testdnsvcn.oraclevcn.com)(PORT = 1521))  
  
(CONNECT_DATA =
```

```
(SERVER = DEDICATED)

(SERVICE_NAME = JDEORCL.sub0123456789.testdnsvcn.oraclevcn.com)

)

)
```

### Example: DB System- RAC

```
JDEORCL =

(DESCRIPTION =

(AADDRESS = (PROTOCOL = TCP)(HOST = dbsrc14-scan.sub0123456789.testdnsvcn.oraclevcn.com)

(PORT = 1521))

(CONNECT_DATA =

(SERVER = DEDICATED)

(SERVICE_NAME = JDEORCL.sub0123456789.testdnsvcn.oraclevcn.com)

)

)
```

9. You must ensure that the search setting in the `/etc/resolv.conf` file specifies the DNS domain name of the Availability Domain to which all JD Edwards EnterpriseOne servers belong. While logged in as root (the owner of the `resolv.conf` file), you must add a line with this syntax:

```
search <DNS_Domain_Name> <subnet>.<DNS_Domain_Name>
```

Because each region has at least three subnets, you must specify the exact subnet in which your JD Edwards EnterpriseOne servers are running.

For example, your subnets can look like this:

The screenshot displays the Oracle Cloud Infrastructure console. On the left, a sidebar shows a navigation menu with 'Subnets (3)' selected. The main content area is divided into two sections. The top section shows a VCN (Virtual Cloud Network) with a green hexagonal icon containing 'VCN' and the status 'AVAILABLE'. To the right of the VCN icon are buttons for 'Terminate' and 'Apply Tag(s)'. Below the VCN icon, there is a 'VCN Information' tab and a 'Tags' tab. The 'VCN Information' tab is active, showing the following details: 'CIDR Block: 10.0.0.0/16', 'Compartment: EnterpriseOne\_BM', and 'Created:'. The bottom section is titled 'Subnets in EnterpriseOne\_BM Compartment' and features a 'Create Subnet' button. Below this, there is a 'Sort by:' dropdown menu set to 'Created Date (Desc)'. A table lists three subnets, each with a green hexagonal icon containing an 'S' and the status 'AVAILABLE'. The subnets are: 1. 'Public Subnet IAUF-PHX-AD-3' with CIDR Block 10.0.2.0/24, Virtual Router MAC Address 00:00, and DNS Domain sub0123456. 2. 'Public Subnet IAUF-PHX-AD-2' with CIDR Block 10.0.1.0/24, Virtual Router MAC Address 00:00, and DNS Domain sub0123456. 3. 'Public Subnet IAUF-PHX-AD-1' with CIDR Block 10.0.0.0/24, Virtual Router MAC Address 00:00, and DNS Domain sub0123456. The 'DNS Domain' and 'Subnet Acc' columns for each subnet are highlighted with a red box.

Using the above example, assuming that your JD Edwards EnterpriseOne Servers are running in the Phoenix Availability Domain, you would edit your /etc/resolve.conf file to add a line with a search setting similar to the setting shown below to include all the three domains:

```
search testdnsvcn.oraclevcn.com sub012345678900.testdnsvcn.oraclevcn.com
sub012345678901.testdnsvcn.oraclevcn.com sub012345678902.testdnsvcn.oraclevcn.com
```

10. From a SQL prompt on the DBS machine, use these commands to allocate recovery space for archive logging::

- o Log in as the **oracle** user using this command:

```
$ sudo su - oracle
```

- o Log in to the database using this command:

```
$ sqlplus sys/<DB_ADM_PWD>@<DB_UNIQUE_NAME> as sysdba;
```

- o Set the recovery space using this command:

```
sql> ALTER SYSTEM SET db_recovery_file_dest_size=50G SCOPE=BOTH;
```

- o Verify the available and used recovery space using this command:

```
sql> SELECT * FROM V$RECOVERY_FILE_DEST;
```

For example, if you set the recovery space to 50 GB and install a full complement of pathcodes (SHARED, PS, DV, PY), issuing this command returns these results which show that the space limit is approximately 54 GB with 48 GB in use.

```
NAME
-----
SPACE_LIMIT SPACE_USED SPACE_RECLAIMABLE NUMBER_OF_FILES CON_ID
-----
+RECO
5.3687E+10 4.7264E+10 0 53 0
```

11. From a SQL prompt on the DBS machine, use these commands to set number of processes:

- o Set the number of processes to 1500 using this command:

```
sql> alter system set processes=1500 scope=spfile;
```

12. From a SQL prompt on the DBS machine, use these commands to set PGA\_AGGREGATE\_LIMIT to 15GB

- o Set the PGA\_AGGREGATE\_LIMIT using this command:

```
sql> alter system set pga_aggregate_limit=15G scope=spfile;
```

13. Check whether the temporary tablespace with name 'TEMP' is available by running following sequence of commands:

- o Use this command to log in to sqlplus as the system user at the PDB Level:

```
sqlplus system/<db_adm_pwd>@JDEORCL
```

- o Run the following query to check temporary for the existence of a tablespace with name 'TEMP':

```
SELECT TABLESPACE_NAME from DBA_TABLESPACES
```

where TABLESPACE\_NAME='TEMP'

- o If the tablespace query does not output results that a temporary tablespace exists with name 'TEMP', run the following command as a single contiguous line with no returns:

```
CREATE TEMPORARY TABLESPACE TEMP TEMPFILE 'jdetemp.dbf' SIZE 500m
autoextend on next 10m maxsize unlimited
```

If the command executes correctly, it should output results like "Tablespace Created".

## Setting Up a DB System with RAC

This section shows you how to set up a DB System on Oracle Cloud Infrastructure with an Oracle Real Application Cluster (RAC).

This section describes the general setup tasks that must be performed on the Oracle Cloud Infrastructure database service called DB System (DBS). If you are using a Linux-based VM in Oracle Cloud Infrastructure Compute for the Database Server, refer to the Learning Path "[Deploying JD Edwards EnterpriseOne on Oracle Cloud Infrastructure on Linux with Compute Database](#)".

You will need to perform setup on the primary and secondary nodes of DBS as described by following the steps described in these sections:

- Setting Up the Primary Node
- Setting Up the Secondary Node
- Stopping the Database in the Secondary Node

### Prerequisites

- You must have previously created a DB System by following the process described in the preceding module "Creating a DB System in Oracle Cloud Infrastructure" of this Learning Path .
- You must have specified more than one node when you created the DB System by following the process described in the preceding module "Creating a DB System in Oracle Cloud Infrastructure" of this Learning Path.
- You must have set up a DB System by following the process described in the preceding module "Setting up a DB System".
- You should have a fundamental understanding of the Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site:

[Oracle Cloud Infrastructure](#)

- You must have a subscription to Oracle Cloud Infrastructure and an Administrator account in the platform. For more information, refer to this site:

[Getting Started with Oracle Cloud](#)

- To access the Oracle Cloud Infrastructure Console, you must use a [supported browser](#).

## Setting Up the Primary Node

To use a RAC in your DB System (also called DBaaS in industry terms), you must have enabled DNS in your VCN and therefore have DNS subnets. This step is necessary because VM shapes must be used for DB Systems and are not supported on non-DNS subnets.

**Note:** This section describes the setup tasks that must be performed in the Oracle Compute Infrastructure database service called DB System. If you are using a Linux-based VM in Oracle Cloud Infrastructure Compute for the Database Server, refer to the Learning Path "[Deploying JD Edwards EnterpriseOne on Oracle Cloud Infrastructure on Linux with Compute Database](#)".

The deployment of an RAC instance using the Oracle Cloud Infrastructure console creates a primary node and a secondary node in the cluster. Consider the node that has the instance name as its name with the suffix 1 as the primary node and the node with the suffix 2 as the secondary node.

To set up a DB System with a RAC, ensure that you have completed the following tasks which are described in the module "Setting up a DB System", which applies to setting up the primary node.


- Created the requisite groups and users and set permissions and ownership on /u01
- Opened the required ports in the firewall
- Edited the .bash\_profile file
- Edited the /etc/resolv.conf file
- Edited the tnsnames.ora file
- Allocated recovery space for archive logging
- Set the number of processes
- Set the PGA\_AGGREGATE\_LIMIT

## Setting Up the Secondary Node

The deployment of an RAC instance using the Oracle Cloud Infrastructure console creates a primary node and a secondary node in the cluster. This procedure describes how to set up the secondary node. Consider the node that has the instance name as its name with the suffix 1 as the primary node and the node with the suffix 2 as the secondary node.

**Note:** After you complete the configuration described in this procedure, you must shut down the secondary node (node 2) prior to deploying One-Click Provisioning for Oracle Cloud Infrastructure by following the procedure described in the next section "Stopping the Database in the Secondary Node".

1. Determine the **Database Unique Name** by navigating to the DB Systems instance summary screen of the Oracle Cloud Infrastructure console.



**finaldbs**

Scale Storage Up Add SSH Keys Apply Tag(s) Termina

**DB System Information** Tags

**Availability Domain:** IAUF:PHX-AD-3

**Shape:** VM.Standard1.8

**Compartment:** EnterpriseOne\_BM

**Oracle Database Software Edition:** Enterprise Edition

**Available Data Storage:** 256 GB

**Total Storage Size:** 712 GB

**Hostname Prefix:** finaldbs

**SCAN DNS Name:** finaldbs-scan... [Show](#) [Copy](#)

**Resources**

- Nodes (1)
- Databases (1)**
- Patches (1)

**Databases**

**DB** [orcl](#)

**Database Home:**

**Launched:**

AVAILABLE

**Note:** In the above example, the value **orcl\_phx34r** is the Database Unique Name. In subsequent examples, this value is referred to as the site variable **<DB\_UNIQUE\_NAME>**.

2. Add environment variables for the **oracle** user by editing `/home/oracle/.bash_profile` using these commands:

```
$ sudo su - oracle
```

```
$ vi /home/oracle/.bash_profile
```

3. Use this command to execute the `.bash_profile` file for the variables to take effect:

```
$ source /home/oracle/.bash_profile
```

Typically, a properly completed `.bash_profile` will look like this:

```
export ORACLE_HOME=/u01/app/oracle/product/dbhome_1
```

```
export ORACLE_UNQNAME=ORCL_phx1mk
```

```
PATH=$ORACLE_HOME/bin:$PATH
```

```
export PATH
```

Value	Description
ORACLE_HOME	The <b>ORACLE_HOME</b> environment variable value is typically the software installation directory of your Oracle database. By default, the directory structure is: <code>/u01/app/oracle/product/12.2.0.1/dbhome_1</code>
DB_UNIQUE_NAME	Refer to Step 1.

4. Make a TNS entry for the pluggable database in the `tnsnames.ora` file located in the `$ORACLE_HOME/network/admin` directory of the DB System. This entry is in addition to the existing entries in the `tnsnames.ora` file.

Copy the `tnsnames.ora` entry you had made for the pluggable database in the primary node into the `tnsnames.ora` of this node.

In the preceding example in this document, the TNS entry for the pluggable database in the `tnsnames.ora` file was:

```
JDEORCL =  
  
(DESCRIPTION =  
  
(ADDRESS = (PROTOCOL = TCP) (HOST = dbsrc14-scan.sub06220506330.testdnsvcn.oraclevcn.com) (PORT = 1521))  
  
(CONNECT_DATA =  
  
(SERVER = DEDICATED)  
  
(SERVICE_NAME = JDEORCL.sub06220506332.testdnsvcn.oraclevcn.com)  
  
)  
  
)
```

- You must ensure that the search setting in the `/etc/resolv.conf` file specifies the DNS domain name of the Availability Domain to which all the JD Edwards EnterpriseOne servers belong. While logged in as the `opc` user, you must edit the file and add a line with this syntax:

```
$ vi /etc/resolv.conf
```

```
search <DNS_Domain_Name> <subnet>.<DNS_Domain_Name>
```

Because each region has at least three subnets, you must specify the exact subnet in which your JD Edwards EnterpriseOne servers are running. For example, your subnets can look like this:

The screenshot displays the Oracle Cloud console interface. On the left, a sidebar shows navigation options under 'Resources' and 'List Scope'. The main area is divided into two sections: 'VCN Information' and 'Subnets in EnterpriseOne\_BM Compartment'.

**VCN Information:** A green hexagonal icon with 'VCN' and 'AVAILABLE' below it. To the right are 'Terminate' and 'Apply Tag(s)' buttons. Below are tabs for 'VCN Information' and 'Tags'. The information includes:
 

- CIDR Block: 10.0.0.0/16
- Compartment: EnterpriseOne\_BM
- Created: Thu, 22 Jun 2017 05:06:34 GMT

**Subnets in EnterpriseOne\_BM Compartment:** A blue 'Create Subnet' button is at the top. Below is a 'Sort by: Created Date (Desc)' dropdown. A table lists three subnets, each with a green 'S' icon and 'AVAILABLE' status.
 

Subnet Name	CIDR Block	Virtual Router MAC Address	Availability
Public Subnet IAUF-PHX-AD-3 OCID: ...2ags6q	10.0.2.0/24	00:00:17:A6:C8:3B	DNS Domain: sub0622050
Public Subnet IAUF-PHX-AD-2 OCID: ...6pvz3a	10.0.1.0/24	00:00:17:A6:C8:3B	DNS Domain: sub0622050
Public Subnet IAUF-PHX-AD-1 OCID: ...lkw4ca	10.0.0.0/24	00:00:17:A6:C8:3B	DNS Domain: sub0622050

**Resources:**

- Subnets (3)
- Route Tables (1)
- Internet Gateways (1)
- Dynamic Routing Gateways (0)
- Security Lists (1)
- DHCP Options (1)
- Local Peering Gateways (0)

**List Scope:** COMPARTMENT: EnterpriseOne\_BM

Using the above example, assuming that your JD Edwards EnterpriseOne Servers are running in the Phoenix Availability Domain 2 (labeled as **IAUF:PHX-AD-2**), you would edit your `/etc/resolve.conf` file to add a line with a search setting similar to the setting below:

```
search testdnsvcn.oraclevcn.com sub06220506331.testdnsvcn.oraclevcn.com
```

**Tip:** Retrieve a host name

1. Run the `hostname` command and note the output.
2. Run the `nslookup` command using the output of Step 1 as the first argument.

The host name is specified in the **Name** field of the output from the `nslookup` command.

For example:

```
root@my_machine share]# hostname

mymachine

[root@my_machine share]# nslookup mymachine

Server: 11.111.11.111

Address: 11.111.11.111#11

Non-authoritative answer:

Name: mymachine.us.oraclecx.com

Address: 11.111.111.111
```

## Stopping the Database in the Secondary Node

At this point, prior to deploying One-Click Provisioning for Oracle Cloud Infrastructure, you must stop the database that is running in the secondary node for the RAC.

**Note:** It is *not* recommended to use the user interface in Oracle Cloud Infrastructure to shut down the secondary node because this can cause a delay in synchronization between the nodes upon deployment and during fail over scenarios.

The recommended procedure to stop the database is to use this line command:

```
srvctl stop instance -d <DB_UNIQUE_NAME> -i <DB_NAME>
```

Where


- `<DB_UNIQUE_NAME>` is the name you determined in the preceding section in this OBE "*Setting Up the Secondary Node*".
- `<DB_NAME>` is the name you have given the database and which is appended with the number 2. For example, if you gave the database the name ORCL, then the database in the secondary node is named ORCL2.

---

**Note:** After One-Click Provisioning completes the deployment of JD Edwards EnterpriseOne, you will need to start the secondary node by following the process documented in the OBE "Performing Post-Provisioning Tasks", in the section "Accessing the Provisioned Servers".

To view details of the secondary node in the RAC:

1. On the Oracle Cloud Infrastructure Console Home page, click the navigation menu in the upper-left corner.



2. From the navigation menu, in the **Database** section, select **Bare Metal, VM, and Exadata**.

3. In the left panel, ensure that DB Systems is selected, and under **List Scope**, the applicable **COMPARTMENT** is selected which contains the DB System with RAC that you created contains the DB System that you created with a RAC.
4. Click the link for your DB System with a RAC.

5. In the **Resources** section in the left pane, click **Nodes**.

The details for the two nodes are displayed as shown below:

The screenshot displays the Oracle Cloud Infrastructure console for a DBS system named 'dbs2rac'. On the left, a large green hexagonal icon with 'DBS' in white is shown with the status 'AVAILABLE' below it. The main area shows the node name 'dbs2rac' and several action buttons: 'Scale Storage Up', 'Add SSH Keys', 'Apply Tag(s)', and 'Terminate'. Below these are two tabs: 'DB System Information' (selected) and 'Tags'. The 'DB System Information' tab lists the following details: Availability Domain: IAUF:PHX-AD-2, Shape: VM.Standard2.2, Compartment: EnterpriseOne\_BM, Oracle Database Software Edition: Enterprise Edition Extreme Performance, Available Data Storage: 512 GB, Total Storage Size: 1168 GB, Port: (redacted), Host Domain Name: (redacted), and Scan IP Addresses: (redacted). At the bottom left, a 'Resources' sidebar lists 'Nodes (2)', 'Databases (1)', 'Patches (1)', and 'Patch History (0)'. The 'Nodes' section at the bottom right shows two nodes: 'dbs2rac2' (OCID: ...cqj46q) and 'dbs2rac1' (OCID: ...466pja), both with 'AVAILABLE' status and redacted IP addresses.

6. As previously mentioned, the secondary node is identified with the suffix 2.



# 8 Preparing the Microsoft Windows Deployment Server

## Creating a Windows VM in Oracle Cloud Infrastructure

This section describes how to create a Microsoft Windows instance in Oracle Cloud Infrastructure.

Oracle Cloud Infrastructure Compute lets you provision and manage compute hosts, known as instances.

**Note:** While Oracle Cloud Infrastructure offers both Bare Metal and Virtual Machine instances, the current version of One-Click Provisioning for Oracle Cloud Infrastructure only supports Virtual Machine instances.

For additional information refer to [Creating an Instance](#).

In preparation for JD Edwards EnterpriseOne One-Click Provisioning, each installation **must** create a Microsoft Windows VM instance in Oracle Cloud Infrastructure Compute for the Deployment Server, which is a JD Edwards EnterpriseOne core server.

### Creating a Windows VM Instance in Oracle Cloud Infrastructure


With the following exceptions, the procedure for creating a Microsoft Windows instance as a VM is specified in the OBE in this Learning Path entitled "Creating the Linux Instance for the One-Click Provisioning Server".

#### Exception 1: Change Image for Microsoft Windows Server

Instead of having the requisite Operating System version automatically selected when you are installing from a Marketplace image for the Provisioning Server, you must manually select a specific image that is certified with JD

Edwards EnterpriseOne. Refer to the "Supported Software Versions" section of this Learning Path for the supported release of Microsoft Windows Server.

1. On Create Compute Instance, in the **Image** section, click the **Change Image** button.



2. On Browse All Images:
  - o In the **Image name** column, click the **Windows** checkbox.
  - o In the **OS version** column, use the pull-down to select the supported version as specified in the "Supported Software Versions" section of this Learning Path. For example, **Server 2019 Standard**.
  - o In the **Image build** column, use the pull-down to select the latest build. For example, **2021.03.17-0**.
3. Click the **Select Image** button.

### Exception 2: Login Credentials

Upon creating this Microsoft Windows instance, both a user name and an initial password will be generated for you. They will be available on the details screen for the newly launched Instance. You must create a new password upon logging into the instance for the first time.

### Exception 3: Sizing the VM

You must size the VM for the Deployment Server per the Minimum Resource Requirements, which currently states a value of 256 GB.

When you are creating the Windows VM instance, in the "Boot volume" section:

1. Select the option "Specify a custom boot volume size".
2. In the "Boot volume size (GB)" field, enter the value 256 .

3. If it is selected by default, remove the selection for option “Use in-transit encryption”. Neither encryption checkbox should be selected.

**ORACLE Cloud** Search for resources, services, and documentation

## Create compute instance

### Boot volume

A [boot volume](#) is a detachable device that contains the image used to boot the compute instance.

Specify a custom boot volume size  
[Volume performance](#) varies with volume size. Default boot volume size: 47.0 GB. When you specify a custom boot volume size, service limits a

**Boot volume size (GB)**  
256  
Integer between 50 GB and 32,768 GB (32 TB). Must be larger than the default boot volume size for the selected image.

Use in-transit encryption  
[Encrypts data](#) in transit between the instance, the boot volume, and the block volumes.

Encrypt this volume with a key that you manage  
By default, Oracle manages the keys that encrypt this volume, but you can choose a key from a vault that you have access to if you want greater control over the key's lifecycle and how it's used. [How do I manage my own encryption keys?](#)

**Create** Save as stack [Cancel](#)

[Terms of Use and Privacy](#) [Cookie Preferences](#)



# 9 Configuring the Microsoft Windows Deployment Server

## Logging in to the Windows VM

This section shows you how to log in to the Microsoft Windows virtual machine (VM) in Oracle Cloud Infrastructure.

### Prerequisite

You must have previously created a Microsoft Windows VM in Oracle Cloud Infrastructure as described in the previous module of this Learning Path entitled: *Creating a Windows VM in Oracle Cloud Infrastructure*.

### Log in to the Windows VM


1. Connect to the Microsoft Windows VM in Oracle Cloud Infrastructure with a Remote Desktop Protocol (RDP) connection using this command in a Command Window:

```
mstsc /f
```

2. On Remote Desktop Connection, complete these fields:

o **Computer**


Enter the Public IP Address which can be derived from the Instance Details for the Microsoft Windows Instance for the Deployment Server in the **Public IP Address** field.



o **User name**


Enter the value **opc**.

3. Click the **Connect** button.




4. You are prompted to enter a password. This is the password that the system assigned upon creation of the Windows VM. On the **Instance Details** screen for the Windows VM that you created, locate the **Initial password** field.

5. In the **Initial password** field, click to expand more options and click the **Copy** option to copy the password.




6. On Remote Desktop Connection, enter `opc` as the user and paste the copied password.




7. After you enter the credentials the first time you log in, you are prompted to change the password:

**The user's password must be changed before signing in.**



8. Change the password for the **opc** user following the Microsoft Windows policy for creating a user password.

**Note:** The Password must contain at least 12 characters and must be comprised of at least one lower case letter, one upper case letter, one numeric digit, and one special character (for example; special characters could be \_ @ ~ ! # % \* +. Be sure and make a note of this password because you will need to use this same password later in the One-Click Provisioning Console.



## Running Commands to Change Microsoft Windows Settings

This section shows you how to run commands to change Microsoft Windows settings.

### Prerequisites

- You must have access to a physical or virtual Windows machine dedicated for use as a JD Edwards EnterpriseOne Deployment Server.
- You must be able to connect to the Microsoft Windows machine using a Remote Desktop Protocol (RDP) session from a Microsoft Windows client machine.

## Enable Remote Command Execution Through Microsoft PowerShell

From Microsoft PowerShell, use this command to enable remote command execution:

```
winrm quickconfig -q
```

## Enable Inbound Ports in the Firewall


If you have the Microsoft Windows firewall enabled for any profile (public, private, default), which is recommended, in order for One-Click Provisioning to deploy to the Deployment Server and for JD Edwards EnterpriseOne runtime to function properly, you will need to explicitly open Inbound and Outbound ports.

Use this procedure to open the Inbound ports for **each** Microsoft Windows instance.

1. Go to Administrative Tools > Windows Firewall with Advanced Security.
2. In the left pane, highlight **Inbound Rules**.
3. In the right pane, Actions, Inbound Rules, click **New Rule ...**
4. On Rule Type, select the **Port** radio button as the type of rule to create.
5. Click the **Next** button.
6. On Protocol and Ports:
  - o You can accept the default value of **TCP** for the protocol to which this rule applies.
  - o Choose the radio button for **Specific local ports** and, for **each** Windows Server, enter each of the ports shown in the following table, separated by a comma.

Windows Server Firewall Port List	
Component	Inbound Ports to Open
Deployment Server	445 3389 5150 5985 6017-6022 14502-14510

The following example shows the ports you should specify for the Deployment Server.



7. Click the **Next** button.
8. On Action, you can accept the default value which is **Allow the connection**.
9. Click the **Next** button.
10. On Profile, select all firewall profile options (**Domain, Private, Public**).
11. Specify a name for the rule. For example, **JDESMC\_RDP**.
12. Click the **Finish** button to save the rule and exit the wizard.


## Enable Outbound Ports in the Firewall

If you have the Microsoft Windows firewall enabled for any profile (public, private, default), which is recommended, in order for One-Click Provisioning to deploy to the Deployment Server and for JD Edwards EnterpriseOne run-time to function properly, you will need to explicitly open Inbound and Outbound ports.

Use this procedure to open the Outbound ports in your Microsoft Windows instance.

1. Go to Administrative Tools > Windows Firewall with Advanced Security.
2. In the left pane, highlight **Outbound Rules**.

3. In the right pane, Actions, click **New Rule ...**
4. On Rule Type, select the **Port** option as the type of rule to create.
5. Click the **Next** button.
6. On Protocol and Ports:
  - o You can accept the default value of **TCP** for the protocol to which this rule applies.
  - o Choose the option for **All remote ports**.



7. On Action, you can accept the default value which is **Allow the connection**.
8. Click the **Next** button.
9. On Profile, select all firewall profile options (**Domain, Private, Public**).
10. Specify a name for the rule.
11. Click the **Finish** button to save the rule and exit the wizard.

## Configure Settings for Ethernet Connections

You must configure settings for Ethernet connection to specify the domain name of the Domain Name System (DNS) for the Availability Domain to which all JD Edwards EnterpriseOne servers belong.

For example, if your subnets look like that shown in the example below, you must configure your Network Settings using this procedure:


The screenshot displays the Oracle Cloud console interface. On the left, a sidebar shows navigation options: Resources, Subnets (3), Route Tables (1), Internet Gateways (1), Dynamic Routing Gateways (0), Security Lists (1), DHCP Options (1), and Local Peering Gateways (0). Below this is a 'List Scope' section with a 'COMPARTMENT' dropdown set to 'EnterpriseOne\_BM'. The main content area shows a 'VCN' card with a green 'AVAILABLE' status and buttons for 'Terminate' and 'Apply Tag(s)'. Below the VCN card, there are tabs for 'VCN Information' and 'Tags'. The 'VCN Information' tab shows: CIDR Block: 10.0.0.0/16, Compartment: EnterpriseOne\_BM, and Created: [timestamp].

The main section is titled 'Subnets in EnterpriseOne\_BM Compartment' and includes a 'Create Subnet' button. A 'Sort by:' dropdown is set to 'Created Date (Desc)'. Below this is a table of three subnets:

Subnet Name	CIDR Block	Virtual Router MAC Address	Availability Domain	DNS Domain Name	Subnet Access
Public Subnet IAUF:PHX-AD-3	10.0.2.0/24	[MAC Address]	IAUF:PHX-AD-3	sub06220506332.testdnsvcn.oraclevcn.com	Public Subnet
Public Subnet IAUF:PHX-AD-2	10.0.1.0/24	[MAC Address]	IAUF:PHX-AD-2	sub06220506331.testdnsvcn.oraclevcn.com	Public Subnet
Public Subnet IAUF:PHX-AD-1	10.0.0.0/24	[MAC Address]	IAUF:PHX-AD-1	sub06220506330.testdnsvcn.oraclevcn.com	Public Subnet


1. Open **Network and Sharing Center**.

2. On Ethernet settings, in Network > Connections, click **Ethernet** to open **Ethernet Status**.




3. On Ethernet Status, click the **Properties** button.

4. On Ethernet Properties, highlight this line: **Internet Protocol Version 4 (TCP/IPv4)** and click the **Properties** button.



5. On Internet Protocol Version 4 (TCP/IPv4) Properties, click the **Advanced** button.




6. On Advanced TCP/IP Settings, click to enable this option: **Append these DNS suffixes (in order)**; and click the **Add** button.
7. On the TCP/IP Domain Suffix dialog, enter the value of the DNS Domain Name for your Availability Domain. For example, assuming your subnets were as shown in the preceding screen showing the subnets for each Availability Domain and all servers are created in **sub0622506330.testdnsvcn.oraclevcn.com** subnet, you would enter this value for the suffix:

`sub0622506330.testdnsvcn.oraclevcn.com`

8. Click the **Add** button to add the DNS suffix.

9. Add this same subnet (in this example, **sub0622506330.testdnsvcn.oraclevcn.com**) in the field labelled **DNS suffix for this connection**.



10. Click the **OK** button to accept the values and exit the **Network and Sharing Center**.

## Change Security Option

If you chose a user other than **opc** when for the One-Click Provisioning deployment of your Deployment Server, use this procedure to change the Microsoft Windows security option so that user will be recognized by JD Edwards EnterpriseOne.

1. Log in to the Deployment Server as the user you configured, which is other than the **opc** user.
2. Open the Microsoft Windows **Local Security Policy** program from Start > Run, or from a Command Prompt:


```
secpol.msc
```

3. On Local Security Policy, navigate to Local Policies > Security Options.
4. Locate and edit this setting:

**Network Security: LAN Manager authentication level**

5. Use the pulldown to select this setting:

### Send NTLM V2 response only



6. Click the **Apply** button to save the setting.

## Change the Maximum Transmission Unit (MTU) Setting

The recommended MTU setting is 1500. Use this procedure to check, and if necessary, change the current MTU setting.

1. Open Windows PowerShell as Administrator and run the following command (as a single contiguous line) to check the current value of the MTU setting:

```
Get-NetIPInterface | where {($_.InterfaceAlias -eq "Ethernet") -and ($_.AddressFamily -eq "IPv4") -and ($_.NlMtu -Gt 0)}
```

2. If the returned value is not set to 1500, run this command (as a single contiguous line) to set the MTU value to 1500:

```
Get-NetIPInterface | where {($_.InterfaceAlias -eq "Ethernet") -and ($_.AddressFamily -eq "IPv4") -and  
($_.NlMtu -Gt 0)} | Set-NetIPInterface -NlMtuBytes 1500
```

# 10 Using the One-Click Provisioning Server

## Configure CA Certificates for One-Click UI (Optional)

This section shows you how to configure CA Certificates for the One-Click User Interface. This task is optional.

JD Edwards EnterpriseOne One-Click Provisioning can be configured with a supplied CA certificate. However, after initial installation you must obtain your own CA certificates. These must be certificates that are verified by a verified CA authority such as Entrust and Symantec Corporation.

### Prerequisite

You must obtain CA certificates and their chain of deliverables.

## Configuring CA Certificates for One-Click UI (Optional)

Use this procedure to configure CA certificates for the One-Click Provisioning user interface. This step is not required for initial installation but is required for subsequent usage of JD Edwards EnterpriseOne in Oracle Cloud Infrastructure.

1. Combine the contents of `rootca.pem` and `intermediateca.pem` certificates to a file named `ca-cert.pem` file as per order from the CA authority.
2. Rename `.net.key` to `key.pem`.
3. Rename `<variable>.crt` to `cert.pem`.
4. Copy `ca-cert.pem`, `key.pem` and `cert.pem` to this directory:

```
/E1CloudConsole/keys
```

5. Restart the Provisioning Server:
  - o **Linux-based Provisioning Server**

Restart the E1CloudConsole.service using following command:

```
sudo systemctl stop E1CloudConsole.service sudo systemctl start E1CloudConsole.service
```

- o **Microsoft Windows-based Provisioning Server**

Use these steps to restart the user interface:

- Navigate to this directory:

```
\JDE\bin
```
- Open Powershell with Administrator rights.
- Run this script:

```
.\E1CloudConsoleWin.ps1
```

## Accessing the JD Edwards Provisioning Console

This section shows you how to access the JD Edwards Provisioning Console.

As described in the the subsequent OBEs in this Learning Path, you will access and use the Provisioning Console to set up a completely functional EnterpriseOne environment using the JD Edwards One-Click Provisioning Console by performing these three steps:

- Configure – Provide the Server Manager details.
- Orchestrate – Create the deployment plan.
- Deploy – Initiate the scripts for the automated provisioning of the EnterpriseOne system.

### Prerequisites

- You should have a fundamental understanding of the Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site: [Oracle Cloud Infrastructure](#)
- You must have a subscription and an Administrator account to Oracle Cloud Infrastructure as described at this site: [Getting Started with Oracle Cloud Applications](#)
- To access the Provisioning Console, you must use a supported browser. See **Supported Browsers** in [Troubleshooting Signing In to the Console](#).

## Accessing the JD Edwards Provisioning Console

The recommended browsers for accessing the One-Click Provisioning Console are:


- Google Chrome
- Mozilla Firefox

Open the browser and connect to the URL using this syntax:

`https://XXX.XXX.XXX.XXX:3000`

Where:

- **https** is the only supported browser protocol.
- **XXX.XXX.XXX.XXX** is the public IP address for the One-Click Provisioning Server Instance. This IP address is shown in the Oracle Cloud Infrastructure user interface on the Instance Details screen for the instance that you created for the One-Click Provisioning Server, as shown in the below example:



The screenshot displays the Oracle Cloud Infrastructure console interface. At the top, there is a navigation bar with the Oracle Cloud Infrastructure logo, a search bar, and a location dropdown set to 'us-phoenix-1'. Below the navigation bar, the breadcrumb trail reads 'Compute » Instances » Instance Details'. The main content area shows the instance 'JDEPP' with a green 'RUNNING' status indicator. A row of action buttons includes 'Create Custom Image', 'Start', 'Stop', 'Reboot', 'Terminate', 'Apply Tag(s)', and 'Create Instance Configuration'. The 'Instance Information' tab is selected, showing the following details:

- Instance Information**
- Availability Domain: IAUF-PHX-AD-1
- Fault Domain: FAULT-DOMAIN-1
- Region: phx
- Shape: VM.Standard2.1
- Virtual Cloud Network: [Redacted]
- Maintenance Reboot: -
- Image: [Redacted]
- OCID: [Redacted] [Show Copy](#)
- Launched: [Redacted]
- Compartment: [Redacted]
- Launch Mode: NATIVE
- Primary VNIC Information
- Private IP Address: [Redacted]
- Public IP Address: XXX.XXX.XXX.XXX
- Internal FQDN: jdepp... [Show Copy](#)
- Subnet: [Public Subnet IAUF-PHX-AD-1](#)

*This Instance's traffic is controlled by its firewall rules in addition to the associated [Subnet's Security Lists](#).*

- **3000** is the port on which the One-Click Provisioning Server is running, and which you must include as part of the address.

**Note:** Should you exit the Provisioning Console or experience a timeout, the next time you enter the Provisioning Console it displays the point where you left off. When you click the **Configure** icon, you will be prompted for the same credentials that you entered during your first access to the One-Click Provisioning Console.

## Configuring the Server Manager Account

This tutorial shows how to configure the Server Manager account in JD Edwards One-Click Provisioning Console.

### *Configuring the Server Manager Account*

## Configuring the Server Manager Account

This section shows how to configure the Server Manager account in JD Edwards One-Click Provisioning Console.

If you are a new user, you are required to change the administrator passwords for WebLogic Server and Server Manager Console. Remember the Server Manager password you entered in the Change Password window for future logins.


### **Prerequisite**

Downloaded the One-Click archive files from the Oracle Software Delivery Cloud (also called OSDC or E-Delivery). For more information see the section entitled: **Setting Up the Provisioning Server** .

## Configure the Server Manager Account

Use this procedure to provide the account information.

1. On Welcome to the JD Edwards Provisioning Console, click the **Configure** icon.



2. If you are a new user, as prompted by the JD Edwards Provisioning Console, you are also required to change the administrator passwords for WebLogic Server and Server Manager Console.

On Change Password, enter the passwords for the Server Manager Administrator. The password must only have numbers, alphabets, and special characters (@,!,\$,\_,#), and is between 8 and 30 characters long.


Also, enter the password for the WebLogic Server. The password must start with a letter, is between 8 and 30 characters long, contains at least one number, and optionally, any number of special characters (#,\_,). For example, Ach1z0#d

**Note:** The password for any WebLogic Server user cannot contain the \$ or ! character. Using either of these characters violates the Oracle password policy and will result in denied access.


**Tip:** Valid values for the passwords are displayed in the tooltip when you click the field.

Click the **OK** button.

**Note:** The system displays a message indicating that is changing default passwords; this may take a few minutes to complete before the next screen is displayed.




3. On the Success window, click the **OK** button.



4. On Oracle JD Edwards Server Manager Details, reenter the Admin password for the Server Manager Console. The SMC Endpoint is pre-populated automatically.

**Note:** It is recommended that you record this value on the Pre-Install Worksheet, which you created as described in the companion document to this tutorial in the section entitled: Create the **Pre-Install Worksheet**.



5. Click the **Save Configuration** button.

The system will take some time to authenticate the Server Manager Endpoint and Credentials. When the authentication is verified, click the **OK** button on the **Congratulations** box.

The screenshot shows the Oracle JD Edwards Provisioning Console interface. At the top left, there is a 'Cancel' button. Below it, the section is titled 'Oracle JD Edwards Server Manager Details' with a sub-instruction: 'Enter your Server Manager User Name, Password, and REST endpoint details to start creating your orchestration.' The main form area is titled 'JD Edwards Server Manager Details' and contains three input fields: '\* User Name' with the value 'jde\_admin', '\* Password' with masked characters, and '\* SMC Endpoint' with the value 'https://prov4akshya:8998/manage/mgr'. A 'Congratulations' dialog box is overlaid on the right side of the form, containing the text: 'You have successfully configured your account. You can now orchestrate your servers.' and an 'OK' button.

# 11 Creating a Deployment Plan

## Orchestrating a Quick Start Deployment Plan

This tutorial shows how to create a Quick Start deployment plan on Oracle Cloud Infrastructure on Linux using the JD Edwards One-Click Provisioning Console.

*Orchestrating a Quick Start Deployment Plan Using an Oracle Database*

## Orchestrating Using Quick Start Mode

This section shows you how to orchestrate a basic Deployment Plan using the Quick Start mode. For performance reasons, an orchestration using the Quick Start mode alone is not recommended for Production environments.

Use the Quick Start mode in the JD Edwards One-Click Provisioning Console to create a deployment plan that includes all the core components of JD Edwards EnterpriseOne, which will be deployed exclusively on Oracle Cloud Infrastructure.

Refer to the OBE "Fundamentals" of this Learning Path for a description of the various servers that can be deployed by One-Click Provisioning.

### **Prerequisite**

You must have configured the administrator passwords for the WebLogic Server and the Server Manager Console in the Configure section of the JD Edwards One-Click Provisioning Console.

## Orchestrating a Quick Start Deployment Plan

To orchestrate a Quick Start deployment plan:

1. On Welcome to the JD Edwards Provisioning Console, click the **Orchestrate** icon.

The screenshot displays the Oracle JD Edwards Provisioning Console interface. At the top, it reads "ORACLE® JD Edwards Provisioning Console". Below this is a heading "Welcome to JD Edwards One-Click Provisioning Console". There are two main cards. The left card, titled "Configure", has a teal background with a white icon of a person and a key inside a cloud. The text below the icon says "Configure" and "Configure your Oracle Cloud account details such as user name, domain, and REST endpoint to create your deployment plan." At the bottom of this card, it shows "Configuration status : Successful" with a green checkmark icon. The right card, titled "Orchestrate", has an orange background with a white icon of a gear and a circular arrow inside a cloud. The text below the icon says "Orchestrate" and "Create or modify your orchestration plan." Below this, there is a link: "Learn more about best practices for JD Edwards on Cloud". At the bottom of this card, it shows "Orchestration status : Not configured". A red rectangular box highlights the "Orchestrate" card.

2. If this is the first pass through a JD Edwards One-Click Provisioning orchestration, the following Global Settings screen will appear first. In the **SSH Private Key** section, click the **View/Edit Private Key** button.

## Global Settings

### Configure Global Settings

 SSH Private Key

SSH Private Key [View/Edit Private Key](#)

 Enter the SSH Private key without the passphrase.

 Windows Administrator Details

User Name

Password

3. On the **Private Key input for VM access** dialog box, you must either specify the SSH private key text, or browse and select the file that contains the SSH private key contents for accessing all the instances that are provisioned using this tool.

**Note:** Ensure the uploaded file is in the legacy `.openssh` format which is supported in One-Click Provisioning. For Example: `oci_Instance.openssh`.

**Note:** The private key in the legacy `.openssh` format starts with `-----BEGIN RSA PRIVATE KEY-----` and ends with `-----END RSA PRIVATE KEY-----`. While the new format starts with `-----BEGIN OPENSSSH PRIVATE KEY-----` and ends with `-----END OPENSSSH PRIVATE KEY-----`.

To browse and select the file, select the **SSH Private Key File** option and then click the **Choose File** button. For more information regarding SSH Keys, refer to the section "[Generating Secure SHell \(SSH\) Key Pairs](#)."

**Note:** Ensure that the SSH Private Key Text field is not blank. The One-Click Provisioning Console validates the private keys and you cannot save the Global Settings if this field is blank.

**Private Key input for VM access** [X]


Select and then provide the values for either the Private Key text, or the file that contains the Private Key contents for accessing all Cloud VM's provisioned through this tool.

SSH Private Key Text

SSH Private Key File  No file chosen

4. Browse and select the appropriate file, and then click OK.

**Note:** If you click the **View/Edit Private Key** button again, you can see the **Public Key for VM access** window with the SSH Public Key value in the **SSH Public Key** text field. To change the private key, click the **Change** button and provide the new value.



5. Click the **Close** button.
6. In the Windows Administrator Details section, enter the Windows user name and password. Ensure that the user name is entered as `opc` and that this user has the administrative privileges.

**Note:** You must enter the same password for this Windows Server that you previously specified in the section "*Logging in to the Windows VM*" of this Learning Path.

7. In the Set EnterpriseOne Passwords section, enter and then confirm these passwords:

- o **JDE User Password**

Create the password for JD Edwards EnterpriseOne. In support of the long password functionality, the password must be between 12 and 30 characters. It can contain only alphanumeric characters, and can only include this special character: \_ (underscore).

- o **Site Key Passphrase**

Enter the passphrase for generating the site key. The passphrase must start with a letter, end with an alphanumeric character, must be between 8 and 40 characters, and contain at least 2 uppercase letters, 2 lowercase letters, 2 numbers, and 2 underscore characters.


**Tip:** The conditions to set the passwords appear in a tooltip when you click the fields.

**Note:** It is highly recommended that you keep a record of these critical passwords. If you have not already done so, you should record these values in the Preinstallation Worksheet.

8. Click the **Save** button to exit the Global Settings screen.

9. On the Choose your Orchestration Template window, click the **Quick Start** icon to create your Quick Start JD Edwards Deployment Plan.

**Note:** Refer to the applicable OBEs of this Learning Path for instructions on using the Advanced mode, and Export and Import orchestration functions.



- 
10. On Database Server Instance page, complete these fields to create and configure the Database Server instance.

**Server Configuration**

- *Database Server Type*

The Database Server Type is populated by default as Oracle Database.

- *ATP-D*

You should only enable the ATP-D option if you are using an Oracle Autonomous Database Dedicated; this database is only supported in Oracle Cloud Infrastructure. This functionality is described in the

Learning Path "Deploying JD Edwards EnterpriseOne on Oracle Cloud Infrastructure on Linux with Autonomous Database."

- *Platform*

This field is disabled and it is automatically populated as Linux.

- *Instance Name*

Create an instance name for your database instance.

- *Host Name*

Enter the host name.

### Database Configuration

- *DB Install Path*

Enter the DB installation path.

- *DB Admin Password*

Enter the password of the database administrator.

- *Net Service Name*

Enter the net service name.

### JD Edwards Database Configuration

- *Use ASM feature*

Enable this option if you are using RAC DB as your Database Server.

If you disable ASM in your Orchestration, you must enter valid values for the install, table, and index directories for your Oracle database. For example:

- /u01/DataDB
- /u01/ORATABLE
- /u01/ORAINDEX

If you enable ASM in your Orchestration, you must enter valid values for your DISK group. By default the values for are assumed to be DATA. Otherwise, you can enter any other name that you have created. An example screen is shown below as Database Server Instance - ASM Enabled.

- *JDE DB Install Directory*

Enter the installation path.

**Path Rules:** All directories in the specified path must preexist, **except** the last directory in the path. Therefore you must manually create the directory structure except for the last directory, which the Provisioning Server deployment process creates. For example, if you specify /u01/ORCL/INSTALL,

---

the /u01/ORCL directory must preexist and the Provisioning Server deployment creates the /INSTALL directory.

- *JDE DB Table Directory*

Enter the path to install the table data.

**Path Rules:** All directories in the specified path must preexist, **except** the last directory in the path. Therefore you must manually create the directory structure except for the last directory, which the Provisioning Server deployment process creates. For example, if you specify /u02/ORCL/TABLE, the /u02/ORCL directory must preexist and the Provisioning Server deployment creates the /TABLE directory.

- *JDE DB Index Directory*

Enter the path to install the indexes.

**Path Rules:** All directories in the specified path must preexist, **except** the last directory in the path. Therefore you must manually create the directory structure except for the last directory, which the

---

Provisioning Server deployment process creates. For example, if you specify /u03/ORCL/INDEX, the /u03/ORCL directory must preexist and the Provisioning Server deployment creates the /INDEX directory.

- o *Schemas*

Click the Schemas field and select the schemas you want from the auto-suggest text. The schemas available are: Shared, Development, Prototype, Production, and Pristine with Demo data.

**Note:** It is mandatory to add the Shared schema.

**Note:** At this point, you should ensure that you specify **all** the schemas you might plan to use. The schemas you choose to install on the Database Server can only be deployed once, which is specified at this point in the Provisioning Console. You can use the Provisioning Console to programmatically add additional schemas after deploying the orchestration.

- o *Demo Data*

Click the **Demo Data** field and select the demo data from the auto-suggest text. Demo data is available depending on the schema selected. For example, if you select the schema as Development, the Development demo data will be available.

## Database Server Instance

Enter the details to configure your database server instance.



### Server Configuration

Database Server Type	<input type="text" value="Oracle Database"/>
ATP-D	<input type="checkbox"/>
Platform	<input type="text" value="Linux"/>
Instance Name	<input type="text" value="Dbsrv"/>
Host Name	<input type="text" value="jan22db1.privatregsub.jan22.oraclevcn."/>



### Database Configuration

DB Install Path	<input type="text" value="/u01/app/oracle/product/19.0.0.0/dbhc"/>
DB Admin Password	<input type="password" value="....."/>
Net Service Name	<input type="text" value="JDEORCL"/>

## Database Server Instance

Enter the details to configure your database server instance.



### Server Configuration

Database Server Type	<input type="text" value="Oracle Database"/>
ATP-D	<input type="checkbox"/>
Platform	<input type="text" value="Linux"/>
Instance Name	<input type="text" value="Dbsrv"/>
Host Name	<input type="text" value="jan22db1.privatregsub.jan22.oraclevcn."/>



### Database Configuration

DB Install Path	<input type="text" value="/u01/app/oracle/product/19.0.0.0/dbhc"/>
DB Admin Password	<input type="password" value="....."/>
Net Service Name	<input type="text" value="JDEORCL"/>

11. Click the **Next** button. Because you will be connecting to an existing Oracle Cloud Infrastructure Service database instance, the system validates all the input that you provide. If the validation is successful, the JD Edwards Enterprise Server page is displayed.

12. On Enterprise Server Instance page, complete these fields to create and configure the Enterprise Server instance.

### Server Configuration

- o *Platform*

This field is disabled and it is automatically populated as Linux.

- o *Instance Name*

Create an instance name for the Enterprise Server. The conditions to set the instance name is displayed in the tooltip when you click the field.

- o *Host Name*

Enter the host name.

### Enterprise Server Preferences

- o *Server Type*

Select one or both of the available server types for this Enterprise Server.

**Single Enterprise Server.** If you are deploying only a single Enterprise Server, select both Logic and Batch as the server types.

**Multiple Enterprise Servers.** If you are deploying multiple Enterprise Servers, at least one server must be specified as a Logic server for each pathcode. The other servers can be specified as Batch servers.

- o *Pathcodes*

Click the Available Pathcodes field and select the pathcodes required from the auto-suggest text. The four available pathcodes are: Development, Prototype, Pristine, and Production.

**Note:** It is good practice to select pathcodes here that correlate to the schemas you selected for the Database Server. The Provisioning Console programmatically enforce this correlation. If you select pathcodes on the Enterprise Server that are a superset of the database schemas you selected, the Enterprise Server will not be able to access the data required to function correctly. In the Provisioning Console, the pathcodes that you specify at this point for installation on the Enterprise Server can be deployed only once. You can use the Provisioning Console to programmatically add additional schemas after deploying the orchestration.

- o **Oracle JDBC Driver Details**

This driver is required for connectivity between the Enterprise Server and the Oracle database server.

Click the **Browse** button to select each of the required components for the Oracle JDBC driver. For example:

- odbc8.jar
- ons.jar
- ucp.jar

**Note:** Refer to Oracle Certifications for the version of the supported driver and associated components.

### JD Edwards Basic Plan Details

< Previous    Cancel

Database Server    **Enterprise Server**    HTML Server

#### Enterprise Server Instance

Enter the details to install and configure your enterprise server instance.

#### Server Configuration

\* Platform

\* Instance Name

\* Host Name

#### Oracle JDBC Driver Details

\* Select Oracle JDBC Driver (ojdbc8.jar)

\* Select Oracle JDBC Driver (ons.jar)

\* Select Oracle JDBC Driver (ucp.jar)

13. Click the **Next** button. Because you will be connecting to an existing Oracle Cloud Infrastructure Service EnterpriseOne instance, the system validates all the input that you provide. If the validation is successful, the JD Edwards HTML Server page is displayed.

14. On the HTML Server Instance page, complete these fields to create and configure the HTML Server instance.

### Server Configuration

- *Platform*

This field is disabled and it is automatically populated as Linux.

- *Instance Name*

Create the instance name of the HTML Server instance.

- *Host Name*

Enter the host name.

- *Port*

Enter a unique (available) port number for this server that will use an SSL connection. This port number must be between 1024 and 65535. This port number is used by HTTPS to create a container and deploy

the web component. Ensure the availability of a port that is one less than the port number that you enter here. That is, if you specify port 8081, you must also ensure that port 8080 is available.

**Note:** For each SSL port that you open in the firewall, you must also open a companion port for non-SSL access required for Server Manager. The numeric value for the companion port must be one less than the value specified for the SSL port. For example, if you specify a port value of 8081 for SSL, in the firewall you must also open a port one less than that value; in this case you must open port 8080. Refer to the section "Enable Inbound Ports in the Firewall for Compute Instances" in the OBE "Performing Common Setup for All Linux Servers" of this Learning Path.

### Web Server Preferences

- o *Pathcode*

Select the required pathcode from the drop-down menu.

**Note:** Using the Quick Start mode, you can specify only a dedicated HTML Server for AIS. If you want to create a standard HTML Server, which is strongly recommended for Production environments, you must use the Advanced Deployment mode. For a description of each HTML Server type, refer to the OBE "Fundamentals" of this Learning Path.x

**Note:** Each dedicated HTML Server and AIS Server pair can support only one pathcode. If you want additional HTML instances to support additional pathcodes, you must configure additional HTML Server pairs using the Advanced deployment mode of the Provisioning Console. For more information, refer to the OBE "Orchestrating Using Advanced Mode" of this Learning Path.

### WebLogic Details

- o *User Name*

Enter the user name.

- o *Password*

Enter the WebLogic Server password.

- o *Admin Port*

Enter the port number to access the WebLogic Administration Console.

- o *Install Path*

Enter the installation path of the WebLogic instance.

- o *JDK Install Path*

Enter the JDK installation path.

### JD Edwards Basic Plan Details

The screenshot shows the 'JD Edwards Basic Plan Details' configuration page. At the top, there is a progress bar with five steps: Database Server, Enterprise Server, HTML Server (current step), AIS Server, and Deployment Server. Below the progress bar, there are 'Previous' and 'Cancel' buttons. The main section is titled 'HTML Server Instance' and contains the instruction: 'Enter the details of WebLogic server to configure your HTML server instance.' The configuration is divided into three sections: 'Server Configuration', 'Web Server Preferences', and 'WebLogic Details'. 'Server Configuration' includes fields for Platform (Linux), Instance Name (DedicatedHTML), Host Name, and Port (8001). 'Web Server Preferences' includes a PathCode field (Production). 'WebLogic Details' includes fields for User Name (weblogic), Password, Admin Port (7001), Install Path, and JDK Install Path.

- o *JD Edwards Web Server Details*

Web Server Instance Details - Dedicated HTML Server for AIS

15. Click the **Next** button. The system validates the input. If the validation is successful, the AIS Server Instance page is displayed.
16. On AIS Server Instance page, complete these fields to configure your AIS Server instance.

#### Same as HTML Server

This option is selected by default. You cannot deselect it because this AIS Server must be paired with the dedicated HTML Server that you configured in the preceding step.

#### Server Configuration

- o *Platform*

This field is disabled and it is automatically populated as Linux.

- o *Instance Name*

Create an instance name for the WebLogic Server.

- o *Host Name*

Enter the host name.

- o *Port*

Enter a unique (available) port number for this server that will use an SSL connection. This port number must be between 1024 and 65535. This port number is used by HTTPS to create a container and deploy

the web component. Ensure the availability of a port that is one less than the port number that you enter here. That is, if you specify port 8081, you must also ensure that port 8080 is available.

**Note:** Important: For each SSL port that you open in the firewall, you must also open a companion port for non-SSL access required for Server Manager. The numeric value for the companion port must be one less than the value specified for the SSL port. For example, if you specify a port value of 8081 for SSL, in the firewall you must also open a port one less than that value; in this case you must open port 8080. Refer to the section "Enable Inbound Ports in the Firewall for Compute Instances" in the OBE "Performing Common Setup for All Linux Servers" of this Learning Path.

### Web Server Preferences

- o *Type*

This field is disabled and is automatically populated as **AIS Server**.

- o *HTML Server Instance*

Select the instance of the previously defined dedicated HTML Server from the drop-down menu.

### WebLogic Details

- o *User Name*

Enter the user name.

- o *Password*

Enter the WebLogic password.

- o *Admin Port*

Enter the admin port number.

- o *Install Path*

Enter the installation path of the WebLogic instance.

- o *JDK Install Path*

Enter the JDK installation path.

### JD Edwards Basic Plan Details

[← Previous](#) [Cancel](#)

Database Server  Enterprise Server  HTML Server

#### AIS Server Instance

Enter the details of WebLogic server to configure your AIS server instance.

Same as HTML Server

#### Server Configuration

\* Platform

\* Instance Name

\* Host Name

\* Port

17. Click the **Next** button. The system validates the input. If the validation is successful, the JD Edwards Deployment Server page is displayed.

18. On JD Edwards Deployment Server page, complete these fields to create and configure your Deployment Server instance.

### Server Configuration

- o *Instance Name*

Create a name for the Deployment Server instance. The conditions to set the instance name is displayed in the tooltip when you click the field.

- o *Host Name*

Enter the host name.

- o *Windows User*

Enter the name of the Windows user.

- o *Windows Password*

Enter the password of the Windows user.

### Deployment Server Preferences

- o *Location*

Enter the location.

This value is the base location for your JD Edwards EnterpriseOne machines. For example, typical values might be a city name (such as Denver or Austin), a geographical region name (such as US or India), or a general location name (such as Corporate).

- o *Installation Drive*

Enter the drive for the installation.

- o *Pathcodes*

This field is automatically populated.

### JD Edwards Basic Plan Details

< Previous Cancel

Database Server Enterprise Server HTML Server

#### Deployment Server Instance


Enter the details to install and configure your deployment server instance.

#### Server Configuration

\* Instance Name DemoDEP


\* Host Name

19. Click the **Finish** button.



20. Click **OK** in the success message window.

21. The summary window is displayed. In the summary window, you can see that one instance is created for each of the servers. Click the **Back** button to proceed to deploy your services as described in the OBE "Deploying an Orchestration" of this Learning Path.



**Note:** You can click **Options** in the menu bar and then select the menu item to change your Global Settings or to reset your settings (that is, delete your configuration details, global settings, and orchestration data). Also optionally, you can further customize a completed Quick Start Deployment Plan using the **Advanced** deployment function of the JD Edwards Provisioning Console. For more information, refer to the OBE "Orchestrating Using Advanced Mode" of this Learning Path.

## Orchestrating an Advanced Deployment Plan

This tutorial shows how to orchestrate a deployment plan using the advanced mode on Linux using the JD Edwards One-Click Provisioning Console.

*Orchestrating Using Advanced Mode*

## Orchestrating Using Advanced Mode

This section shows how to orchestrate a deployment plan using the advanced mode on Linux using the JD Edwards One-Click Provisioning Console.

You can orchestrate a Deployment Plan using Advanced mode, which allows you to:

- Modify and add servers to an existing Orchestration that was created using the Quick Start wizard.
- Create a new Orchestration with no guidance from a wizard. Unlike using the Quick Start wizard, the Advanced mode will **not** guide you through the required sequence of machines to satisfy dependencies of the configuration. For example, the allowable pathcodes for an Enterprise Server are dependent on the schemas previously selected for the Database Server.

### Prerequisite

- You must have configured the administrator passwords for WebLogic Server and Server Manager Console in the Configure section of the JD Edwards One-Click Provisioning Console.
- Before orchestrating an Advanced Deployment Plan, the recommended practice is to first orchestrate a basic Deployment Plan using the Quick Start mode. The Quick Start procedure is documented in the section of this document entitled: Orchestrate Using Quick Start Mode. After this Quick Start orchestration is created, you can use the Advanced mode to modify, delete, or add on additional server instances.
- Alternately, experienced users can use Advanced Mode to create an orchestration without assistance from a structured wizard, which assumes they are aware of the required sequence of creation and the inter dependencies.

## Orchestrating an Advanced Deployment Plan

**Note:** The following procedure explains how to modify and add servers to an existing orchestration that was created using the Quick Start mode.

The required sequence of adding instances to an orchestration and the rules related to the machines and pathcodes is as follows:

### 1. Database Server

You can create five database instances if you select one schema per instance.

### 2. Enterprise Server

One to many Enterprise Servers can be created. At least one Enterprise Server must be created with selected pathcodes available from the available schemas that were selected for the Database Server. An Enterprise Server must be configured before you can add HTML Servers. If multiple Enterprise Servers are deployed, at least one must be configured as a Logic Server per pathcode. Additional Enterprise Servers can be added to an Orchestration and they can be deployed after your initial plan is deployed.

### 3. Web Servers

**HTML Server.** Web Servers include the JD Edwards EnterpriseOne HTML Server. There are two types of HTML Servers: **Standard JAS** and **Dedicated HTML for AIS**.

One to many HTML Server instances can be created and each will be associated with one specific pathcode that is available on the Enterprise Server. Additional HTML Servers can be added to an Orchestration and they can be deployed after your initial plan is deployed.

Refer to the *Fundamentals* section of this Learning Path for a description of each type of HTML Server.

**AIS Server.** Another type of Web Server for JD Edwards EnterpriseOne is the AIS Server, which must be installed and configured along with a Dedicated HTML Server for AIS.

Zero to many AIS Server instances can be created and each will be associated with a specific HTML Server instance. Additional AIS Server instances can be added on to your plan and deployed after your initial plan is deployed.

**Note:** If you do not specify at least one AIS Server, the full functionality of certain JD Edwards EnterpriseOne applications will not be available. If you used the Quick Start mode to configure a basic environment, the workflow required the inclusion of this server.

**Note:** You cannot specify a single HTML Server instance to also support an AIS Server; that is, you cannot combine two servers in the same instance. You must create a separate instance for each AIS Server.


### 4. Deployment Server

A single Deployment Server can be created and all pathcodes can be selected regardless of pathcodes selected for your runtime servers.


**Note:** For any orchestration created or modified using the Advanced Mode Deployment Plan, you can click the **Options** function from the menu bar to change your Global Settings or to Reset your settings (that is, to delete your configuration details, global settings, and orchestration data)

To use the JD Edwards Provisioning Console to orchestrate an Advanced Deployment Plan:

1. On the JD Edwards Provisioning Console, click the **Orchestrate** icon.



2. On JD Edwards Servers, click on the instance of an existing server, or click the **New Server** icon to add a new JD Edwards service. Alternately you can select the desired server from **Service Types** on the left tab, and then click **New Server** to add a New Server.



**Note:** The remainder of this procedure includes steps to either add (where allowed) or modify (existing) these instances:

- Database Server
- Enterprise Server
- Web Server (for example, HTML Server and AIS Server)
- Deployment Server\*

\* The Provisioning Console will not allow you to add more than one of these server types because only one server of this type is supported per deployment.

## Database Server


You can create five database instances if you select one schema per instance. For example, if you select Development and Shared schemas for an instance, you can create three more database instances. For one deployment instance, you can have a maximum number of five schemas distributed across one or many database instances.

You can provision the Database Server instance with the available schemas as required. The following schemas are available for the database instance:

- Development
- Shared (required)
- Prototype
- Production
- Pristine

To add a Database Server:

1. Click the **New Server** icon and select Database Server from the Select a Server Component window.



2. On Database Server Instance page, complete the following fields to create and configure the Database Server instance.

The below sections and supported screens are separated for Standard Oracle Database and Oracle Autonomous Database.

### **Standard Oracle Database**

#### **Server Configuration**

- o *Database Server Type*

The Database Server Type is populated by default as Oracle Database.

- o *ATP-D*

You should only enable the ATP-D option if you are using an Oracle Autonomous Database Dedicated; this database is only supported in Oracle Cloud Infrastructure. This functionality is described in the

Learning Path "Deploying JD Edwards EnterpriseOne on Oracle Cloud Infrastructure on Linux with Autonomous Database."

A description of the fields specific to Autonomous Database are presented below the first figure below.

- *Platform*

This field is disabled and it is automatically populated as Linux.

- *Instance Name*

Create an instance name for your database instance.

- *Host Name*

Enter the host name.

### Database Configuration

- *DB Install Path*

Enter the DB installation path.

- *DB Admin Password*

Enter the password of the database administrator.

- *Net Service Name*

Enter the net service name.

### JD Edwards Database Configuration

- *Use ASM feature*

Enable this option if you are using RAC DB as your Database Server.

If you disable ASM in your Orchestration, you must enter valid values for the install, table, and index directories for your Oracle database. For example:

- /u01/DataDB
- /u01/ORATABLE
- /u01/ORAINDEX

If you enable ASM in your Orchestration, you must enter valid values for your DISK group. By default the values for are assumed to be DATA. Otherwise, you can enter any other name that you have created. An example screen is shown below as Database Server Instance - ASM Enabled.

- *JDE DB Install Directory*

Enter the installation path.

**Path Rules.** All directories in the specified path must preexist, **except** the last directory in the path. Therefore you must manually create the directory structure except for the last directory, which the Provisioning Server deployment process creates. For example, if you specify /u01/ORCL/INSTALL,

---

the /u01/ORCL directory must preexist and the Provisioning Server deployment creates the /INSTALL directory.

- *JDE DB Table Directory*

Enter the path to install the table data.

**Path Rules:** All directories in the specified path must preexist, **except** the last directory in the path. Therefore you must manually create the directory structure except for the last directory, which the Provisioning Server deployment process creates. For example, if you specify /u02/ORCL/TABLE, the /u02/ORCL directory must preexist and the Provisioning Server deployment creates the /TABLE directory.

- *JDE DB Index Directory*

Enter the path to install the indexes.

**Path Rules:** All directories in the specified path must preexist, **except** the last directory in the path. Therefore you must manually create the directory structure except for the last directory, which the

Provisioning Server deployment process creates. For example, if you specify /u03/ORCL/INDEX, the /u03/ORCL directory must preexist and the Provisioning Server deployment creates the /INDEX directory.

- o **Schemas**

Click the Schemas field and select the schemas you want from the auto-suggest text. The schemas available are: Shared, Development, Prototype, Production, and Pristine with Demo data.

**Note:** Note: It is mandatory to add the Shared schema.

**Note:** At this point, you should ensure that you specify all the schemas you might plan to use. The schemas you choose to install on the Database Server can only be deployed once, which is specified at this point in the Provisioning Console. You can use the Provisioning Console to programmatically add additional schemas after deploying the orchestration.

- o **Demo Data**

Click the **Demo Data** field and select the demo data from the auto-suggest text. Demo data is available depending on the schema selected. For example, if you select the schema as Development, the Development demo data will be available.

The screenshot displays the 'Database Server Instance' configuration page. It is divided into two main sections: 'Server Configuration' and 'Database Configuration'.  
**Server Configuration:**

- \* Database Server Type: Oracle Database (dropdown)
- ATP-D: (toggle switch)
- \* Platform: Linux (dropdown)
- \* Instance Name: DemoDb (text input)
- \* Host Name: (text input)

**Database Configuration:**

- \* DB Install Path: /u01/app/oracle/product/12.1.0.2/dbh...
- \* DB Admin Password: (password field)
- \* Net Service Name: JDEORCL

**JD Edwards Database Configuration:**

- Use ASM feature: (toggle switch)
- \* JDE DB Install Directory: /u01/DataDB
- \* JDE DB Table Directory: /u01/ORATABLE
- \* JDE DB Index Directory: /u01/ORAINDEX
- \* Schemas: Shared X, Production X
- Demo Data: Production X

## Oracle Autonomous Database

### Server Configuration

- *Database Server Type*

The Database Server Type is displayed as Oracle Database.

- *ATP-D*

Enable this selector button for Oracle Autonomous Database ATP-D.

- *Platform*

This field is disabled and it is automatically populated as Linux.

- *Instance Name*

Create an instance name for your database instance.

- *Host Name*

Enter the host name.

### Database Configuration

- *DB Admin Password*

Enter the password of the database administrator.

- *DB Wallet*

Click the **Browse** button to locate and select the DB Wallet that you created by following the steps in the section "Downloading a Database Wallet for Autonomous Transaction Processing on Dedicated Infrastructure" of this Learning Path.

### JD Edwards Database Configuration

- *JDE DB Install Directory*

Enter the installation path.

**Path Rules.** All directories in the specified path must preexist, except the last directory. Therefore you must manually create the directory structure except for the last directory, which the Provisioning Server

deployment process creates. For example, if you specify `/u01/ORCL/INSTALL`, the `/u01/ORCL` directory must preexist and the Provisioning Server deployment creates the `/INSTALL` directory.

- *Schemas*

Click the **Schemas** field and select the schemas from the auto-suggest text. The schemas available are: Shared, Development, Prototype, Production, and Pristine with Demo Data.

**Note:** Note: It is mandatory to add the Shared schema.

**Note:** point, you should ensure that you specify all the schemas you plan to use. The schemas you choose to install on the Database Server can only be deployed once, which is specified at this point in the Provisioning Console. You can use the Provisioning Console to programmatically add additional schemas after deploying the orchestration.

- *Demo Data*

Click the **Demo Data** field and select the demo data available from the auto-suggest text. Demo data will be available depending on the schema selected. For example, if you select the schema as Development, the Development demo data will be available.

### OCI Object Storage Details

- *Tenancy*

Enter the tenancy where you have access to the Object Storage Service in Oracle Cloud Infrastructure.

- *User Name*

Enter the user name with which you can access the Object Storage Service in Oracle Cloud Infrastructure.

- *Auth Token*

Enter the Auth Token for the given user. This token is used to upload the JD Edwards database dump files into the Object Storage Service in Oracle Cloud Infrastructure.

For additional details, see the section [Getting an Auth Token](#)


- *Region*

OCI Region


- *Bucket*

Enter the bucket name that you have previously created for use with Oracle Cloud Infrastructure Object Storage Service.


For additional details, see the section "Managing Buckets" in this Learning Path.



3. You should now be able to view multiple instances of the Database Server.



4. If a Database Server exists, click **View** from the Application Options tab to view the existing configuration for the Database Server. To modify the instance configuration use the Application Options tab and choose the **Edit** option.




5. To delete the instance, use the Application Options tab to select **Delete**.

## Enterprise Server

You can define any number of Enterprise Server instances. If you only want one Enterprise Server, you should define it to run both Logic and Batch. If you want to define multiple Enterprise Servers, at least one must be a Logic Server per pathcode.

To add an Enterprise Server:

1. Click the **New Server** icon and select **Enterprise Server** from the Select a Server Component window.



2. On Enterprise Server Instance page, complete these fields to create and configure the Enterprise Server instance.

### Server Configuration

- o *Platform*

This field is disabled and it is automatically populated as Linux.

- o *Instance Name*

Create an instance name for the Enterprise Server. The conditions to set the instance name is displayed in the tooltip when you click the field.

- o *Host Name*

Enter the host name.

### Enterprise Server Preferences

- o *Server Type*

Select one or both of the available server types for this Enterprise Server.

**Single Enterprise Server.** If you are deploying only a single Enterprise Server, select both Logic and Batch as the server types.

**Multiple Enterprise Servers.** If you are deploying multiple Enterprise Servers, at least one server must be specified as a Logic server for each pathcode. The other servers can be specified as Batch servers.

- o *Pathcodes*

Click the Available Pathcodes field and select the pathcodes required from the auto-suggest text. The four available pathcodes are: Development, Prototype, Pristine, and Production.

**Note:** Important: It is good practice to select pathcodes here that correlate to the schemas you selected for the Database Server. The Provisioning Console programmatically enforce this correlation. If you select pathcodes on the Enterprise Server that are a superset of the database schemas you selected, the Enterprise Server will not be able to access the data required to function correctly. In the Provisioning Console, the pathcodes that you specify at this point for installation on the Enterprise Server can be deployed only once. You can use the Provisioning Console to programmatically add additional schemas after deploying the orchestration.

- o **Oracle JDBC Driver Details**

This driver is required for connectivity between the Enterprise Server and the Oracle database server.

Click the Browse button to select each of the required components for the Oracle JDBC driver. For example:

- odbc8.jar
- ons.jar
- ucp.jar

**Note:** Refer to Oracle Certifications for the version of the supported driver and associated components.

### Enterprise Server Instance

Enter the details to install and configure your enterprise server instance.

#### Server Configuration

- \* Platform: Linux
- \* Instance Name: DemoEnt
- \* Host Name: dec2pdbatch2.privatregsub.dec22.orac
- HA Enabled:


#### Enterprise Server Preferences

- \* Server Type: Batch X Logic X
- \* Database Instance: dec2pdb1
- \* Pathcodes: Production X


#### Oracle JDBC Driver Details

- \* Select Oracle JDBC Driver (ojdbc8.jar)
- \* Select Oracle JDBC Driver (ons.jar)
- \* Select Oracle JDBC Driver (ucp.jar)

3. You should now be able to view multiple instances of the Enterprise Server.



4. If an Enterprise Server exists, click **View** from the Application Options tab to view the existing configuration for the Enterprise Server. To modify the instance configuration use the Application Option tab and choose the **Edit** option. Use the Clone option to **clone** the Enterprise Server instance.



5. To delete the instance, use the Application option tab to select **Delete**.

## Web Server

The Instance Type for Web Servers can be any of the available servers types that are selectable from the drop-down list; however, you must have at least one configured Dedicated HTML Server saved prior to creating an associated AIS instance.

You can define any number of Web Server instances.

To add or modify a Web Server instance:

1. Select the Service Type for Web Server.
  - o To create a new Web Server, click the **New Server** icon and then the **Web Server** icon and complete the required fields.
  - o To modify an existing Web Server, click **View** from the Application Actions tab to view the existing configuration for the Web Server. To modify the instance configuration use the action tab and choose the **Edit** option.

2. On the Web Server Instance, you can configure each of these Web Server types:

- HTML Server (Dedicated HTML Server for AIS)

At least one of these servers must be specified in a pair with an AIS Server.

- Application Interface Services (AIS) Server

At least one of these servers must be specified in a pair with a Dedicated HTML Server for AIS.

- Standard JAS Server

This is a traditional JAS Server, which is optional and can be none to many.

**Note:** For Oracle Cloud Infrastructure only, you can select the HA Enabled option if required, and when prompted, should enter the Virtual Host Name, and then click OK.

**Note:** For a description of each HTML server type (Dedicated for AIS or Standard), refer to the Fundamentals section of this Learning Path.

**Note:** Because multiple Web Servers instances can run on the same WebLogic Server running in Oracle Cloud Infrastructure, you MUST specify different ports for each instance.

3. On the HTML Server Instance page, complete these fields to create and configure the HTML Server instance.

**Server Configuration**

- *Platform*

This field is disabled and it is automatically populated as Linux.

- *Instance Name*

Create the instance name of the HTML Server instance.

- *Host Name*

Enter the host name.

- *Port*

Enter a unique (available) port number for this server that will use an SSL connection. This port number must be between 1024 and 65535. This port number is used by HTTPS to create a container and deploy

the web component. Ensure the availability of a port that is one less than the port number that you enter here. That is, if you specify port 8081, you must also ensure that port 8080 is available.

**Note:** For each SSL port that you open in the firewall, you must also open a companion port for non-SSL access required for Server Manager. The numeric value for the companion port must be one less than the value specified for the SSL port. For example, if you specify a port value of 8081 for SSL, in the firewall you must also open a port one less than that value; in this case you must open port 8080. Refer to the section "Enable Inbound Ports in the Firewall for Compute Instances" in the OBE "Performing Common Setup for All Linux Servers" of this Learning Path.

## Web Server Preferences

- *Pathcode*

Select the required pathcode from the drop-down menu.

**Note:** Using the Quick Start mode, you can specify only a dedicated HTML Server for AIS. If you want to create a standard HTML Server, which is strongly recommended for Production environments, you must use the Advanced Deployment mode. For a description of each HTML Server type, refer to the section "Fundamentals" of this Learning Path.

**Note:** Each dedicated HTML Server and AIS Server pair can support only one pathcode. If you want additional HTML instances to support additional pathcodes, you must configure additional HTML Server pairs using the Advanced deployment mode of the Provisioning Console. For more information, refer to the OBE "Orchestrating Using Advanced Mode" of this Learning Path.

## WebLogic Details

- *User Name*

Enter the user name.

- *Password*

Enter the WebLogic Server password.

- *Admin Port*

Enter the port number to access the WebLogic Administration Console.

- *Install Path*

Enter the installation path of the WebLogic instance.

- *JDK Install Path*

Enter the JDK installation path.

### Web Server Instance

Enter the details to configure your web server instance.

#### Server Configuration

- \* Platform: Linux
- \* Instance Name: DedicateHTML
- \* Host Name: jan7pdwls1.privatregsub.jan07.oraclevc
- \* Port: 8003

#### Web Server Preferences

- \* Type: HTML Server
- \* Enterprise Server Instance: jan7pdlogic1
- \* PathCode: Production
- Standard JAS:

#### WebLogic Details

- \* User Name: weblogic
- \* Password: .....
- \* Admin Port: 7001
- \* Install Path: /u01/oracle/JDE/app/middleware
- \* JDK Install Path: /u01/oracle/JDE/jdk\_path
- HA Enabled:

### Web Server Instance

Enter the details to configure your web server instance.

#### Server Configuration

- \* Platform: Linux
- \* Instance Name: jan7pd1ais1
- \* Host Name:
- \* Port: 8005

#### Web Server Preferences

- \* Type: AIS Server
- \* HTML Server Instance: DedicatedHTML

#### WebLogic Details

- \* User Name: weblogic
- \* Password: .....
- \* Admin Port: 7001
- \* Install Path: /u01/oracle/JDE/app/middleware
- \* JDK Install Path: /u01/oracle/JDE/jdk\_path
- HA Enabled:

#### Load Balancer Details

- \* Virtual Host Name: web1b

### Web Server Instance

Enter the details to configure your web server instance.

#### Server Configuration

\* Platform

\* Instance Name

\* Host Name

\* Port

#### WebLogic Details

\* User Name

\* Password

\* Admin Port

\* Install Path

\* JDK Install Path

HA Enabled

#### Web Server Preferences

\* Type

\* Enterprise Server Instance

\* PathCode

Standard JAS


\* AIS Server Instance

#### Load Balancer Details

\* Virtual Host Name

4. Click the **OK** button.


5. Verify the Web Server instances you modified or added is displayed in the JD Edwards Servers window.



6. To delete any web instance, use the Application Options tab to select **Delete**.


## Deployment Server

You can use only one Deployment Server per deployment. If you attempt to add more than one Deployment Server, the Provisioning Console displays an error.



To modify the Deployment Server instance:

1. On JD Edwards Servers, click the existing Deployment Server instance, click the **Applications Options** icon, and then click **Edit**.



2. On JD Edwards Deployment Server page, complete these fields to create and configure your Deployment Server instance.

### Server Configuration

- o Instance Name

Create a name for the Deployment Server instance. The conditions to set the instance name is displayed in the tooltip when you click the field.

- o Host Name

Enter the host name.

- o Windows User

Enter the name of the Windows user.

- o Windows Password

Enter the password of the Windows user.

### Deployment Server Preferences

- o *Location*

Enter the location.

This value is the base location for your JD Edwards EnterpriseOne machines. For example, typical values might be a city name (such as Denver or Austin), a geographical region name (such as US or India), or a general location name (such as Corporate).

- o *Installation Drive*

Enter the drive for the installation.

- o *Pathcodes*

This field is automatically populated.

### JD Edwards Basic Plan Details

[← Previous](#) [Cancel](#)

Database Server Enterprise Server HTML Server

#### Deployment Server Instance

Enter the details to install and configure your deployment server instance.

#### Server Configuration

\* Instance Name

\* Host Name

3. Verify that the Deployment Server instance you modified is displayed in the JD Edwards Servers window.
4. You can choose the **Delete** option in the action tab to delete the Deployment Server instance. After you delete the existing Deployment Server instance, you can click the **New Server** icon, and then select Deployment Server from the Select a Component page to add a new Deployment Server instance.

**Note:** To deploy an orchestration, refer to the section of this tutorial entitled: **Deploying an Orchestration**.

# 12 Deploying JD Edwards EnterpriseOne

## Deploying an Orchestration

This tutorial shows how to deploy an orchestration on Oracle Cloud Infrastructure on Linux using the JD Edwards One-Click Provisioning Console.

*Deploying an Orchestration*

## Deploying an Orchestration

This section shows you how to deploy an Orchestration.

You can create a Quick Start or an Advanced Deployment Plan in the Orchestrate section of the JD Edwards One-Click Provisioning Console. When you start your deployment, the system initiates the scripts for the automated provisioning of the EnterpriseOne system.


### **Prerequisite**

A completed Quick Start or an Advanced Deployment Plan created using the JD Edwards One-Click Provisioning Console.

## Deploying an Orchestration

This procedure describes how to deploy an orchestration, whether it is a Quick Start or an Advanced mode Deployment Plan.

1. After you create a Deployment Plan, from the JD Edwards Provisioning Console, click the **Deploy** icon.



The screenshot displays the Oracle JD Edwards Provisioning Console interface. At the top, the Oracle logo and the text 'JD Edwards Provisioning Console' are visible. Below this, a welcome message reads 'Welcome to JD Edwards One-Click Provisioning Console'. The main area features two side-by-side cards. The left card, titled 'Configure', has a teal header with a cloud icon containing a person and a key. The text below describes configuring Oracle JD Edwards Server Manager details. At the bottom, it shows 'Configuration status : Successful' with a green checkmark. The right card, titled 'Orchestrate', has an orange header with a cloud icon containing a gear and arrows. The text describes creating or modifying an orchestration. At the bottom, it shows 'Orchestration status : Successful'.

**ORACLE** JD Edwards Provisioning Console

Welcome to JD Edwards One-Click Provisioning Console

### Configure

Configure your Oracle JD Edwards Server Manager details such as username, password and REST endpoint to create your deployment plan.

Configuration status : Successful 

### Orchestrate

Create or modify your orchestration.

[Learn more about best practices for JD Edwards.](#)

Orchestration status : Successful

2. To view the Account details and Global Settings Summary, in the **Deployment Details** tab click the ">" icon for each server in the Deployment Details to see the details of the servers you provisioned.

The screenshot displays the Oracle JD Edwards Provisioning Console interface. At the top, the Oracle logo and the text "JD Edwards Provisioning Console" are visible. Below this, the main heading is "Oracle JD Edwards Deployment".

The "Release Summary" section is highlighted and contains the following information:

- JD Edwards Application Release: 9.2
- JD Edwards Tools Release: 9.2.5.2

To the right of the Release Summary is a "Deployment Details" tab. This tab lists four deployment instances:

- DeployDemo**: Instance: Deploy, Platform: Windows. Represented by a monitor icon with a cloud and arrow.
- DBDemo**: Instance: Database, Platform: Linux. Represented by a database cylinder icon.
- EntDemo**: Instance: Enterprise, Platform: Linux. Represented by a server rack icon.
- EntDemo2**: Instance: Enterprise, Platform: Linux. Represented by a server rack icon.

3. Click the **Back** button if required to make additional changes to the server instances.
4. To start the deployment, click the **Start Deployment** button.

5. On Deployment Status, you can see all the instances and task details and their progress. You can also view the log or summary of each of the tasks. The time taken to deploy the servers depends on your customization.

The screenshot shows the Oracle JD Edwards Provisioning Console interface. The main heading is "Oracle JD Edwards Deployment". Below it, the "Deployment Status" section is active, displaying a table of tasks. The table has two columns: "Task Name" and "Status".

Task Name	Status
DatabaseBMCS	✓
Install JDK	✓
Install Server Manager Agent	✓
Distribute JDE Database Component to Server Manager Agent	✓
Create Database Server Instance in Server Manager	✓
EnterpriseDemo	✓
Install JDK	✓
Install Database Client	✓
Install Server Manager Agent	✓
Configure Database Client	✓
Distribute Tools Component to Server Manager Agent	✓
Distribute Apps Component to Server Manager Agent	✓
Create Enterprise Server Instance in Server Manager	✓
Configure INI	✓
Register Enterprise Server Instance as OS Service & Encrypt INIs	✓


6. Click the **Back** button if you want to go back to the Deployment Summary window.

## Adding Additional Pathcodes Post Deployment

You can add additional pathcodes to the Database Server instance after the deployment is successful.


To add additional pathcodes:

1. On Welcome to the JD Edwards Provisioning Console, click the **Orchestrate** icon.
2. On JD Edwards Servers, click on **Database Server Instances**.
3. Select the Database Server instance, and then use the action tab to choose **Edit Schema** option.



4. On Existing Database Instance Details, select the available pathcodes. An error message window appears if you attempt to delete the previously installed schema or the demo data.
5. Click the **OK** button.

6. Now you can see the Deployment status as **MODIFIED**.



7. Click the **Back** button, and then click **Deploy** icon to start your modified deployment.

## Orchestrating an Advanced Deployment Plan by Adding Web Servers and Enterprise Servers Post Deployment

This section shows you how to orchestrate an advanced deployment plan by adding Web Servers and Enterprise Servers post deployment.

You can add additional Web Servers and Enterprise Servers after you complete your Deployment. You cannot add any other server type after the deployment.

### Prerequisite

Successfully completed the Deployment of a Quick Start or an Advanced Deployment Plan using the JD Edwards One-Click Provisioning Console. These tasks are described in preceding sections of this Learning Path.

## Orchestrating an Advanced Deployment Plan by Adding Web Servers and Enterprise Servers Post Deployment

To add additional servers post deployment:

1. On JD Edwards One-Click Provisioning Console, click the **Orchestrate** icon .
2. On JD Edwards Servers, click the **New Server** icon, and in the Select a Component window, select **Web Server**.
3. On Web Server Instance Details, enter appropriate values for your installation.
4. Click the **OK** button. Similarly, you can add new Enterprise Servers.
5. On JD Edwards Servers, click the **Back** button.
6. On **JD Edwards One-Click Provisioning Console**, click the **Deploy** icon.

7. On **JD Edwards Deployment** window, review the deployment summary. You can verify the newly added servers in the **Deployment Details** tab.

**Note:** To deploy an orchestration, refer to the section of this guide entitled: ***Deploy an Orchestration.***



# 13 Saving and Reusing Deployment Plans

## Exporting an Orchestration

This section shows you how to export an orchestration.

You can use the export and import functions of the JD Edwards Provisioning Console to save an existing orchestration (export) and to reuse (import) the saved orchestration.


### Prerequisite

A completed Quick Start Deployment Plan or an Advanced Deployment Plan created using the JD Edwards One-Click Provisioning Console.


## Exporting an Orchestration

To export an orchestration:


1. On the JD Edwards Provisioning Console window, click the **Orchestrate** icon.



2. To export an existing orchestration, on an existing orchestration, from the title bar select **Export Orchestration**.




3. On the **Save As** dialog box, choose a path and file name for the exported orchestration.



4. Click the **Save** button.

**Note:** If you want to view the raw contents of the .json file, you can open the file in an ASCII editor as shown in the following screenshot.



```
1 {
2   "depServer": [
3     {
4       "instanceName": "DeployDemo",
5       "serviceType": "VM",
6       "hostDetails": {
7         "serviceName": "depfinalAD2",
8         "userName": "opc",
9         "password": "ADQW20jVUBBtKxl/LBDSbx/rIAsraf0DTJAA==",
10        "osPlatform": "WINDOWS"
11      },
12      "serverDetails": {
13        "dependentServer": "DBDemo",
14        "pathcodes": [
15          "DEVELOPMENT",
16          "PRISTINE",
17          "PROTOTYPE",
18          "PRODUCTION"
19        ],
20        "jdeLocation": "Corporate",
21        "setupDrive": "D:"
22      }
23    }
24  ],
25  "databaseServer": [
26    {
27      "instanceName": "DBDemo",
28      "serviceType": "VM",
29      "hostDetails": {
30        "serviceName": "dbad2",
```

## Importing an Orchestration

This section shows you how to import an orchestration.

You can use the export and import functions of the JD Edwards Provisioning Console to save an existing orchestration (export) and to reuse (import) the saved orchestration.


### Prerequisite

You must have configured the administrator passwords for WebLogic Server and Server Manager Console in the Configure section of the JD Edwards One-Click Provisioning Console.


## Importing an Orchestration

To import an existing exported orchestration:


1. On the JD Edwards Provisioning Console, click the **Orchestrate** icon.




2. Click the **Import** icon.



3. On the Import One-Click Provisioning Console Orchestration window, click **Choose File**, and then browse and select the exported `.json` file.



**Note:** If an error exists in the orchestration file you imported, the system displays the details of that error. Also, the system displays an error as illustrated in the following screenshot, if password authentication is required. You must edit the instance, enter the required password, and then save the instance.





# 14 Configuring JD Edwards Components Post Deployment

## Deployment Server

This section shows you how to perform post installation for the Deployment Server.

After you successfully provision all the Servers using the One-Click Provisioning Console, you must build packages on your Deployment Server.

### Prerequisite

The complete Visual Studio product (which includes the runtime, the compiler, and associated tools) must be purchased and licensed from Microsoft.

- JD Edwards EnterpriseOne Applications Release 9.2 requires runtime libraries and the full product for Visual Studio.

### General

The Deployment Server that is deployed by the Provisioning Server includes all the required third-party products including a JDK, E1Local Oracle database, and the EnterpriseOne database client. If you will be performing package builds, refer to the subsection entitled: Package Build Considerations.

### Accessing the Deployment Server

You can access your Deployment Server using Microsoft Windows Remote Desktop Protocol (RDP).

- For One-Click Provisioning, you will need the Public IP address of the Deployment Server and the password.
- For Infrastructure Provisioning, you will need to connect as described in the section entitled "Connecting to a Windows Host in a Private Network Through the Bastion Host".

For information regarding the Public IP address, refer to the section of this Learning Path entitled: **Accessing the JD Edwards EnterpriseOne Servers Using Their Public IP Addresses.**

The password for the Deployment Server was assigned when you input values in the **Deployment Server Instance** screen in the preceding sections of this Learning Path that are titled: **Orchestrate a Quick Start Deployment Plan** . If you followed the recommendation, this password should be recorded on the **Pre-Install Worksheet** .

### Package Build Considerations

In order to build packages on your Deployment Server, you will need to:

- Install Microsoft Windows Visual Studio and Windows SDK
- Update Visual Studio Version in the jde.ini File
- Refresh CNC Data in JDEPLAN
- Build a New Client Package

- Build a New Server Package

## Install Microsoft Windows Visual Studio and Windows SDK

The One-Click Provisioning Server delivers a Deployment Server to Windows 2022 Standard with most of the software already installed with the exception of Microsoft Windows Visual Studio and Microsoft Windows Software Development Kit (SDK). Refer to the JD Edwards Deployment Server Certification page for current updates on supported software versions and software prerequisites. The Certification page can be accessed through the Oracle Support Portal:

<https://www.oracle.com/support/index.html>

The Visual Studio runtime libraries (which are partial products with no development tools) for each supported release of Visual Studio are freely available from the Microsoft Download Center. The complete Visual Studio product (which includes the runtime and the compiler and associated tools) must be purchased and licensed from Microsoft.

As of the general availability of JD Edwards EnterpriseOne One-Click Provisioning for Tools Release 9.2, the following versions and associated links and navigation are valid.

- **Visual Studio 2022 Full Product**

**Note:** You need Visual Studio 2022, which is a licensed product from Microsoft, if you plan on building packages on the Deployment Server. <https://visualstudio.microsoft.com/downloads/>

- **Microsoft Software Development Kit (SDK) for Windows 11**

**Note:** Although the SDK download is labelled as Microsoft Windows 11, the same download is applicable to both Windows Client 11 and Windows Server 2022. This SDK is specifically required for any Microsoft Windows-based machine that is building JD Edwards EnterpriseOne packages. Windows Software Development Kit Version 10.0.22621.0 <https://msdn.microsoft.com/en-us/windows/downloads/sdk-archive>

## Update Visual Studio Version in the jde.ini File

Ensure that you set the correct version of Visual Studio in the `{JDE_CFG}` section of the `jde.ini` file on the Deployment Server. For details, refer to this document on Oracle Technology Network (OTN) for instructions:

*JD Edwards EnterpriseOne Development Client Installation Guide for Oracle WebLogic Server (WLS) and WebSphere Application Server (WAS) Express.*

- Understanding the Development Client Installation
- Installing Compiler, Linker, and Software Development Kit (SDK)
- Updating the jde.ini File

## Refresh CNC Data in JDEPLAN

The ESU process has changed to include automatic generation of OCM mappings and tables for tables that are not in Business Data. In order for this process to work correctly, you must update the CNC information in JDEPLAN before applying any Tools-related ESUs. Also if you have multiple Enterprise Servers, Database Servers, or both, you must perform this procedure in order to synchronize data between the System and Planner pathcodes before you proceed further.

1. Sign into JDEPLAN.

2. Run R9840C, and copy system/planner information

**from:** System – 920

**to:** Planner – 920

**Note:** R9840C will copy any missing CNC from System to Planner.

3. Run R98403A, choosing version XJDE0004, for syncing the data from System – 920 to Planner – 920 database.

4. Change the Data Selection to F98611.

5. Change the Processing Options as follows:

- o Source Data Source = System – 920
- o Target Data Source = Planner – 920
- o Proof Mode = 1
- o Replace Duplicates = Y
- o Clear Table = N

Using these processing options, running the R98403A will add any missing data source definitions in JDEPLAN with the correct definitions from System – 920.

### Build a New Client Package

You must build a new Client package in order to obtain source files for the path code and to build future update packages against.

**Note:** Update packages against the delivered FA packages (PS920FA, PY920FA, PD920FA, and DV920FA) is not supported.

Due to space considerations on the `D:\` drive, you will need to move the `D:\Software` directory and all of its contents to the `C:\` drive or another computer. For example:

1. Add a new directory under the `C:\` drive labeled:

`C:\SoftwareBKUP`


2. Copy the `D:\Software` directory (and all its contents) to the `C:\SoftwareBKUP` directory.

3. Delete the `D:\Software` directory.

Complete the following steps to build a full package by following the standard procedure to build a full package with the following important distinctions.

**Note:** The creation of update packages against the delivered FA packages (PS920FA, PY920FA, PD920FA, and DV920FA) is not supported. In order to build update packages in the future, you must build and deploy a new full package.

1. On the last screen of the Build Definition, on Package Assembly – [Package Build Revisions], select the Compression Options tab.
2. Ensure the **Compress Foundation** check box is selected. This is required to recompress the system folder on the Deployment Server to create a new `systemcomp` directory that includes a JRE. This JRE is required for use by the Development Client.



**Note:** If you encounter NER failures during your full package build (server side only), to resolve these failures refer to the My Oracle Support Doc Id 1950295.1 at this link: <https://support.oracle.com/epmos/faces/DocumentDisplay?id=1950295.1>


## Build a New Server Package

As a best practice it is strongly recommended that you build a new server package. For multiple Enterprise Server environments, the procedures in this section are mandatory.

On Package Build, Package Build Revisions, in addition to the normal compression options, you must select these additional options during the package build process for any full package:

- **Compress Server Package**

- **All Directories**



## Standalone Deployment Server

This section shows you how to perform the post installation tasks for the standalone Deployment Server with Oracle database.

**Note:** This section is *only* applicable if you have deployed a standalone Deployment Server with Oracle database using One-Click Provisioning.

You can use One-Click Provisioning to install a standalone Deployment Server. A standalone Deployment Server is deployed when you first use One-Click Provisioning to provision a Deployment Server only, and then use One-Click Provisioning to provision other servers such as the Database Server, Enterprise Server, and HTML Server. This section describes how to complete the postinstallation steps for such a standalone Deployment Server.

If you have used One-Click Provisioning to deploy a standalone Deployment Server (that is, you did not use One-Click to initially deploy a complete system), you must perform the following procedure on your Deployment Server to enable access by JD Edwards EnterpriseOne.

## Enable DEP920 Login for an Oracle Database

**Note:** This section is only applicable if your deployment of JD Edwards EnterpriseOne includes an Oracle Database Server.

After you have used One-Click Provisioning to deploy the complete suite of JD Edwards EnterpriseOne servers, you need to enable EnterpriseOne access to the Oracle database from the Deployment Server.

1. Access the Deployment Server as described in the preceding section "Accessing the Deployment Server".
2. Edit the `jde.ini` file, which is typically located in this directory:

```
c:\Windows
```

3. Edit the `jde.ini` file to provide a valid value for the **SecurityServer=** setting. This is the machine name for your Enterprise Server. For example:

```
[SECURITY]
```

```
SecurityServer=oraes
```

4. Save and close the `jde.ini` file.
5. Navigate to the location of the Oracle Client that is installed on your Deployment Server. For example:

```
C:\JDE\oracle1212\product\client_1\network\admin
```

6. In the above directory, edit the `tnsnames.ora` file to add the listener details. You can copy these details from the `tnsnames.ora` file on your Server Manager machine or your Enterprise Server machine. This `tnsnames.ora` file is located in the same location on each machine. From the Server Manager, use this navigation to find this `tnsnames.ora` file on either the Server Manager machine or the Enterprise Server:

From the HTML Server, select DATABASE, and then select Tnsnames.

For example, this is the listener section you should copy:

```
JDEORCL =  
(DESCRIPTION =  
(ADDRESS = (PROTOCOL = TCP) (HOST = oradb.subnet.vcn.com) (PORT = 1521))  
(CONNECT_DATA =  
(SERVER = DEDICATED)  
(SERVICE_NAME = jdeorcl.subnet.vcn.com)  
)  
)
```

7. Save and close the `tnsnames.ora` file.
8. Navigate to the location of the E1Local Network, which is typically:

```
C:\JDE\DEP\Oracle\E1Local\NETWORK\ADMIN
```

9. In the above directory, edit the `tnsnames.ora` file to add the same listener details that you obtained and copied in a previous step in this procedure.
10. Save and close the `tnsnames.ora` file.
11. Validate the configuration of the `tnsnames.ora` file by running `ActiveConsole.exe` and logging in to the DEP920 environment.

## Development Client

This section explains the required considerations before you create the Development Clients.

### Prerequisites

- If you want to install a JD Edwards EnterpriseOne Development Client that will work with JD Edwards EnterpriseOne One-Click Provisioning, you must manually provision an additional Microsoft Windows machine. After the Microsoft Windows machine is provisioned, the process to set up and install a Development Client is the same regardless of where the client is installed.
- You must also install all the required third-party software and build a full client package on the Deployment Server.
- Refer to the *JD Edwards EnterpriseOne Development Client Installation Guide* for detailed instructions.

## Considerations for Development Client

Consider the following requirements before you create the Development Clients:

- Microsoft Windows machines must be on the same private network on which the JD Edwards EnterpriseOne Database Server and Enterprise Server exist, and the machines must be able to communicate with those servers.
- Ensure that a full package build is completed on the Deployment Server. This package build creates the Development Client package installation. The delivered FA package will technically install a Development Client, but such a Development Client is not suitable for most developer activities.
- Ensure that IPv6 is disabled on the Microsoft Windows machine on which you will install the JD Edwards EnterpriseOne Development Client.

Run this command to disable IPv6:

```
reg add hklm\system\currentcontrolset\services\tcpip6\parameters /v DisabledComponents /t REG_DWORD /d 0xFFFFFFFF
```

Use **ipconfig** to verify that the status of IPv6 is set to disabled.

## CA Certificates

This section shows you how to obtain and install CA Certificates in the Oracle WebLogic Servers and the Deployment Server.

The deployment of JD Edwards EnterpriseOne One-Click Provisioning includes temporary Certificate Authority (CA) certificates. Because these certificates are set to expire at preset and non-extendable times, you must obtain and install your own CA certificates. These must be certificates that are verified by a verified CA authority such as Entrust and Symantec Corporation.

### Prerequisite

## Installed Java Keystore.

The following outlines the general procedure to create a Keystore and to generate a Certificate Signing Request (CSR).

1. In your local environment, obtain and install a Java Keystore. This is a repository for security certificates – either authorization certificates or public key certificates – plus corresponding private keys. These keys are used for SSL encryption by the Oracle WebLogic Server. A file with extension jks serves as keystore.
2. From the Keystore, generate a Certificate Signing Request (CSR).
3. Export the Certificate Signing Request (CSR).
4. Validate the CSR. For example, you could use the validation tools provided by Symantec such as "checker".
5. Submit the CSR to the Certificate Authority such as Entrust or Symantec Corporation.
6. Upon return receipt, import the validated certificates to the Keystore for each server. That is, each server that must communicate with another must have its own certificate **plus** that of the target server. In this case, the HTML Server must have its own certificate plus that of the AIS Server, and vice versa.
7. Logged in as the WebLogic Administrator, you must manually modify each of these instance of Oracle WebLogic Server within your One-Click deployment to use the new Keystore:
  - o Server Manager Console
  - o Each instance of a JD Edwards EnterpriseOne HTML Server (JAS)
  - o Each instance of a JD Edwards EnterpriseOne AIS Server
8. You should also modify the parameters using Server Manager to use the https connection for communication between the HTML Server and the AIS Server.
  - a. In the **HTML instance**, modify the following Web Runtime parameters to use https, a fully qualified domain name, and https port:

The screenshot shows a configuration panel for the AIS instance. It contains three rows of parameters, each with an information icon (i) on the left and a copy icon on the right. The first row is 'AIS Protocol' with a dropdown menu set to 'https'. The second row is 'AIS Host' with a text input field containing '<Fully Qualified Domain Name>'. The third row is 'AIS Port' with a text input field containing '<HTTPS Port>'.

- b. In the **AIS instance**, modify the following HTML Server parameters to use https, a fully qualified domain name, and https port:

The screenshot shows a configuration panel for the HTML Server instance. It contains three rows of parameters, each with an information icon (i) on the left and a copy icon on the right. The first row is 'HTML Server End Point Host Name' with a text input field containing '<Fully Qualified Domain Name>'. The second row is 'HTML Server End Point Port' with a text input field containing '<HTTPS Port>'. The third row is 'HTML Server End Point Protocol' with a dropdown menu set to 'https'.

**Tip:** After you have SSL configured and tested, it is recommended that you disable all the non-SSL ports.

For additional details on working with CA certificates on your Oracle WebLogic Server, refer to this guide: [Administering Security for Oracle WebLogic Server..](#)

# 15 Accessing the Provisioned Servers

## Performing Post Provisioning Tasks

This section shows you how to perform the post-provisioning tasks.

### Prerequisite

Successfully completed the Deployment of a Quick Start or an Advanced Deployment Plan using the JD Edwards One-Click Provisioning Console.

### Enabling Enterprise Server Predefined Ports

You must enable Predefined Ports in the `jde.ini` file on the Enterprise Server. Use Server Manager to ensure this setting exists:

```
[JDENET]
```

```
enablePredefinedPorts=1
```

For Release 9.2, the `serviceNameListen` value is 6017. The next port for use by net services on the Enterprise Server is defined by the value `serviceNameListen+1` until the value set by `maxNetProcesses=` is reached, where the default is value is 6 net processes. Therefore, the default value of 6 net process means you must open ports in the firewall on the Enterprise Server 6018–6023 for use by net processes. These ports cannot be in use by any other process running on the Enterprise Server. If they are already in use, then whatever program is using them must be reconfigured to use different ports.

### Starting the Database in the Secondary Node in RAC

If you are using DB Systems for your database, and if you have enabled RAC within it, if you have followed the recommendation in this Learning Path you have previously stopped the database in the Secondary Node in RAC. At this point you must start the database in the Secondary Node for RAC. The recommended procedure is to use a line command as shown below.

```
srvctl start instance -d <DB_UNIQUE_NAME> -i <DB_NAME>
```


where `<DB_UNIQUE_NAME>` is the name you determined in the preceding OBE in this Learning Path entitled: xxxx and in the section within that OBE entitled: **Setting Up the Secondary Node**.

where `<DB_NAME>` is name you have given the database and which is appended with a 2. For example, if you gave the database name as ORCL, then the database name in the Secondary Node is named ORCL2.

**Note:** At this point both nodes of the RAC in DB Systems are running. Therefore, when transactions are submitted to the database by any JD Edwards EnterpriseOne server, the transaction can go to either node (Primary or Secondary). If for any reason either node goes down, the transactions from JD Edwards EnterpriseOne will be served by the node that is running. However, if the node that went down was the node in which the database connection failed while it was running a transaction, then there is lag of operation while the system switches the transactions to the node that is running. Further, if the Database is down on both nodes, and if in start up of the nodes there is delay of more than 75 seconds, then you must manually restart both the HTML Server and the Enterprise Server after the database is properly started.

To view details of the Secondary Node in RAC:

1. On the Oracle Cloud Infrastructure Console Home page, click the **Navigation** Menu in the upper-left corner.



2. From the Navigation Menu, in the **Database** section, click to select **Bare Metal, VM, and Exadata**.
3. In the left panel ensure that DB Systems is selected, and that under **List Scope** that the applicable **COMPARTMENT** is selected which contains the DB System with RAC that you created.
4. Click the link for your DB System with RAC.

5. In the **Resources** section in the left pane, click **Nodes**.

Details for two Nodes are displayed as shown below:

The screenshot displays the Oracle Cloud Infrastructure console for a DBS system named 'dbs2rac'. The system is in an 'AVAILABLE' state, indicated by a green hexagonal icon with 'DBS' and 'AVAILABLE' text below it. The console shows various system information and a list of nodes.

**DB System Information**

Availability Domain: IAUF:PHX-AD-2	OCID: ...i32owq <a href="#">Show</a> <a href="#">Copy</a>
Shape: VM.Standard2.2	Created: [Redacted]
Compartment: EnterpriseOne_BM	DB System Version: 12.2.0.1.180417
Oracle Database Software Edition: Enterprise Edition Extreme Performance	Virtual Cloud Network: <a href="#">testDNSVcn</a>
Available Data Storage: 512 GB	Client Subnet: Public Subnet IAUF:PHX-AD-2
Total Storage Size: 1168 GB	Cluster Name: None
Port: [Redacted]	Hostname Prefix: dbs2rac
Host Domain Name: [Redacted]	Scan DNS Name: <a href="#">dbs2rac-scan...</a> <a href="#">Show</a> <a href="#">Copy</a>
Scan IP Addresses: [Redacted]	License Type: License Included

**Resources**

- Nodes (2)
- Databases (1)
- Patches (1)
- Patch History (0)

**Nodes**

Node Icon	Host Name	Private IP Address & DNS Name	Public IP Address
	Host Name: dbs2rac2 OCID: ...cqj46q <a href="#">Show</a> <a href="#">Copy</a>	(dbs2rac2... <a href="#">Show</a> <a href="#">Copy</a> )	[Redacted]
	Host Name: dbs2rac1 OCID: ...466pja <a href="#">Show</a> <a href="#">Copy</a>	(dbs2rac1... <a href="#">Show</a> <a href="#">Copy</a> )	[Redacted]

## Setting up Additional Security Configurations

As part of meeting the CIS Benchmarks for secure Linux Machines, you can further secure your One-Click Provisioned Linux environments by performing the below steps:

These settings in the `sshd_config` file are located at `/etc/ssh`.

- **Disable TCP Forwarding**

Edit the `/etc/ssh/sshd_config` file to set the parameter as follows:

```
AllowTcpForwarding=no
```

- **Disable Root Login**

Edit the `/etc/ssh/sshd_config` file to set the parameter as follows:

```
PermitRootLogin=no
```

Ensure that there are no other entries that might override the above settings. For the settings to reflect, restart the SSH Service using the below command:

```
sudo systemctl restart sshd
```

## Closing Port 22 on Public IP for Enhanced Security

For enhanced security, it is highly recommended to close Port 22 (SSH) in both the Security List (VCN/Subnet level) and the Network Security Group (NSG) after provisioning is complete. This minimizes potential vulnerabilities and aligns with a stronger security posture.

Follow the below steps to close Port 22 in Security List and NSG:

- Security List:
  - a. Navigate to the OCI Console > Networking > Virtual Cloud Networks (VCN)
  - b. Select the VCN associated with your instance.
  - c. Open the Security List attached to the subnet.
  - d. Locate the ingress rule for Port 22 (TCP) and delete it.
- Network Security Group (NSG):
  - a. Navigate to the OCI Console > Networking > Network Security Groups
  - b. Select the NSG attached to your instance.
  - c. Locate the ingress rule allowing Port 22 (TCP) and delete it.

## Accessing the JD Edwards EnterpriseOne Servers Using Their Public IP Addresses

This section shows you how to access the JD Edwards EnterpriseOne Servers using their public IP addresses.

### Prerequisites

- The user interface for the Oracle Cloud Infrastructure Console is constantly evolving. For the most up-to-date descriptions and navigation, refer to [Using the Console](#).
- You should have a fundamental understanding of the Oracle Cloud Infrastructure. It is highly recommended that you review the extensive collateral information, including training, at this site: [Oracle Cloud Infrastructure](#)
- You must have a subscription and an Administrator account to Oracle Cloud Infrastructure as described at this site: [Getting Started with Oracle Cloud](#)
- Successfully completed the Deployment of a Quick Start or an Advanced Deployment Plan using the JD Edwards One-Click Provisioning Console.

After the successful deployment of all the Servers according to the Orchestration created using the JD Edwards One-Click Provisioning Console, you can access these deployed JD Edwards EnterpriseOne Servers and Development Client Using their public IP addresses:

- Server Manager Console
- HTML Server
- AIS Server
- Deployment Server

## Server Manager Console

After the Server Manager Console is started, you can access it using its public IP address using this syntax:

**http://<Public IP Address for Server Manager>:8999/manage**

For example:

**http://111.11.11.111:8999/manage**

**Note:** You should always use HTTP to access the Server Manager Console for normal operations. Although the Server Manager Console is also enabled for HTTPS/SSL protocol, such access is restricted for internal use as part of the REST/API functionality, and should not be used for normal operations.

To acquire the public IP address assigned to the instance:

1. Access Oracle Cloud Infrastructure and go to **Compute**, and select the **instance** menu. The system displays the list of instances.
2. Click the **host name** of your provisioning server in the displayed list. For example, click ProvisionPrime.

 RUNNING	<b>ProvisionPrime</b> OCID: ...ildooq <a href="#">Show Copy</a>	<b>Shape:</b> VM.Standard1.1	<b>Region:</b> phx <b>Availability Domain:</b> IAUF:PHX-AD-1
--	--	------------------------------	---

The system now displays the details of the instance where you can find the public IP address of the instance.

Compute » Instances » Instance Details



### ProvisionPrime

[Create Custom Image](#) [Start](#) [Stop](#) [Reboot](#) [Terminate](#)

#### Instance Information

**Availability Domain:** IAUF:PHX-AD-1  
**OCID:** ...ildooq [Show](#) [Copy](#)  
**Launched:** Tue, 31 Oct 2017 05:03:20 GMT  
**Compartment:** EnterpriseOne\_BM

#### Primary VNIC Information

**Private IP Address:** 10.0.0.163  
**Public IP Address:** 129.146.67.44

*This Instance's traffic is controlled by its firewall rules in addition to the associated Subnet's Security Lists.*

## HTML Server

After your HTML Server is deployed, you can access it using its public IP address using this syntax:

**https://<Public IP Address for HTML Server>:<port as defined in orchestration>/jde/E1Menu.maf**

**Note:** The file name E1Menu.maf is case-sensitive and must be specified exactly as shown here.

For example:

**https://111.11.11.111:8001/jde/E1Menu.maf**


To acquire the public IP address assigned to the HTML instance:

1. Access Oracle Cloud Infrastructure and go to **Compute**, and select the **instance** menu. The system displays the list of instances.
2. Click the **host name** of your provisioning server in the displayed list. For example, click WeblogicServer.



 RUNNING	<b>WeblogicServer</b> OCID: ...qlccfq <a href="#">Show</a> <a href="#">Copy</a>	<b>Shape:</b> VM.Standard1.1	<b>Region:</b> phx <b>Availability Domain:</b> IAUF:PHX-AD-1
--	--	------------------------------	---

The system now displays the details of the instance where you can find the public IP address of the instance.



The screenshot shows the 'Instance Details' page for a VM named 'WeblogicServer'. The instance is in a 'RUNNING' state, indicated by a green square with a white vertical bar. Below the status bar, the word 'RUNNING' is written in green. To the right of the status bar are several control buttons: 'Create Custom Image', 'Start', 'Stop', 'Reboot', and 'Terminate'. The 'Instance Information' section lists: 'Availability Domain: IAUF:PHX-AD-1', 'OCID: ...qlccfq Show Copy', 'Launched: Tue, 31 Oct 2017 05:07:01 GMT', and 'Compartment: EnterpriseOne\_BM'. The 'Primary VNIC Information' section lists: 'Private IP Address: 10.0.0.166' and 'Public IP Address: 129.146.66.247'. The public IP address is highlighted with a red rectangular box. Below this section, a note states: 'This Instance's traffic is controlled by its firewall rules in addition to the associated Subnet's Security List'.

## AIS Server

After your AIS Server is deployed, you can access it using its public IP address using this syntax:

**https://<Public IP Address for AIS Server>:<port as defined in orchestration>/jderest/defaultconfig**

For example:

**https://111.11.111:8002/jderest/defaultconfig**

To acquire the public IP address assigned to the AIS instance:


1. Access Oracle Cloud Infrastructure and go to **Compute**, and select the **instance** menu. The system displays the list of instances.
2. Click the **host name** of your provisioning server in the displayed list. For example, click WeblogicServer.



The screenshot shows a list of instances in Oracle Cloud Infrastructure. A row for 'WeblogicServer' is highlighted with a red rectangular box. The instance is in a 'RUNNING' state, indicated by a green square with a white vertical bar. The 'WeblogicServer' name and 'OCID: ...qlccfq Show Copy' are visible within the red box. To the right of the instance name, the 'Shape: VM.Standard1.1', 'Region: phx', and 'Availability Domain: IAUF:PHX-AD-1' are listed.

The system now displays the details of the instance where you can find the public IP address of the instance.

Compute » Instances » Instance Details



The screenshot shows the 'Instance Details' page for an instance named 'WeblogicServer'. At the top left, there is a breadcrumb trail: 'Compute » Instances » Instance Details'. Below this is a large green square with a white vertical bar in the center, representing the instance's status, with the word 'RUNNING' written in green below it. To the right of the status indicator are five buttons: 'Create Custom Image', 'Start', 'Stop', 'Reboot', and 'Terminate'. The 'Terminate' button is highlighted in red. Below the buttons is the 'Instance Information' section, which includes: 'Availability Domain: IAUF:PHX-AD-1', 'OCID: ...qlccfq Show Copy', 'Launched: Tue, 31 Oct 2017 05:07:01 GMT', and 'Compartment: EnterpriseOne\_BM'. Below this is the 'Primary VNIC Information' section, which includes: 'Private IP Address: 10.0.0.166' and 'Public IP Address: 129.146.66.247'. The 'Public IP Address' is highlighted with a red rectangular box. At the bottom of the page, there is a note: 'This Instance's traffic is controlled by its firewall rules in addition to the associated Subnet's Security List'.

## WeblogicServer

Create Custom Image Start Stop Reboot Terminate

### Instance Information

Availability Domain: IAUF:PHX-AD-1  
OCID: ...qlccfq Show Copy  
Launched: Tue, 31 Oct 2017 05:07:01 GMT  
Compartment: EnterpriseOne\_BM

### Primary VNIC Information

Private IP Address: 10.0.0.166  
Public IP Address: 129.146.66.247

*This Instance's traffic is controlled by its firewall rules in addition to the associated Subnet's Security List*

## Deployment Server

You can access your Deployment Server using Microsoft Windows Remote Desktop Protocol (RDP). To do so, you will need the public IP address of this instance.

To acquire the public IP address assigned to the Deployment server instance:

1. Access Oracle Cloud Infrastructure and go to **Compute**, and select the **instance** menu. The system displays the list of instances.
2. Click the **host name** of your provisioning server in the displayed list. For example, click DeploymentServr.



The screenshot shows a list of instances in Oracle Cloud Infrastructure. The instance 'DeploymentServr' is highlighted. It has a green status indicator with a white vertical bar and the word 'RUNNING' below it. To the right of the status indicator, the instance name 'DeploymentServr' is displayed in blue, followed by 'OCID: ...3xlp7a Show Copy'. Further to the right, the 'Shape' is listed as 'VM.Standard1.1' and the 'Region' is 'phx'. Below the region, the 'Availability Domain' is partially visible.

DeploymentServr Shape: VM.Standard1.1 Region: phx  
OCID: ...3xlp7a Show Copy Availability Domain:

The system now displays the details of the instance where you can find the public IP address of the instance.

[Compute](#) » [Instances](#) » Instance Details



RUNNING

## DeploymentServr

Create Custom Image

Start

Stop

Reboot

T

### Instance Information

**Availability Domain:** IAUF:PHX-AD-1

**OCID:** ...3xlp7a [Show Copy](#)

**Launched:** Tue, 31 Oct 2017 05:07:54 GMT

**Compartment:** EnterpriseOne\_BM

**Virtual Cloud Network:** [e1network](#)

### Primary VNIC Information

**Private IP Address:** 10.0.0.167

**Public IP Address:** 129.146.65.43

*This Instance's traffic is controlled by its firewall rules in addition to the ass*



# 16 Troubleshooting Your One-Click Deployment

## Troubleshooting

This section shows you the list of troubleshooting topics and resolutions.

### One-Click Provisioning Console Troubleshooting Tips

This section contains the following troubleshooting tips for the EnterpriseOne One-Click Provisioning Console:

- Accessing a Previously Saved Provisioning Console Configuration
- Console Administration
- Console Service Status
- Start the Console
- Stop the Console
- View the Console Logs

#### Accessing a Previously Saved Provisioning Console Configuration

<b>Symptom:</b>	You cannot access a previously created Quick Start Deployment Plan.
<b>Cause:</b>	After you created a Quick Start Deployment Plan (either complete or partial), you exited the browser used to connect to the One-Click Provisioning Console.
<b>Resolution:</b>	When you next access the Provisioning Console, you will be prompted to enter the same credentials that you entered for the first access to the console. Those credentials are the password for the Server Manager for JD Edwards EnterpriseOne. After the credentials are validated, you can access the previously saved configuration.

#### Console Administration

The One-Click Provisioning Console process is configured as a system service in the One-Click Provisioning Server image. The configuration file (E1CloudConsole.service) is located in this directory:

```
/etc/systemd/system/E1CloudConsole.service
```

#### Console Service Status

Run following command in the shell to display the One-Click Provisioning Console service status:

```
$ sudo systemctl status E1CloudConsole
```

#### Start the Console

Run the following command in the shell to start the One-Click Provisioning Console service.

```
$ sudo systemctl start E1CloudConsole
```

Run the following command to verify the service status within same machine:

```
$ curl -kI https://localhost:3000
```

The response from the Curl command should be similar to this:

```
[opc@multitest ~]$ curl -kI https://localhost:3000 HTTP/1.1 200 OK
X-DNS-Prefetch-Control: off
X-Content-Type-Options: nosniff
X-Frame-Options: SAMEORIGIN
Strict-Transport-Security: max-age=86400
X-Download-Options: noopen
X-XSS-Protection: 1; mode=block
Accept-Ranges: bytes
Cache-Control: public, max-age=0
Last-Modified:
ETag: W/"5862-156cad16600"
Content-Type: text/html; charset=UTF-8
Content-Length: 22626
Date:
Connection: keep-alive
```

Outside the machine, you can access the One-Click Provisioning Console application using the below URL:

```
https://<#PUBLIC_IP#>:3000/
```

### Stop the Console

Run following command in the shell to stop the One-Click Provisioning Console service.

```
$ sudo systemctl stop E1CloudConsole
```

### View the Console Logs

Run following command in the shell to view the logs for the One-Click Provisioning Console.

```
$ sudo journalctl -u E1CloudConsole
```

Press **Page-Down** to scroll through the logs.

Enter **Shift + G** to scroll to end of the log.

**Note:** The One-Click Provisioning Console logs are completely regenerated each time the Console is run.

## Enterprise Server Provisioning Fails - Communication Failure

<b>Symptom:</b>	Provisioning fails to deploy the Enterprise Server with an error returned indicating a communication failure.
<b>Cause:</b>	A timeout may have occurred during communications between the One-Click Provisioning processes and the Oracle Cloud Infrastructure Services.
<b>Resolution:</b>	Restart the deployment of One-Click Provisioning.

## Enterprise Server Provisioning Fails - Health Check Fails

<b>Symptom:</b>	Porttest remotely executes, but fails.
<b>Cause:</b>	Possibly a timing issue if the kernels are not starting up fast enough to execute a porttest successfully.
<b>Resolution:</b>	<p>If host name command in the Enterprise Server returns the FQDN then set the short hostname by using the following command: <code>sudo hostnamectl set-hostname &lt;short host name&gt;</code></p> <p>Rerun the Deployment Server again. It should quickly skip to the Ent Health Check and pass the health check.</p>

## HTML Server Intermittently Unavailable

<b>Symptom:</b>	<p>There is an intermittently occurring issue with the HTML server provisioned on the WebLogic Server going down and users not being able to access the EnterpriseOne HTML login page.</p> <p>Generally when this issue occurs, the below error is displayed in the WebLogic Server logs or in the HTML Server logs:</p> <p><b>java.lang.OutOfMemoryError: PermGen space</b></p>
<b>Resolution:</b>	<p>To bring up the EnterpriseOne HTML server when it goes down with the above error, try one of the following steps:</p> <ol style="list-style-type: none"> <li>1. Restart the EnterpriseOne HTML Server instance from the Server Manager Console and then check if the EnterpriseOne HTML login page is accessible.</li> <li>2. If the JD Edwards EnterpriseOne HTML Server login page is not accessible even after restart, then set the below JVM arguments in the HTML Server from the WebLogic Server console and then restart the HTML Server.             <ol style="list-style-type: none"> <li>a. Log in to the WebLogic Server console.</li> <li>b. Go to the Servers on the environment tab and then select the HTML Server.</li> <li>c. Go to Server Start tab and click the <b>Lock &amp; Edit</b> button in the left upper corner.</li> <li>d. In the Arguments section, change the values for the following arguments from their existing value to 1024m:                     <pre>-XX:PermSize=1024m</pre> <pre>-XX:MaxPermSize=1024m</pre> </li> <li>e. In the Arguments section, go to the end and enter one line space and paste the below arguments:                     <pre>-XX:+CMSClassUnloadingEnabled</pre> <pre>-XX:+CMSPermGenSweepingEnabled</pre> <pre>-XX:+UseConcMarkSweepGC</pre> </li> <li>f. Click the <b>Save</b> button.</li> <li>g. Click the <b>Activate Changes</b> button in the left upper corner.</li> <li>h. Restart the EnterpriseOne HTML Server.</li> </ol> </li> <li>3. If the JD Edwards EnterpriseOne HTML Server login page is still not accessible, then free up some resources (OCPU and memory) from the cloud domain and restart the EnterpriseOne HTML Server from the Server Manager console.</li> </ol>

## Server Manager Console Fails to View Log File and Download Log for Enterprise Server and HTML Server

<b>Symptom:</b>	Server Manager Console Fails to View Log File and Download Log for Enterprise Server and HTML Server.
<b>Resolution:</b>	You should always use the HTTP protocol to access the Server Manager Console for normal operations. Although the Server Manager Console is also enabled for HTTPS/SSL protocol, such access is restricted for internal use as part of the REST/API functionality, and should not be used for normal operations.

## PDB on Compute Not Open

The Console checks to ensure the Pluggable Database (PDB) on the Oracle Cloud Infrastructure is open (set to READ WRITE) as you begin to provision it. If the PDB is not open, the Console scripts will issue commands to open it. However, if the PDB is still closed (not set to READ WRITE) when the deployment commences, the deployment will fail. Use the following procedure to determine if the PDB is open, and if not how to set it to open.

1. Connect to the database using this command:

```
sqlplus '/as sysdba';
```

2. Verify the pluggable database **JDEORCL** is open using this command:

```
select OPEN_MODE from v$pdb where NAME = 'JDEORCL';
```

3. If the **OPEN\_MODE** is set to **READ WRITE**, then the PDB is ready to be provisioned by the JD Edwards EnterpriseOne One-Click Provisioning Server.
4. If the **OPEN\_MODE** is not **READ WRITE**, then the PDB is not open. Open the PDB using this command:

```
alter pluggable database JDEORCL open;
```

## Not Able to View and Download Server Manager Home Logs When Server Manager is SSL-Enabled

When Server Manager is SSL-enabled, the users may not be able to view and download the Server Manager Home logs. The root cause may be because the proper security certificates are not available. For instructions on how create and import security certificates, refer to these documents:

- [JD Edwards EnterpriseOne Tools Server Manager Guide](#)
- [JD Edwards EnterpriseOne Tools Security Administration Guide](#)

## The JD Edwards EnterpriseOne HTML Server Login Fails

If the JD Edwards EnterpriseOne HTML Server login fails, run the port test on the JD Edwards EnterpriseOne Enterprise Server. If the port test fails, check the host entries in the `/etc/hosts` file. See **Edit the `/etc/hosts` File for Connectivity** section in this tutorial.

## JAVA BSFN Fails in Web Server

If the host name command in the JAS Server returns the FQDN then set the short hostname by using the following command.

```
sudo hostnamectl set-hostname<short host name>
```

## The JD Edwards Enterprise Server - Port Test Fails

If the port test fails on the JD Edwards EnterpriseOne Enterprise Server, check the host entries in the `/etc/hosts` file. See **Edit the `/etc/hosts` File for Connectivity** section in this tutorial.

## Resolving Hostname Issues During Provisioning

If you encounter hostname issues during orchestration because the provisioning was run against machines with the long hostnames, FQDNs, or both, then use the following procedure to resolve the issue:

1. On the operating system level, change the hostnames of all servers in the on-premises architecture to use a short hostname without the FQDN.
2. On the database level, change all the hostnames in JDE tables to use short hostnames without using the FQDN.
3. Ping all the machines with short hostnames and verify that the ping test is successful.

See [Understanding Machine Names](#) for more information.

## Health Checks Fail as Final Step in OCI Provisioning

If the health checks fail during the final step in OCI Provisioning (as shown in the example below), it is likely because the predefined ports for the Enterprise Server are either not enabled or not properly defined in the VCN.

The screenshot shows the Oracle JD Edwards Deployment console. The 'Deployment Status' section contains a table of tasks. The 'HealthCheck' task is highlighted with a red 'X' icon, indicating failure. A mouse cursor is pointing at the 'HealthCheck' task. To the right, the 'HealthCheck log details' window is open, showing the following log entries:

```
Nov 28 17:40:12 - Health check for sqejasdv started
Nov 28 17:43:12 - Health check for sqejasdv failed
Nov 28 17:43:12 - Health check for sqeaisdv started
Nov 28 17:43:13 - Health check for sqeaisdv failed
```

Task Name	Status
sqejasdv	✓
Install Server Manager Agent	✓
Distribute JDE Web Component to Server Manager Agent	✓
Register WLS in Server Manager Console	✓
Create Web Component Instance in Server Manager Console	✓
Configure JDE Web Component INI Setting	✓
sqeaisdv	✓
Install Server Manager Agent	✓
Distribute JDE Web Component to Server Manager Agent	✓
Register WLS in Server Manager Console	✓
Create Web Component Instance in Server Manager Console	✓
Configure JDE Web Component INI Setting	✓
Integration	✓
HealthCheck	✗
sqejasdv	✗
sqeaisdv	✗

## Security Server JdeSocket Or SocketException Errors When Logging In To EnterpriseOne

If a JD Edwards EnterpriseOne Server is deployed inside a firewall-protected network, you must enable predefined ports so that all NET server ports are allocated within the predefined port range.

### Error ORA-00904: "NRUSER1": Invalid Identifier for Table F980051

The JAS log files displays the following error after you install EnterpriseOne using the JD Edwards One-Click Provisioning Console with Tools 9.2.2.4:

```
[SEVERE] - [JDBJ] SQLException occurred in the SQLPhysicalConnection.select():Auto: | Table or View Name = F980051 - Data Source[0] = System - 920 java.sql.SQLException: ORA-00904: "NRUSER1": invalid identifier
```

```
[SEVERE] - [BASE] com.jdedwards.database.base.JDBException: [SQL_EXCEPTION_OCCURRED] An SQL exception occurred: ORA-00904: "NRUSER1": invalid identifier . java.sql.SQLException: ORA-00904: "NRUSER1": invalid identifier
```

```
[SEVERE] - [BASE] com.jdedwards.database.base.JDBException: [SQL_EXCEPTION_OCCURRED] An SQL exception occurred: ORA-00904: "NRUSER1": invalid identifier . com.jdedwards.database.base.JDBException: [SQL_EXCEPTION_OCCURRED] An SQL exception occurred: ORA-00904: "NRUSER1": invalid identifier
```

#### Cause:

The delivered image for One-Click Provisioning has incorrect OCM mappings for the F980051 table. The OCM for this table is pointing to the System - 920 database data source where the structure of the table is not consistent with the table specs.

#### Solution:

1. Check both the System and the Server Map data source OCM mappings and change the OCM mappings as shown in the following list:

Use the following correct OCM mappings for F98005\* tables:

- o F980051 (Bell Status) mapped to Control Tables - <Environment>
- o F980052 (Notification Execution History) mapped to Control Tables - <Environment>
- o F980053 (Subscription Metadata) mapped to Control Tables - <Environment>
- o F980054 (Notification Queue) mapped to System - 920
- o F980055 (Notifications Constants) mapped to System - 920
- o F980056 (Notifications Offline Repository) mapped to System - 920
- o F980057 (Notifications Offline Repository Archive) mapped to System - 920

2. Restart the Enterprise service.

For more information, see Doc ID 2408472.1 on My Oracle Support.

## Error in Server Manager Console Enterprise Server Process Detail Graph

<b>Symptom:</b>	Unable to display the results of the selected monitor. The monitor is no longer available for viewing.
-----------------	--

<b>Cause:</b>	The monitors were registered for each of the Enterprise Server instances but the Server manager Console did not identify these monitors, and hence caused an issue related to the graphs.
<b>Resolution:</b>	Verify monitors.xml located in the path \SCFMC\targets\home\ , and check if the entries are recorded for all the required monitors. If the graphs are not visible for a particular monitor even if the monitor's entry is recorded in the monitors.xml file, then restart the Server Manager Console.

## Orchestrating JD Edwards EnterpriseOne Servers Returns IPV6 Is Not Disabled

Use this procedure if One-Click Provisioning returns this message for any Linux server that you are provisioning:

- IPV6 Is Not Disabled

- a. Ensure that `/etc/sysctl.conf` file contains below list of entries:

```
net.ipv6.conf.default.disable_ipv6 = 1
```

```
net.ipv6.conf.all.disable_ipv6 = 1
```

- b. If the above settings do not exist, you must update the `/etc/sysctl.conf` file to include the above settings.

**Note:** A mandatory reboot is necessary in order for the settings to take affect. and reboot the machine.

- c. Verify the output of below command to ensure there is no entry for the string "inet6"

```
sudo ifconfig | grep inet6
```

- d. If the string "inet6" continues to occur in the output of the above command output, verify your settings and ensure that the machine has been rebooted.

## Regenerating and Reinstalling Self-Signed Certificates for One-Click Provisioning

This section shows you how to regenerate and reinstall Self-Signed Certificates for One-Click Provisioning.

The deployment of JD Edwards EnterpriseOne One-Click Provisioning includes temporary self-signed certificates. By design, these certificates are set to expire at one-year intervals from when they were generated.

**Note:** After self-signed certificates are expired, Oracle strongly recommends that you generate and install your own CA certificates as described in this section. These must be certificates that are verified by a verified CA authority such as Entrust and Symantec Corporation.

### Prerequisite

You must have an installation of Java Keystore.

## Generating Self-Signed Certificates on Linux

Use this procedure to generate self-signed certificates on Linux.

1. Log into Provisioning Server.
2. Run the following commands (where each bulleted item is one contiguous line):
  - o `sudo -i`
  - o `mv /u01/jde920/.vm_unconfigured /u01/jde920/vm_unconfigured`
  - o `/u01/jdk1.8.0/jre/bin/keytool -delete -alias cert -keystore "/u01/jdk1.8.0/jre/lib/security/cacerts" -storepass *****`
  - o `/u01/CertGen/ConfigureCertKey_CC.sh`
  - o `/u01/CertGen/ConfigureCertKey_SMC.sh <WebLogic Admin Password>`
  - o `mv /u01/jde920/vm_unconfigured /u01/jde920/.vm_unconfigured`

### Note:

- o The `storepass` value `*****` in above commands is the WebLogic Admin password.
- o The generated `cert.pem` file is located in: `/u01/E1CloudConsole/keys`
- o The log file path is: `/var/log`

## Importing the Self-Signed Certificate into Target Machines on Linux

The self-signed certificate file that you generated in the previous steps must be imported into these target machines that were deployed by JD Edwards EnterpriseOne One-Click Provisioning:

- HTML Server
- Enterprise Server
- Oracle Database Server

### HTML Server

Use this procedure to import the self-signed certificate into the HTML Server.

1. Run this command:

```
sudo -i
```
2. Get the `cert.pem` file from Provisioning Server, which you generated in the previous procedure in this section entitled: "Generating Self-Signed Certificates on Linux".

3. Use this command to determine if a certificate with an alias of **smcert** is already imported to `jdk/jre/lib/security/cacerts`, where this command is a single contiguous line:  

```
/u01/jde_home/SCFHA/jdk/jre/bin/keytool -list -v -alias smcert -keystore "/u01/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

If the results of the above command indicate that an alias of **smcert** certificate is already imported to the JDK/JRE lib location, use this command to remove it, where this command is a single contiguous line:  

```
/u01/jde_home/SCFHA/jdk/jre/bin/keytool -delete -file cert.pem -alias smcert -keystore "/u01/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

**Note:** The storepass value `*****` in above commands is the default password for Java trustStore.
4. Use these commands to import the certificate that you generated in the previous procedure of this section entitled: "Generate Self-Signed Certificates" to `/u01/jde_home/SCFHA/jdk`, where each command is a single contiguous line:  

```
/u01/jde_home/SCFHA/jdk/jre/bin/keytool -import -file cert.pem -alias smcert -keystore "/u01/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

```
/u01/jde_home/SCFHA/jdk/jre/bin/keytool -list -v -alias smcert -keystore "/u01/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

**Note:** The storepass value `*****` in above commands is the default password for Java trustStore.
5. Use this command to determine if a certificate with an alias of **smcert** is already imported for the JDK path:  

```
/u01/oracleJDE/jdk_path/jre/bin/keytool -list -v -alias smcert -keystore "/u01/oracleJDE/jdk_path/jre/lib/security/cacerts" -storepass *****
```

If the results of the above command indicate that an alias of **smcert** certificate is already imported, use this command to remove it, where this command is a single contiguous line:  

```
/u01/oracleJDE/jdk_path/jre/bin/keytool -delete -alias smcert -keystore "/u01/oracleJDE/jdk_path/jre/lib/security/cacerts" -storepass *****
```

**Note:** The storepass value `*****` in above commands is the WebLogic Admin password.
6. Use these commands to import the certificate that you generated in the previous procedure of this document entitled: "Generate Self-Signed Certificates" to `/u01/oracleJDE/jdk_path`, where each command is a single contiguous line:  

```
/u01/oracleJDE/jdk_path/jre/bin/keytool -import -file cert.pem -alias smcert -keystore "/u01/oracleJDE/jdk_path/jre/lib/security/cacerts" -storepass *****
```

```
/u01/oracleJDE/jdk_path/jre/bin/keytool -list -v -alias smcert -keystore "/u01/oracleJDE/jdk_path/jre/lib/security/cacerts" -storepass *****
```

**Note:** The storepass value `*****` in above commands is the WebLogic Admin password.

## Enterprise Server

Use this procedure to import the self-signed certificate into the HTML Server.

1. Run this command:

```
sudo -i
```

2. Get the `cert.pem` file from Provisioning Server, which you generated in the previous procedure in this section entitled: "Generating Self-Signed Certificates on Linux".
3. Use this command to determine if a certificate with an alias of **smcert** is already imported to `jdk/jre/lib/security/cacerts`, where this command is a single contiguous line:

```
/u01/jde920/jde_home/SCFHA/jdk/jre/bin/keytool -list -v -alias smcert -keystore "/u01/jde920/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

If the results of the above command indicate that an alias of **smcert** certificate is already imported, use this command to remove it, where this command is a single contiguous line:

```
/u01/jde920/jde_home/SCFHA/jdk/jre/bin/keytool -delete -alias smcert -keystore "/u01/jde920/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

**Note:** The storepass value `*****` in above commands is the default password for Java trustStore.

4. Use these commands to import the certificate that you generated in the previous procedure of this section entitled: **Generate Self-Signed Certificates** to `/u01/jde920/jde_home/SCFHA/jdk`, where each command is a single contiguous line:

```
/u01/jde920/jde_home/SCFHA/jdk/jre/bin/keytool -import -file cert.pem -alias smcert -keystore "/u01/jde920/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

```
/u01/jde920/jde_home/SCFHA/jdk/jre/bin/keytool -list -v -alias smcert -keystore "/u01/jde920/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

**Note:** The storepass value `*****` in above commands is the default password for Java trustStore.

5. Use this command to determine if a certificate with an alias of **smcert** is already imported for the JDK path:

```
/u01/jdk8_32/jre/bin/keytool -list -v -alias smcert -keystore "/u01/jdk8_32/jre/lib/security/cacerts" -storepass *****
```

If the results of the above command indicate that an alias of `smcert` certificate is already imported, use this command to remove it, where this command is a single contiguous line:

```
/u01/jdk8_32/jre/bin/keytool -delete -alias smcert -keystore "/u01/jdk8_32/jre/lib/security/cacerts" -storepass *****
```

**Note:** The storepass value `*****` in above commands is the Site Key password.

6. Use these commands to import the certificate that you generated in the previous procedure of this section entitled: "Generate Self-Signed Certificates" to `/u01/jdk8_32`, where each command is a single contiguous line:

```
/u01/jdk8_32/jre/bin/keytool -import -file cert.pem -alias smcert -keystore "/u01/jdk8_32/jre/lib/security/cacerts" -storepass *****
```

```
/u01/jdk8_32/jre/bin/keytool -list -v -alias smcert -keystore "/u01/jdk8_32/jre/lib/security/cacerts" -storepass *****
```

**Note:** The storepass value `*****` in above commands is the Site Key password.

## Database Server

Use this procedure to import the self-signed certificate into the Oracle Database Server. Note that is only applicable if you are using Oracle Compute service for your Database Server; it not applicable if you are using the Oracle Database Service (DBS).

1. Log into the Oracle Compute Database Server.
2. Get the cert.pem file from Provisioning Server, which you generated in the previous procedure in this section entitled: "Generating Self-Signed Certificates on Linux".
3. Run this command:

```
sudo -i
```

4. Use this command is determine if a certificate with an alias of **smcert** is already imported to `jdk/jre/lib/security/cacerts`, where this command is a single contiguous line:

```
/u01/jde_home/SCFHA/jdk/jre/bin/keytool -list -v -alias smcert -keystore "/u01/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

If the results of the above command indicate that an alias of **smcert** certificate is already imported, use this command to remove it, where this command is a single contiguous line:

```
/u01/jde_home/SCFHA/jdk/jre/bin/keytool -delete -alias smcert -keystore "/u01/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

**Note:** The storepass value \*\*\*\*\* in above commands is the default password for Java trustStore.

5. Use these commands to import the certificate that you generated in the previous procedure of this document entitled: "Generate Self-Signed Certificates" to `/u01/jde_home/SCFHA/jdk`, where each command is a single contiguous line:

```
/u01/jde_home/SCFHA/jdk/jre/bin/keytool -import -file cert.pem -alias smcert -keystore "/u01/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

```
/u01/jde_home/SCFHA/jdk/jre/bin/keytool -list -v -alias smcert -keystore "/u01/jde_home/SCFHA/jdk/jre/lib/security/cacerts" -storepass *****
```

**Note:** The storepass value \*\*\*\*\* in above commands is the default password for Java trustStore.

## Generating Self-Signed Certificates on Microsoft Windows

Use this procedure to generate self-signed certificates on Microsoft Windows.

1. Log into Provisioning Server.
2. Open Windows Powershell **As Administrator**.

3. Run the following commands, where each command is a single contiguous line:

```
ren <drive>\JDE\PP\jde920\.vm_unconfigured <drive>\JDE\PP\jde920\vm_unconfigured

<drive>\JDE\jdk1.8_64\jre\bin\keytool -delete -alias cert -keystore "<drive>\JDE\jdk1.8_64\jre\lib
\security\cacerts" -storepass *****
```

**Note:** The storepass value \*\*\*\*\* in above command is the WebLogic Admin password.

```
$env:OPENSSL_CONF += "C:\JDE\bin\openssl.cnf"

<drive>\JDE\PP\CertGen\ConfigureCertKey_CC.ps1

<drive>\JDE\PP\CertGen\ConfigureCertKey_SMC.ps1 <WebLogic Admin Password>

ren <drive>\JDE\PP\jde920\vm_unconfigured <drive>\JDE\PP\jde920\.vm_unconfigured
```

## Importing the Self-Signed Certificate into Target Machines on Microsoft Windows

The self-signed certificate file that you generated in the previous steps must be imported into these target machines that were delivered by JD Edwards EnterpriseOne One-Click Provisioning:

- All Servers
- HTML Server
- Enterprise Server

### All Servers

Use this procedure to import the self-signed certificate into all Microsoft Windows servers.

1. Log into the each Microsoft Windows server.
2. Get the `cert.pem` file that is located on the Provisioning Server. You generated this key using the previous procedure in this section entitled: "Generating Self-Signed Certificates on Microsoft Windows".

On the Provisioning Server, this file is located at this location:

```
<drive>\JDE\PP\E1CloudConsole\keys
```

3. On each machine, use this command to determine if a certificate with an alias of **smcert** is already imported to `<drive>\JDE\jde_home\SCFHA\jdk`, where this command is a single contiguous line:

```
<drive>\JDE\jde_home\SCFHA\jdk\jre\bin\keytool -list -v -alias smcert -keystore

"<drive>\JDE\jde_home\SCFHA\jdk\jre\lib\security\cacerts" -storepass *****
```

If the results of the above command indicate that an alias of **smcert** certificate is already imported, use this command to remove it, where this command is a single contiguous line:

```
<drive>\JDE\jde_home\SCFHA\jdk\jre\bin\keytool -delete -alias smcert -keystore "<drive>\JDE\jde_home
\SCFHA\jdk\jre\lib\security\cacerts" -storepass *****
```

**Note:** The storepass value \*\*\*\*\* in above commands is the default password for Java trustStore.

4. On each machine, use these commands to import the certificate that you generated in the previous procedure of this section entitled: "Generate Self-Signed Certificates" to `<drive>\JDE\jde_home\SCFHA\jdk`, where each command is a single contiguous line:

```
<drive>\JDE\jde_home\SCFHA\jdk\jre\bin\keytool -import -file cert.pem -alias smcert -keystore "  
<drive>\JDE\jde_home\SCFHA\jdk\jre\lib\security\cacerts" -storepass *****  
<drive>\JDE\jde_home\SCFHA\jdk\jre\bin\keytool -list -v -alias smcert -keystore  
"<drive>\JDE\jde_home\SCFHA\jdk\jre\lib\security\cacerts" -storepass *****
```

**Note:** The storepass value \*\*\*\*\* in above commands is the default password for Java trustStore.

## HTML Server

Use this procedure to import the self-signed certificate into the HTML Server.

1. Log into the HTML server.
2. Get the `cert.pem` file that is located on the Provisioning Server. You generated this key using the previous procedure in this section entitled: "Generating Self-Signed Certificates on Microsoft Windows".

On the Provisioning Server, this file is located at this location:

```
<drive>\JDE\PP\E1CloudConsole\keys
```

3. Use this command to determine if a certificate with an alias of **smcert** is already imported to `c:\Program Files\Java\jdk1.8.0_201`, where this command is a single contiguous line:

```
<JDK_path>\jre\bin\keytool -list -v -alias smcert -keystore "  
<JDK_path>\jre\lib\security\cacerts" -storepass *****
```

If the results of the above command indicate that an alias of **smcert** certificate is already imported, use this command to remove it, where this command is a single contiguous line:

```
<JDK_path>\jre\bin\keytool -delete -alias smcert -keystore "  
<JDK_path>\jre\lib\security\cacerts" -storepass *****
```

**Note:** The storepass value \*\*\*\*\* in above commands is the WebLogic Admin password.

4. Use these commands to import the certificate that you generated in the previous procedure of this document entitled: "Generate Self-Signed Certificates" to `C:\Program Files\Java\jdk1.8.0_201`, where each command is a single contiguous line:

```
<JDK_path>\jre\bin\keytool -import -file cert.pem -alias smcert -keystore "<JDK_path>\jre\lib\security  
\cacerts" -storepass *****  
<JDK_path>\jre\bin\keytool -list -v -alias smcert -keystore "<JDK_path>\jre\lib\security\cacerts" -  
storepass *****
```

**Note:** The storepass value \*\*\*\*\* in above commands is the WebLogic Admin password.

## Enterprise Server

Use this procedure to import the self-signed certificate into the HTML Server.

1. Log into the Enterprise Server.
2. Get the `cert.pem` file that is located on the Provisioning Server. You generated this key using the previous procedure in this section entitled: "Generating Self-Signed Certificates on Microsoft Windows".

On the Provisioning Server, this file is located at this location:

```
<drive>\JDE\PP\E1CloudConsole\keys
```

3. Use this command to determine if a certificate with an alias of `smcert` is already imported to `<drive>\JDE\jdk8_32`, where this command is a single contiguous line:

```
<drive>\JDE\jdk8_32\jre\bin\keytool -list -v -alias smcert -keystore "
```

```
<drive>\JDE\jdk8_32\jre\lib\security\cacerts" -storepass *****
```

If the results of the above command indicate that an alias of **smcert** certificate is already imported, use this command to remove it, where this command is a single contiguous line:

```
<drive>\JDE\jdk8_32\jre\bin\keytool -delete -alias smcert -keystore
```

```
"<drive>\JDE\jdk8_32\jre\lib\security\cacerts" -storepass *****
```

**Note:** The storepass value `*****` in above commands is the Site Key password.

4. Use these commands to import the certificate that you generated in the previous procedure of this document entitled: "Generate Self-Signed Certificates" to `<drive>\JDE\jdk8_32`, where each command is a single contiguous line:

```
<drive>\JDE\jdk8_32\jre\bin\keytool -import -file cert.pem -alias smcert -keystore"
```

```
<drive>\JDE\jdk8_32\jre\lib\security\cacerts" -storepass *****
```

```
<drive>\JDE\jdk8_32\jre\bin\keytool -list -v -alias smcert -keystore "
```

```
<drive>\JDE\jdk8_32\jre\lib\security\cacerts" -storepass *****
```

**Note:** The storepass value `*****` in above commands is the Site Key password.

# 17 Performing Basic Administration

## Starting and Stopping Services

This section shows you how to start or stop services.

In general you should use Server Manager to start or stop services, or to check the status of services, for all JD Edwards EnterpriseOne servers.

### Prerequisite

A deployment of JD Edwards EnterpriseOne.

## Starting and Stopping Services

You can use these commands to manually start, stop, or check the status of the **jde-sm** service for the Server Manager Console Server:

```
sudo su - root  
  
service jde-sm start  
  
service jde-sm stop  
  
service jde-sm status
```

## Configuring the Public IP Address as an Internal Hostname on Client Machine

This section shows you how to configure the public IP address as an internal hostname on client machine.

Without this step, the JD Edwards EnterpriseOne application websites can only be accessed using the Public IP Address in a browser.

### Prerequisite

A deployment of JD Edwards EnterpriseOne.

## Configuring the Public IP Address

As a convenience, in addition to access using a Public IP address, you can also access JD Edwards EnterpriseOne application websites using the hostname. The steps given below assume that you have not configured a public web entry point for the JD Edwards EnterpriseOne application tier. In that case you need to manually add the public IP address and internal DNS hostname of the JD Edwards EnterpriseOne application tier in the hosts file of the client machine.

Alternatively, these steps can be replaced by contacting your site's network administrator and having the address and hostname setup in DNS.

### Access from a UNIX Host

Modify the `/etc/hosts` file as shown below. For example:

- public IP: **123.456.789.999**
- public hostname: **demo.company.com**
- Using the above example values, the `/etc/hosts` file must contain this line:

**123.456.789.999 demo demo.company.com**

### Access from a Microsoft Windows System

Modify the `c:\Windows\System32\drivers\etc\hosts` file as shown below. For example:

- public IP: **123.456.789.999**

# 18 Considering Optional Administrative Tasks

## Understanding JD Edwards EnterpriseOne Security

This section provides an overview of the JD Edwards EnterpriseOne security.

A minimal JD Edwards EnterpriseOne security definition has been shipped with your Database Server.

### Prerequisite

A deployment of JD Edwards EnterpriseOne.

## JD Edwards EnterpriseOne Security

Follow the instructions in the *JD Edwards EnterpriseOne Applications Release 9.2 Installation Guide for Oracle on UNIX* (in the chapter entitled: Performing Post Installation Tasks, in the section entitled: Working With Signon Security and Table Creation Security to change the passwords within EnterpriseOne for JDE and PS920 so they match any changes you make to the passwords for the Oracle Database users.

Additionally, for table creation security you should use the Datasource Master application using the Database Privilege row exit. For further details refer to the *JD Edwards EnterpriseOne Tools Security Administration Guide Release 9.2*.

JD Edwards One-Click Provisioning provides a preconfigured environment with sample data, user-defined content, roles, and security permissions. The JDE user id you used to sign on is associated with the SYSADMIN role, which has a very broad set of permissions. As such, the JDE user will have access to a large number of applications, EnterpriseOne pages, and other content. UDO View Security has been enabled for 9.2.1.0. It may be necessary to adjust security accordingly. To modify or set up the permissions for the JDE user or other users that you add to this environment, refer to *Provisioning User and Role Profiles* in the JD Edwards EnterpriseOne Tools Security Administration Guide Release 9.2.

## Configuring AIS Server Depending on How You Manage Users

This section shows you how to configure the AIS Server depending on how you manage users.

REST services on the JD Edwards EnterpriseOne AIS Server can use HTTP Basic Authentication for access. Support for HTTP Basic Authentication is enabled out of the box and is required to run the EnterpriseOne Orchestrator Client, create custom Java calls from orchestrations, and use the AIS client Java API (versions 1.2.1.x and higher).

### Prerequisite

A deployment of JD Edwards EnterpriseOne.

## Configuring AIS Server

When the AIS Server is deployed on Oracle WebLogic Server, the Oracle WebLogic Server may require the following additional configuration depending on how you manage users:

- If you are maintaining a user registry in Oracle WebLogic Server that matches the user registry in EnterpriseOne, with identical sets of user names and passwords in each system, you do NOT need to modify your configuration.
- If you are NOT maintaining identical sets of users in Oracle WebLogic Server and EnterpriseOne, then you need to perform the following steps to modify your Oracle WebLogic Server configuration. This ensures that Oracle WebLogic Server will not intercept HTTP Basic Authentication credentials passed from the REST service.
  1. In the WebLogic Server domain for your AIS Server, in the Config directory, find the `config.xml` file.
  2. Add this configuration as the last line within the `<security-configuration>` element, just before the `</security-configuration>` tag:

```
<enforce-valid-basic-auth-credentials>false</enforce-valid-basic-auth-credentials>
```
  3. Restart the AIS Server for the changes to take effect.

The following is an example of this configuration in the `<security-configuration>` element:

```
<node-manager-password-encrypted>{AES}tzAokzTHACTNNmkuutLPQEpP8bfk7Ble24vmoycooic=</node-manager-password-encrypted>

<enforce-valid-basic-auth-credentials>false</enforce-valid-basic-auth-credentials>

</security-configuration>

<server>
```

## Updating the Java.security File (Optional)

This section provides a description of an optional procedure that describes how to edit the **Java.security** file in a JDK to restore certain settings in server instances that were deployed by One-Click Provisioning.

### Prerequisite

A deployment of JD Edwards EnterpriseOne.

### Editing the Java.security File

The deployment of a JDK to servers using JD Edwards EnterpriseOne One-Click Provisioning removes the string **anon, NULL** from the property **jdk.tls.disabledAlgorithms** in this file:

```
\jre\lib\security\Java.security
```

Optionally, after the One-Click deployment is complete, you can add the string back in the JDK for each deployed server. For example, you can append the string **anon, NULL** in the Java.security file in the **jdk.tls.disabledAlgorithms** section as shown in the **bolded** string below:

```
jdk.tls.disabledAlgorithms=SSLv3, RC4, DES, MD5withRSA, DH keySize < 1024, \ EC keySize < 224, 3DES-EDE-CBC,
anon, NULL
```

For additional details, refer to [Java.security File](#) in the Server Manager Guide.

## Using the Linux Logical Volume Manager (LVM) to Manage Free Disk Space

This section shows you how to use the Linux Logical Volume Manager (LVM) to Manage Free Disk Space.

The following procedures demonstrate how to extend the /u01 disk file system. An LVM command summary is also provided.

### Prerequisite

- An understanding of Linux system administration.
- Appropriate sudo permissions at the Linux file system level.
- Appropriate access and authority to the Oracle Cloud Infrastructure environment.

## Using the Linux Logical Volume Manager (LVM) to Manage Free Disk Space

The following procedures demonstrate how to extend the /u01 disk file system by:

- Recreating the partition table to include the free space
- Resizing the physical volume
- Extending the physical volume to the existing logical volume

### Recreating the Partition Table

To make the free disk usable, you must recreate the partition table. This is done using the fdisk command as illustrated in the following procedure.

To recreate the a partition table:

1. Log into the instance as the opc user and switch to the root user using this command:

```
sudo -i
```

2. Review available disk space in /u01 prior to adding the new disk space by running this command:

```
df -h /u01
```

#### **Example:**

```
df -h /u01
Filesystem Size Used Avail Use% Mounted on /dev/mapper/vg_jde00-lv_jde00
6.9G 3.0G 3.7G 45% /u01
```

3. Run these commands to show unallocated space:

```
parted /dev/xvdb
```

```
print free
```

quit

**Example:**

```
parted /dev/xvdb
```

```
GNU Parted 2.1
```

```
Using /dev/xvdb
```

```
Welcome to GNU Parted! Type 'help' to view a list of commands. (
```

```
parted) print free
```

```
Number Start End Size Type File system Flags
```

```
32.3kB 1049kB 1016kB Free Space
```

```
1 1049kB 538MB 537MB primary ext3 boot
```

```
2 538MB 20.7GB 20.2GB primary lvm
```

```
3 20.7GB 28.2GB 7509MB primary lvm
```

```
28.2GB 39.7GB 11.5GB Free Space
```

```
(parted) quit
```

4. To modify the partition table, run `fdisk` on the disk device. For example, in the example used in this guide is `xvdb`. `fdisk /dev/xvdb`
5. Next, at the prompts from the `fdisk` command, enter the following command letters to delete the current partition number `3`, and recreate primary partition `#3` with all the remaining free sectors:

```
d
3
n
p
3
<enter>
<enter>
```

w

### Example:

```
fdisk /dev/xvdb
```

**Note:** DOS-compatible mode is deprecated. It's strongly recommended to switch off the mode (command 'c') and change display units to sectors (command 'u').

```
Command (m for help): d
```

```
Partition number (1-4): 3
```

```
Command (m for help): n
```

```
Command action
```

```
e extended
```

```
p primary partition (1-4)
```

```
p
```

```
Partition number (1-4): 3
```

```
First cylinder (2520-4830, default 2520):
```

```
Using default value 2520
```

```
Last cylinder, +cylinders or +size{K,M,G} (2520-4830, default 4830):
```

```
Using default value 4830
```

```
Command (m for help): w
```

```
The partition table has been altered!
```

```
Calling ioctl() to re-read partition table.
```

**Note:** Re-reading the partition table failed with error 16: Device or resource busy. The kernel still uses the old table. The new table will be used at the next reboot or after you run `partprobe(8)` or `kpartx(8)` Syncing disks.

6. This process extended the `/dev/xvdb` partition to include all of the free space. This new disk will be added to the `/u01` logical volume. The system now needs to be rebooted before the partition table change will be recognized by the system. Use the `reboot` command to reboot now. Continue with the next section after rebooting.

## Resizing the Physical Volume with the Partition Table Changes

After you resize the partition table as described in the previous procedure, the disk image is now ready to become a physical volume that can be added to a logical volume.

To resize the physical volume with the new partition space:

1. After the system finishes rebooting, log back into the instance as the `opc` user and switch to the `root` user using this command: `sudo -i`

2. Execute the `pvresize` command as shown below:

```
pvresize /dev/xvdb3
```

**Example:**

```
pvresize /dev/xvdb3
```

```
Physical volume "/dev/xvdb3" changed<
```

```
1 physical volume(s) resized / 0 physical volume(s) not resized
```

**See Also**

For more information refer to the Linux man pages for the `pvresize` command.

### **Extending the Volume Group with the New Physical Disk**

To extend the volume group with the new physical disk:

1. You must determine the name of the volume group to which the disk will be added by using the `vgs` and `lvscan` commands. In the below example, the name of the volume group with free space is `vg_jde00`, and it is located in this directory: `/dev/mapper/vg_jde00-lv_jde00`

**Example:**

```
vgs
```

```
VG #PV #LV #SN Attr VSize VFree  
vg_apol 1 7 0 wz--n- 18.78g 32.00m  
vg_jde00 1 1 0 wz--n- 17.70g 10.71g
```

The `vgs` command shows the 10.71g of free space is in volume group `vg_jde00`

**Example:**

```
lvscan
```

```
ACTIVE '/dev/vg_jde00/lv_jde00' [6.99 GiB] inherit  
ACTIVE '/dev/vg_apol/lv_root' [4.00 GiB] inherit  
ACTIVE '/dev/vg_apol/lv_home' [1.00 GiB] inherit  
ACTIVE '/dev/vg_apol/lv_tmp' [6.00 GiB] inherit  
ACTIVE '/dev/vg_apol/lv_var' [1.50 GiB] inherit  
ACTIVE '/dev/vg_apol/lv_var.log' [2.00 GiB] inherit  
ACTIVE '/dev/vg_apol/lv_var.log.audit' [256.00 MiB] inherit  
ACTIVE '/dev/vg_apol/lv_swap' [4.00 GiB] inherit
```

The `lvscan` shows that volume group `vg_jde00` has one logical volume named `lv_jde00`. This is where the free disk space will be put in this example. Take the volume group name (`vg_jde00`) and the logical volume name (`lv_jde00`) and confirm the location of the logical volume in the `/dev/mapper` directory.

**Example:**

```
ls /dev/mapper/vg_jde00-lv_jde00  
/dev/mapper/vg_jde00-lv_jde00
```

2. Using the volume group name found in the previous step, extend the volume group by using the `lvextend` command. The below example uses **`/dev/mapper/vg_jde00-lv_jde00`**.

```
lvextend --resizefs -l +100%FREE /dev/mapper/vg_jde00-lv_jde00
```

**Example:**

```
lvextend --resizefs -l +100%FREE /dev/mapper/vg_jde00-lv_jde00
```

Size of logical volume `vg_jde00/lv_jde00` changed from 6.99 GiB (1790 extents) to 17.70 GiB (4531 extents).

Logical volume lv\_jde00 successfully resized

resize2fs 1.43-WIP (20-Jun-2013)

Filesystem at /dev/mapper/vg\_jde00-lv\_jde00 is mounted on /u01; on-line resizing required

old\_desc\_blocks = 1, new\_desc\_blocks = 2

Performing an on-line resize of /dev/mapper/vg\_jde00-lv\_jde00 to 4639744 (4k) blocks.

The filesystem on /dev/mapper/vg\_jde00-lv\_jde00 is now 4639744 blocks long.

3. Confirm the space is now available for use by running this command:

```
df -h /u01
```

**Example:**

```
df -h /u01
```

Filesystem	Size	Used	Avail	Use%	Mounted on
------------	------	------	-------	------	------------

/dev/mapper/vg_jde00-lv_jde00					
-------------------------------	--	--	--	--	--

18G	3.0G	14G	18%		/u01
-----	------	-----	-----	--	------

**See Also**

For more information refer to the Linux man pages for the lvextend command.

### Logical Volume Manager Command Summary

This section provides a summary of the Logical Volume Manager commands used in the previous steps of this tutorial.

**[fdisk]**

This is the disk utility command.

To resize the number 3 primary partition, use this syntax where subsequent values are entered at the command prompts:

```
fdisk /dev/xvdb
d
3
n
p
3
<enter>
<enter>
w
```

**[pvresize]**

Use this utility to resize a disk or partition for use by LVM. For example:

```
pvresize /dev/xvdb3
```

**[vgscan]**

Use this command to scan all disks for volume groups and rebuild caches (returns names).

### **[vgextend]**

Use this utility to resize a disk or partition for use by LVM. For example:

```
vgextend VolGroup00 /dev/hdc1
```

### **[lvextend]**

Use this command to extend the size of a logical volume. For example:

```
lvextend --resizefs -l +100%FREE /dev/mapper/vg_jde00-lv_jde00
```



# 19 Upgrading Your One-Click Provisioned Environment

## Upgrade Learning Path

The following learning path will guide you through the upgrade process for your One-Click provisioned environment:

*[Upgrading JD Edwards EnterpriseOne on a One-Click Provisioned Target Environment on Linux](#)*

