

**Oracle Field Service Configurations for
Oracle Work and Asset Cloud Service
Integration to Oracle Field Service**

Setup Guide

Release 25.4

G35534-01

June 2025

Oracle Field Service Configurations for Oracle Work and Asset Cloud Service Integration to Oracle Field
Service Setup Guide

Copyright © 2000, 2025 Oracle and/or its affiliates.

Contents

Preface	i
Audience	ii
Documentation and Resources	ii
Updates to Documentation.....	ii
Documentation Accessibility	iii
Conventions.....	iii
Acronyms.....	iii
 Chapter 1	
Accelerator Overview	1-1
Configuration Overview	1-2
Accelerator Package	1-2
Accelerator Activity Types	1-2
 Chapter 2	
Installing the Basic Accelerator Package	2-1
Order of Importing the Package	2-2
Activity Types.....	2-2
Properties.....	2-3
Glossary.....	2-3
Forms and Plugins	2-4
Measurement Plugin	2-5
Resource Usage Plugin	2-6
Service History Plugin	2-9
Validate Completion Plugin.....	2-12
Planned Service History Plugin.....	2-17
Asset Component Install Exchange Undo Plugin	2-20
Lock Unlock Activity Plugin	2-26
Pick Up Work Plugin.....	2-26
Materials Plugin	2-32
Asset Attribute Plugin	2-40
Asset History Plugin	2-43
View In Map	2-44
User Types	2-45
 Chapter 3	
Additional OFS Configurations	3-1
Sync Mobile Control Data Information from WACS to OFS	3-2
Organization.....	3-7
Work Zones.....	3-7
Resource and Bucket Info.....	3-8
Applications.....	3-10
Configuring the Crew.....	3-11

Adding Crew and Crew Member	3-12
Adding Truck Resource Type	3-13
Assigning Resources	3-14
Offline vs Online Mode.....	3-15
Crew Time	3-17
Inventory Types	3-17
Activity Links	3-20
Timesheet/ Other Direct Charges Flag	3-24
Timeout Seconds	3-25
Checklist	3-26

Chapter 4

User Operations	4-1
Starting the Activity	4-2
Locking Activity	4-2
Activity Details	4-4
Service Histories	4-6
Planned Service Histories.....	4-7
Asset Service Histories	4-10
Measurements.....	4-14
Asset Attribute	4-16
Asset History	4-16
Resource Usage	4-17
Activity Completion	4-21
Asset Installs and Removals	4-21
Pick Up and Follow Up Orders	4-32
Follow Up Work Order.....	4-32
Follow Up Work Request.....	4-33
Mobile Inventory Management	4-33
Overview	4-33
Truck Materials Lifecycle Examples.....	4-36
Truck Storeroom Admin Sync	4-37
Truck Inventory Snapshot	4-37
Assigning Truck to Crews.....	4-38
Using Inventories for Activities	4-39
Update Truck Inventories.....	4-40

Chapter 5

Customizations	5-1
Adding New Fields to Field Activity.....	5-2
Oracle Field Service Configurations.....	5-2
Oracle Utilities Work and Asset Cloud Service Configurations	5-3
User Defined Fields.....	5-4
Adding Custom Business Objects.....	5-5
Plugins Rendering Data	5-5
Measurements	5-5
Resource Usage.....	5-6
Service History.....	5-6
Asset Component Install Exchange Undo.....	5-7
Validate Completion	5-7
Lock Unlock.....	5-8
Pick Up	5-8
Materials.....	5-8
Asset Attribute.....	5-9
Asset History.....	5-9
Validation for Completion	5-9

Chapter 6

Hosting Plug-Ins in OFS	6-1
Hosting Files on a Web Server.....	6-1
Storing Files on Object Storage.....	6-2

Chapter 7

Construction Work Management Support	7-1
Pre-requisites	7-2
Construction Work Activity Operations.....	7-3
Install/Undo Install Tracked Asset.....	7-3
Install/Undo Install Non Tracked Asset.....	7-9
Support for Controls	7-11
Remove Asset	7-11
Install No Asset.....	7-12
Remove No Asset	7-13
Update Quantity	7-13
Interim Completion of Construction Work Activity	7-14

Preface

Welcome to the Oracle Field Service Configurations for Oracle Work and Asset Cloud Service Integration to Oracle Field Service Setup Guide for release 25.4. This document covers the Oracle Field Service configurations, as well as related information required for this integration.

Note: The screenshots and images provided in this document are sample references based on the current release of Oracle Field Service Configurations for Oracle Work and Asset Cloud Service Integration to Oracle Field Service. They may change based on changes in future releases.

The preface includes the following:

- [Audience](#)
- [Documentation and Resources](#)
- [Updates to Documentation](#)
- [Documentation Accessibility](#)
- [Conventions](#)
- [Acronyms](#)

Audience

This document is intended for anyone implementing the Oracle Utilities Integration for Work and Asset Cloud Service and Oracle Field Service.

Documentation and Resources

For more information regarding this integration, foundation technology and the edge applications, refer to the following documents:

Product Documentation

Topic	Location
Oracle Field Service Configurations for Oracle Work and Asset Cloud Service Integration to Oracle Field Service documentation	https:// docs.oracle.com/en/industries/energy-water/integrations-index.html
Oracle Utilities Work and Asset Cloud Service documentation	https://docs.oracle.com/en/industries/energy-water/work-asset-cloud-service/index.html
Oracle Field Service documentation	https://docs.oracle.com/en/cloud/saas/field-service/index.html

Additional Documentation

Resource	Location
Oracle Integration Cloud Service documentation	Refer to the OIC documentation at: https://docs.oracle.com/en/cloud/paas/integration-cloud/index.html
Oracle Support	Visit My Oracle Support at https://support.oracle.com regularly to stay informed about updates and patches. Refer to the <i>Certification Matrix for Oracle Utilities Products (Doc ID 1454143.1)</i> on My Oracle Support to determine if support for newer versions of the listed products is included.
Oracle University for training opportunities	http://education.oracle.com/

Updates to Documentation

The complete Oracle Field Service Configurations for Oracle Work and Asset Cloud Service Integration to Oracle Field Service documentation set is available from Oracle Help Center at <https://docs.oracle.com/en/industries/energy-water/index.html>.

Visit [My Oracle Support](#) for additional and updated information about the product.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers have access to electronic support for the hearing impaired. Visit: <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs>

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Acronyms

The following terms are used in this document:

Term	Expanded Form
OFS	Oracle Field Service
OUWAM/WAM	Oracle Utilities Work and Asset Management
OIC	Oracle Integration Cloud
OUWACS/WACS	Oracle Utilities Work and Asset Cloud Service

Chapter 1

Accelerator Overview

This chapter focuses on the software requirements for Oracle Field Service and provides an overview of the configuration. It includes the following sections:

- [Configuration Overview](#)
- [Accelerator Package](#)
- [Accelerator Activity Types](#)

Configuration Overview

This section covers basic Oracle Field Service configurations, such as Activity Types, User Types, Properties, UI screens, validations for these UIs, plugins and resource configurations.

Accelerator Package

The accelerator package includes various user types, properties, and plugins. This document explains the configurations for other elements such as activity types, work zones, work skills, work conditions and outbound channel.

The package helps customers to configure and set up Oracle Field Service to be used in the Oracle Utilities Work and Asset Cloud Service integration to Oracle Field Service as the package contains only Oracle Utilities Work and Asset Cloud Service and Oracle Integration Cloud configuration files and instructions. It is used in addition to the integration package that provides a complete end-to-end set up for the integration.

The contents of the package are:

- **User Types:** Define layouts and UI screens. Refer to the [User Types](#) section for more details.
- **Properties:** Create layouts and mapping. Refer to the [Properties](#) section for more information.
- **Plugins:** The plugins that are part of this integration are measurements, service history, planned service history, resource usage, assetComponentInstallExchangeUndo, pick up work, lock unlock, materials, asset attributes, asset history, and validate completion. Refer to the [Forms and Plugins](#) section for more information.

Accelerator Activity Types

This accelerator is a sample and supports a few Activity Types in this release. More activity types can be added based on the requirement.

Chapter 2

Installing the Basic Accelerator Package

This chapter focuses on importing the files that come as a part of the package and configuring them in the Oracle Field Service environment for the integration to run successfully. Make sure to follow the same sequence for successful configuration.

- [Order of Importing the Package](#)
- [Activity Types](#)
- [Properties](#)
- [Glossary](#)
- [Forms and Plugins](#)
- [User Types](#)

Order of Importing the Package

Import the following packages. Make sure to follow the order in which they are mentioned below.

1. Properties
2. Glossary
3. Measurements Plugin
4. Resource Usage Plugin
5. Service History Plugin
6. Validate Completion Plugin
7. Planned Service History Plugin
8. Asset Component Install Exchange Undo Plugin
9. Lock Unlock Activity Plugin
10. Pick Up Work Plugin
11. Materials Plugin
12. Asset Attribute Plugin
13. Asset History Plugin
14. WACS OFS User Type
15. WACS OFS Dispatcher User Type

Activity Types

Activity types define the categories of the activity supported by Oracle Field Service (in this case, Oracle Utilities Work and Asset Cloud Service integration to Oracle Field Service). Activity types are synchronized part of admin data from Oracle Utilities Work and Asset Cloud Service to Oracle Field Service.

As a pre-requisite, before running Admin Sync, perform *any* of the following steps.

To create an Activity Type group:

1. Login to Oracle Field Service with valid credentials.
2. Click the hamburger menu icon (icon with three horizontal lines) on the upper-left corner of the **Home** page.
3. Navigate to **Configuration > Resources, Activities, Inventories > Activity Types**.
4. Click **Add Group**.

5. Enter “WAM-OFSC” and then click **Add**.

The screenshot shows a dialog box titled "Add Group". It has a close button (X) in the top right corner. The dialog contains several input fields:

- * Label: WAM-OFSC
- * Name: WAM-OFSC
- * English: WAM-OFSC
- SpanishLA: (empty)
- French (European): (empty)
- Portuguese (Brazil): (empty)
- Chinese (Traditional): (empty)

 At the bottom of the dialog are two buttons: "Cancel" on the left and "Add" on the right.

Properties

Properties enable the integration specific UIs create and map the Oracle Field Service UI element with a property. Each property is classified into types such as field, integer, enumeration, string based on the requirements and should be addressed using this property.

To import the property file included in the accelerator package:

1. On the **Configuration** page, select **Resources, Activities, Inventories > Properties**.
2. Click **Import**.
3. Browse to the location of the file to be imported and click **Import**.
4. Verify the successful import of the file. The **Successfully Imported** message with number of properties imported is displayed. Make sure the **Imported with warnings** and **Not imported** count is 0.

Glossary

Glossary is used for cosmetic changes in label names. This function provides the flexibility to change labels based on the business needs.

To use the glossary function:

1. On the **Configuration** page, click **Glossary** in the **Displays** section.
2. Click **Import** to import the file provided as part of the package.
3. Click **Browse** and select the file. Click **Import**.

Make sure the file imports successfully.

4. As part of the package, the following labels are changed. Change the labels based on the preference.

```
Category (ctg),Identifier (id),Type (tp),ID/Label (lbl),User Types (ut),English (en-US)
"Glossary: mobile_shared, wap_inventory",glossary,translation,10109,,Assets/Equipment
"Glossary: mobile_shared,glossary,translation,10865,,Assets/Equipment
"Glossary: mobile_shared,glossary,translation,10767,,Assets/Equipment Details
"Glossary: wap_inventory,glossary,translation,10111,,Existing
"Screen Configuration - Mobility: Edit/View activity","fae3e1febea180ba048eb3f1b0c011f029fd5e","layout","list_inventories","C2M
OFSC","Equipment"
"Screen Configuration - Mobility: Edit/View activity","9bdc924764e5ac57bf15c4e166282c8a3189de","layout","list_inventories","WAM OFSC","Assets"
```

Category (ctg)	Identifier (id)	Type (tp)	ID/Label (lbl)	User Types (ut)	English (en-US)
Glossary: mobile_shared, wap_inventory	glossary	translation	10109		Assets/Equipment
Glossary: mobile_shared	glossary	translation	10865		Assets/Equipment
Glossary: mobile_shared	glossary	translation	10767		Asset/Equipment Details
Glossary: wap_inventory	glossary	translation	10111		Existing
Glossary: mobile_shared, reports_gps_alerts, wap_inventory	glossary	translation	10114		Resource Inventory
Screen Configuration - Mobility: Edit/View activity	fae3e1febea180ba048eb3f1b0c011f029fd5e	layout	list_inventories	C2M OFSC	Equipment
Screen Configuration - Mobility: Edit/View activity	9bdc924764e5ac57bf15c4e166282c8a3189de	layout	list_inventories	WAM OFSC	Assets

Example: To change the **Asset** label, change the Asset in the given file. You can add more values to the existing values.

Forms and Plugins

Plugins are used to make changes to screen and data based on their type and status of target and parent object. They are also used to enter measurements, record time/materials/equipment used while completing an activity, populate service history information, install/replace/remove/attach/exchange of assets, viewing asset history, viewing asset attributes, using truck inventories and validate completion information before sending the information to verify if the message is accepted by Oracle Utilities Work and Asset Cloud Service.

Plug-ins in Oracle Field Service perform actions not found in the standard solution. They appear as selectable links on the application. They open a new window, tab, or frame in a browser where an external HTML5 application is executed.

For more information on Oracle Field Service plugin framework, refer to latest Oracle Field Service documentation at: <https://docs.oracle.com/en/cloud/saas/field-service/fapcf/c-aboutpluginapi.html#AboutThePlug-inAPI-10D597F8>

Each plugin contains a JavaScript file that has the main business logic required for functionality of the plugin. The data required for each plugin is available through the properties that are added for the plugin. XML data obtained through properties is parsed and appropriate XSL is applied to it to render each UI.

This section provides details about the following plugins in the integration:

- [Measurement Plugin](#)
- [Resource Usage Plugin](#)
- [Service History Plugin](#)
- [Validate Completion Plugin](#)
- [Planned Service History Plugin](#)

- [Asset Component Install Exchange Undo Plugin](#)
- [Lock Unlock Activity Plugin](#)
- [Pick Up Work Plugin](#)
- [Materials Plugin](#)
- [Asset Attribute Plugin](#)
- [Asset History Plugin](#)
- [View In Map](#)

Measurement Plugin

Measurements manage the asset operational and runtime data collected and tracked for assets. Asset measurements include mileage, hours of uptime, number of start-stops, and more.

Since they almost entirely depend on the usage of the related asset, readings cannot be calculated or predicted accurately by the system. Instead, readings must be collected and entered into the system, either manually by a user or imported as the result of activity completion.

Valid measurement types received from Oracle Utilities Work and Asset Cloud Service are assigned to the “wam_valid_measurement_types” property and are obtained in runtime as XML string and displayed in the plugin.

Measurement reason types (wam_measurement_meter_reason, wam_measurement_gauge_reason) are populated based on the measurement type selected.

To import plugins:

1. Login to Oracle Field Service with valid credentials.
2. Click the hamburger menu icon (icon with three horizontal lines) on the upper-left corner of the **Home** page.
3. Navigate to **Configuration > Displays > Forms and Plugins**.
4. From the **Import** drop-down list, select **Plugins**.
5. Click the **Drag and Drop** field to select measurement plugin. Click **Validate**.
Oracle Field Service validates the plugin and the number of valid items should be 1.
6. Click **Import**. Make sure the values in **Number of valid items** and **Number of not valid items** are ‘1’ and ‘0’ respectively.

After the successful import of the plugin, Oracle Field Service displays the details as shown below.

7. Make sure the **Available Properties** tab is populated with all properties.

Available Properties

Select values

Enable lock [enable_lock_plugin] ×

WAM Last Completed Activity [wam_last_completion_act] ×

Measurement Gauge Reason [wam_measurement_gauge_reason] ×

Work Order [appt_number] ×

Activity Status [astatus] × Activity ID [aid] ×

Date [date] ×

Activity Number [wam_work_activity_info] ×

Activity Description [wam_activity_desc] ×

Measurement Numeric Meter Reason [wam_measurement_meter_reason] ×

wam_lock_uname [wam_lock_uname] ×

wam_lock_uid [wam_lock_uid] ×

Construction work related [wam_construction_related] ×

Inventory Id [invid] × Activity Id [inv_aid] ×

Valid Measurement Types [wam_valid_measurement_types] ×

Measurements Ouput [wam_measurements_output] ×

Node Id [wam_node_id] ×

Asset Information [wam_asset_info] ×

Location Information [wam_asset_location_info] ×

Asset Id [wam_asset_id] ×

Resource Usage Plugin

Timesheets are used to record the amount of time that workers (labor resources) spend on activities or work orders. Once charges are entered, processing allows employees to receive proper compensation for their work and labor charges are applied to the appropriate cost buckets.

Generally, only each individual and the person designated as the supervisor on that individual's crew can access timesheet information for that person. Supervisor can enter individual timesheet for himself if the secure parameter "ofsc_sup_in_team" is set to 'true/yes'.

The user operations performed on this plugin page are shown for both Individual Crew and Supervisor.

The resource usage details that can include either the individual time sheet or crew time sheets by supervisor or equipment usage or other equipment usage to the Oracle Utilities OFSC WACS Resource Usage Details integration process deployed on Oracle Integration Cloud which further passes on the details to Oracle Utilities Work and Asset Cloud Service.


This plugin provides real-time visibility into labor and equipment use, supporting accurate cost tracking and improved resource planning across projects.

Artifacts	Value
Integration Process Used	Oracle Utilities OFSC WACS Resource Usage Details
OFSC REST URI	<p>To retrieve the information about specified resource. Method: GET URI: /rest/ofscCore/v1/resources/{resourceId}</p> <p>To retrieve activity properties for the specified activity. Method: GET URI: /rest/ofscCore/v1/activities/{activityId}</p> <p>To retrieves the details about the work skills assigned to the specified resource. Method: GET URI: /rest/ofscCore/v1/resources/{resourceId} / workSkills</p> <p>To retrieve the details of resource types. Method: GET URI: /rest/ofscMetadata/v1/resourceTypes</p>

Refer to the **Business Flow** section in the *Oracle Utilities Work and Asset Cloud Service Integration to Oracle Field Service Configuration Guide* for more information related to the integration processes included in this release. The documentation is available on Oracle Help Center at: [https:// docs.oracle.com/en/industries/energy-water/integrations-index.html](https://docs.oracle.com/en/industries/energy-water/integrations-index.html)

To import the plugin:

1. Repeat steps 1 to 5 from [Measurement Plugin](#).
2. Click the **Import** drop-down list and select **Plugins** to import the resource usage plugin provided in the package.



3. Select the resource plugin and enter the following details under the secure parameters:
 - **oic_url:** `https://OIC_host:OIC_port/ic/api/integration/v2/flows/rest/project/OUTL-BA-WACS_OFSC/OUTL-BA-OFSC_WACS_RES_USAGE_SEND/1.0/resourceUsage`
 - **oic_uname/oic_password:** OIC username/password

Oracle Field Service users should configure the following:

- **ofsc_uname:** clientID@instance ID
- **ofsc_password:** client secret key
- **ofsc_bucket:** External ID of bucket configured in your environment
- **ofsc_hostname:** [api_path]
Example: `https://<site address>.<domainName>`

- **ofsc_sup_in_team**: true/false or yes/no

Parameter Name	Edit	Delete
oic_url		
oic_username		
oic_password		
ofsc_username		
ofsc_password		
ofsc_bucket		
ofsc_hostname		
ofsc_sup_in_team		

Make sure the **Available Properties** tab is populated with properties as shown below.

Property Name	Property ID
Job Order	[XA_WORK_ORDER]
WAM Resource Usage Output	[wam_resource_usage_output]
Activity Number	[wam_work_activity_info]
Activity Description	[wam_activity_desc]
Craft	[wam_craft]
Resource Unit of Measure	[wam_resource_uom]
Labor Earning Type	[wam_labor_earning_type]
Overtime Type	[wam_overtime_type]
Other Resource Type	[wam_other_resource_type]
Crew Shift Type	[wam_crew_shift_type]
wam_lock_uid	[wam_lock_uid]
Resource Usage Flag	[wam_ru_comp_act_flag]
Timeout	[timeout]
Equipment Type	[wam_equipment_type]
wam activity duration	[wam_activity_length]
Time Slot	[time_slot]
Work Order	[appt_number]
Work Skill	[activity_workskills]
Duration	[length]
Start [ETA]	[astatus]
Activity ID [aid]	[end_time]
End	[date]
Traveling Time	[travel]
SLA Start	[sla_window_start]
SLA End	[sla_window_end]
Type [Resource type]	[pname]
External ID	[external_id]
Resource type	[ptype]

Note: For all plugins to which “ofsc_siteAddress” has to be configured under secure parameters, it is replaced with “ofsc_hostname”. While configuring secure parameters for plugins, please note that

“ofsc_siteAddress” parameter is removed and a new parameter “ofsc_hostname” is created.

Service History Plugin

Service history is information about some type of service or maintenance performed on an asset. Information typically associated with service history include record inspection feedback, pass/fail details, downtime, parts failure information, maintenance or service logs, or other information regarding service on the asset.


After a custom business object for a service history is added in Oracle Utilities Work and Asset Cloud Service, the information is available to the Service History plugin along with all other service histories as part of the “wam_asset_valid_service_history_types” property.

If the new business object belongs to one of the predefined service history categories of Questionnaire, Inspection, Failure, Downtime, and General, it is defined in the “wam_service_history_bo” property.

To capture the images or files related to an asset, the crew can use the attachment support functionality.

To import the plugin:

1. Repeat steps 1 to 5 from [Measurement Plugin](#).
2. Click the **Import** drop-down list and select **Plugins** to import the service history plugin provided in the package.

	Service History	ServiceHistoryTypes	Type: Hosted Plugin Name: ServiceHistoryTypes	16 Items Configured	...
---	-----------------	---------------------	--	---------------------	-----

3. Make sure the **Available Properties** tab is populated with the properties as shown below.

Planned Service History Output [wam_planned_service_history_output4]	×
Planned Service History Output [wam_planned_service_history_output5]	×
wam_lock_uname [wam_lock_uname]	×
wam_lock_uid [wam_lock_uid]	×
WAM Last Completed Activity [wam_last_completion_act]	×
wam_global_sh_attachmnt_count [wam_global_sh_attachmnt_count]	×
wam_global_psh_attachmnt_count [wam_global_psh_attachmnt_count]	×
WAM Attachment Count [wam_global_attachmnt_count]	×
Activity ID [aid]	×
Inventory Id [invid]	×
Activity Id [inv_aid]	×
Upload Attachment Output [wam_upload_attachment_output]	×
Node Id [wam_node_id]	×
Asset Information [wam_asset_info]	×
Asset - Valid Service History Types [wam_asset_valid_service_history_types]	×
Failure Information [wam_failure_info]	×
Location Information [wam_asset_location_info]	×
Asset Id [wam_asset_id]	×
Service History Output [wam_service_history_output1]	×

Upload Attachment 5 [wam_upload_attachment_5]	x
Upload Attachment 6 [wam_upload_attachment_6]	x
Upload Attachment 7 [wam_upload_attachment_7]	x
Upload Attachment 8 [wam_upload_attachment_8]	x
Upload Attachment 9 [wam_upload_attachment_9]	x
Upload Attachment 10 [wam_upload_attachment_10]	x
Upload Attachment 11 [wam_upload_attachment_11]	x
Upload Attachment 12 [wam_upload_attachment_12]	x
Upload Attachment 13 [wam_upload_attachment_13]	x
Upload Attachment 14 [wam_upload_attachment_14]	x
Upload Attachment 15 [wam_upload_attachment_15]	x
Attachment Count [wam_attachment_count]	x
Quantity Planned for the Activity [wam_cu_planned_qty]	x
Compatible Unit Information [wam_cu_info]	x
Construction Action [wam_construction_action]	x
WAM Compartment unit function [wam_cu_function]	x
Construction work related [wam_construction_related]	x
Inventory pool [invpool]	x
Inventory Type [invtype]	x
Compatible Unit Id [wam_cu_id]	x
WAM Description [wam_const_info]	x
asset Info [wam_cw_asset_info]	x
Deinstall Status [wam_deinstall_status]	x

Validate Completion Plugin

This plugin helps crew to validate the eligibility to the activity to complete. If the activity is not yet eligible, the plugin displays the corresponding error message. If the eligibility is a success, the crew navigates to the **End Activity** page to complete the activity.


The plugin validates to check if there are any pending service histories and if all the required service histories are completed.

If the validations are not successful, click **OK** and fix the issue. If the validations are successful, the completion message is written to a temporary file and navigated to the **End Activity** page. Click **Submit** to send the completion message to Oracle Utilities Work and Asset Cloud Service using the Oracle Utilities OFSC WACS Activity Complete flow.

Refer to the Business Flows section in the *Oracle Utilities Work and Asset Cloud Service Integration to Oracle Field Service Configuration Guide* for more information about the integration processes included in this release. The documentation is available on [Oracle Help Center](https://docs.oracle.com/en/industries/energy-water/integrations-index.html) at: [https:// docs.oracle.com/en/industries/energy-water/integrations-index.html](https://docs.oracle.com/en/industries/energy-water/integrations-index.html)

To import the plugin:


1. Repeat steps 1 to 5 from the [Measurement Plugin](#) section.
2. Click **Import Validate Completion Plugin** to import the validate completion plugin provided in the package.

	Validate Completion	validateCompletion	Type: Hosted Plugin Name: validateCompletion	18 Items Configured	...
---	---------------------	--------------------	---	---------------------	-----

3. Select the **Validate Completion** plugin and enter the following details in the secure parameters:
 - ofsc_uname: clientID@instance ID
 - ofsc_password: client secret key
 - ofsc_hostname: [api_path]
 - ofsc_multiDay_act_lbls : Activity Type of the Multi-Day activity created in Oracle Field Service. If there are more than one, use the '|' separator.

Example: Act1 | Act2 | Act3

Example: https://<site address>.<domainName>

ofsc_uname		
ofsc_password		
ofsc_hostname		
ofsc_multiDay_act_l...		

- Make sure that the **Available Properties** tab is populated with the properties as shown below.

Available Properties

Select values

Material Usage [wam_material_usage] ×

Enable lock [enable_lock_plugin] ×

Activity Type [aworktype] × Date [date] ×

wam_lock_uname [wam_lock_uname] ×

wam_lock_uid [wam_lock_uid] ×

WAM Resource Usage Output
[wam_resource_usage_output] ×

Work Order [appt_number] × Activity ID [aid] ×

Valid Service History Types
[wam_valid_service_history_types] ×

wam consolidated inventories
[wam_activity_consolidated_inventories] ×

validate flag [wam_validateCompletion_flag] ×

Planned Service History Output
[wam_planned_service_history_output1] ×

Planned Service History Output
[wam_planned_service_history_output2] ×

Planned Service History Output
[wam_planned_service_history_output3] ×

Planned Service History Output
[wam_planned_service_history_output4] ×

Planned Service History Output
[wam_planned_service_history_output5] ×

Pickup Type [wam_pickup_type] ×

WAM Last Completed Activity
[wam_last_completion_act] ×

Construction Work Activity
[wam_construction_activity] ×

WAM Material Last Completed Activity [wam_mat_last_completion_act]	×
Planned SH Count [wam_plnsh_attachment_count]	×
wam_global_psh_attachmnt_count [wam_global_psh_attachmnt_count]	×
Planned SH File 1 [wam_plsh_upload_attachment_1]	×
Planned SH File 2 [wam_plsh_upload_attachment_2]	×
Planned SH File Output 3 [wam_plsh_upload_attachment_3]	×
Planned SH File 4 [wam_plsh_upload_attachment_4]	×
Planned SH File 5 [wam_plsh_upload_attachment_5]	×
Planned SH File 6 [wam_plsh_upload_attachment_6]	×
Planned SH File 7 [wam_plsh_upload_attachment_7]	×
Planned SH File 8 [wam_plsh_upload_attachment_8]	×
Planned SH File 9 [wam_plsh_upload_attachment_9]	×
Planned SH File 10 [wam_plsh_upload_attachment_10]	×
Planned SH File 11 [wam_plsh_upload_attachment_11]	×
Planned SH File 12 [wam_plsh_upload_attachment_12]	×
Planned SH File 13 [wam_plsh_upload_attachment_13]	×
Planned SH File 14 [wam_plsh_upload_attachment_14]	×
Planned SH File 15 [wam_plsh_upload_attachment_15]	×
Serial number Control [wam_serial_num_control]	×
Asset number control [wam_asset_num_control]	×

Badge Number control [wam_badge_num_control]	x
Construction Action [wam_construction_action]	x
Construction work related [wam_construction_related]	x
Quantity Completed Prior to this Shift [wam_cu_completed_qty]	x
Badge Nu Updated [wam_badge_num_up]	x
Asset Number Updated [wam_asset_num_up]	x
Serial Number Updated [wam_serial_num_up]	x
Compatible Unit Id [wam_cu_id]	x
Selected Compartment Id [wam_selected_cu_id]	x
Construction Location Id [wam_cu_location_id]	x
Actual Quantity [wam_cu_actual_qty]	x
Quantity Completed in this Shift [wam_cu_segment_qty]	x
Previous Segment Quantity [wam_cu_segment_prev_qty]	x
Material StoreroomId [wam_material_storeroomId]	x
Inventory pool [invpool]	x
Inventory Id [invid]	x
Activity Id [inv_aid]	x
Measurements Ouput [wam_measurements_output]	x
Node Id [wam_node_id]	x
Asset - Valid Service History Types [wam_asset_valid_service_history_types]	x
Location Information [wam_asset_location_info]	x
Asset Id [wam_asset_id]	x
Service History Output [wam_service_history_output1]	x

Service History Output [wam_service_history_output2]	×
Service History Output [wam_service_history_output3]	×
Service History Output [wam_service_history_output4]	×
Service History Output [wam_service_history_output5]	×
Service History Output [wam_service_history_output6]	×
Service History Output [wam_service_history_output7]	×
Service History Output [wam_service_history_output8]	×
Service History Output [wam_service_history_output9]	×
Service History Output [wam_service_history_output10]	×
Service History Output [wam_service_history_output11]	×
Service History Output [wam_service_history_output12]	×
Service History Output [wam_service_history_output13]	×
Service History Output [wam_service_history_output14]	×
Service History Output [wam_service_history_output15]	×
Service History Output [wam_service_history_output16]	×
Service History Output [wam_service_history_output17]	×

Stock Item Detail Id
[wam_material_masterStockItemDetailId]

×

Inventory Type [invtype] ×

ID [pid] ×

Name [pname] ×

External ID [external_id] ×

Planned Service History Plugin

Planned Service History is information about the type of service or maintenance performed on an asset. Information typically associated with service history include record inspection feedback, pass/fail details, downtime, parts failure information, maintenance or service logs, or other information about services on the asset.

On top of the service history levels, there are 5 supported categories for service histories: Questionnaire, Inspection, Failure, Downtime, and General. Each service history type has a defined business object in Oracle Utilities Work and Asset Cloud Service. Additionally, customized service histories can also be created based on the requirements.

For Planned Service Histories, the crew can add service histories at **Activity Level** or at **All Applicable Assets**, if that particular service history type is not asset specific. To capture any images or files related to the asset/activity, the crew can use the attachment support functionality provided for planned service histories.

To import the plugin:

1. Repeat steps 1 to 5 from the [Measurement Plugin](#) section.
2. Click the **Import** drop-down list and select **Plugins** to import the Planned Service History plugin provided in the package.

	Planned Service History	plannedServiceHistoryTypes	Type: Hosted Plugin Name: plannedServiceHistoryTypes	14 Items Configured	...
--	-------------------------	----------------------------	---	---------------------	-----

3. Select the **Planned Service History** plugin and enter the following details in the secure parameters:

- ofsc_uname: clientID@instance ID
- ofsc_password: client secret key
- ofsc_hostname: [api_path]

Example: https://<site address>.<domainName>

ofsc_uname		
ofsc_password		
ofsc_hostname		

- Make sure the **Available Properties** tab is populated with the properties as shown below.

Available Properties

Select values

Enable lock [enable_lock_plugin] x
wam_plsh_upload_attachment_output [wam_plsh_upload_attachment_output] x
Planned SH File 1 [wam_plsh_upload_attachment_1] x
Planned SH File 2 [wam_plsh_upload_attachment_2] x
Planned SH File Output 3 [wam_plsh_upload_attachment_3] x
Planned SH File 4 [wam_plsh_upload_attachment_4] x
Planned SH File 5 [wam_plsh_upload_attachment_5] x
Planned SH Count [wam_plsh_attachment_count] x
Planned SH File 6 [wam_plsh_upload_attachment_6] x
Planned SH File 7 [wam_plsh_upload_attachment_7] x
Planned SH File 8 [wam_plsh_upload_attachment_8] x
Planned SH File 9 [wam_plsh_upload_attachment_9] x
Planned SH File 10 [wam_plsh_upload_attachment_10] x
Planned SH File 11 [wam_plsh_upload_attachment_11] x
Planned SH File 12 [wam_plsh_upload_attachment_12] x
Planned SH File 13 [wam_plsh_upload_attachment_13] x
Planned SH File 14 [wam_plsh_upload_attachment_14] x
Planned SH File 15 [wam_plsh_upload_attachment_15] x

WAM Last Completed Activity [wam_last_completion_act]	x
Construction Work Activity [wam_construction_activity]	x
wam_activity_asset_id [wam_activity_asset_id]	x
wam_global_sh_attachmnt_count [wam_global_sh_attachmnt_count]	x
wam_global_psh_attachmnt_count [wam_global_psh_attachmnt_count]	x
Inventory pool [invpool]	x
Activity Id [inv_aid]	x
Asset - Valid Service History Types [wam_asset_valid_service_history_types]	x
WAM Activity Id [wam_activity_id]	x
Construction Action [wam_construction_action]	x
Asset Id [wam_asset_id]	x
Asset Installed In OFSC [wam_asset_installed_in_ofsc]	x
Asset Information [wam_asset_info]	x
Location Information [wam_asset_location_info]	x
Item Number [ITEM_NUMBER]	x
Badge Number [wam_badge_number]	x
Material Id [wam_material_id]	x
Stock Code [wam_material_stockCode]	x
Deinstall Status [wam_deinstall_status]	x
Asset Action Taken [wam_asset_action_taken]	x
Upload Attachment 1 [wam_upload_attachment_1]	x

Asset Component Install Exchange Undo Plugin

Handle operations on Install, Uninstall, and Replace actions for the assets and components in a work activity. Information associated with the components used for the assets on completion of the activity is handled.

Oracle Field Service sends the required Asset Query details using Oracle Utilities OFSC WACS Asset Query to Oracle Utilities Work and Asset Cloud Service. Oracle Utilities Work and Asset Cloud Service responds with all the asset details if the call is successful, else it responds with an error message.

Operations that can be performed using this plugin:

- Install Asset
- Attach Component
- Replace Asset
- Replace Component
- Asset Removal
- Asset Out of Service
- Component Removal
- Undo Install
- Undo Remove
- Undo Attach
- Undo Replace
- Back to Service

Artifacts	Value
Integration Process Used	Oracle Utilities OFSC WACS Asset Query
OFSC REST URI	<p>To retrieve the information about specified Resource Method: GET URI: /rest/ofscCore/v1/resources/{resourceId}</p> <p>To retrieve the details of resource types. Method: GET URI: /rest/ofscMetadata/v1/resourceTypes</p>

Refer to the **Business Flows** section in the *Oracle Utilities Work and Asset Cloud Service Integration to Oracle Field Service Configuration Guide* for more information about the integration processes included in this release. The documentation is available on [Oracle Help Center](https://docs.oracle.com/en/industries/energy-water/integrations-index.html) at: <https:// docs.oracle.com/en/industries/energy-water/integrations-index.html>

To import the plugin:

1. Repeat steps 1 to 5 from the [Measurement Plugin](#) section.
2. Click the **Import** drop-down box and select **Plugins** to import the Asset Component Install Exchange Undo plugin provided in the package.

	Asset Component Install Exchan...	assetComponentInstallExchange...	Type: Hosted Plugin Name: assetComponentInstal	202 Items Configured	...
---	-----------------------------------	----------------------------------	---	----------------------	-----

3. Select the **Asset Component Install Exchange Undo** plugin and enter the details under the secure parameters:
 - **oic_url:** https://OIC_host:OIC_port/ic/api/integration/v2/flows/rest/project/OUTL-BA-WACS_OFSC/OUTL-BA-OFSC_WACS_ASSET_QUERY/1.0/assetQueryDetails
 - **oic_uname/oic_password:** OIC username/password
 - **ofsc_multiDay_act_lbls:** The Activity type of the Multi-Day activity created in OFSC. If there are more than one use '|' separator.
Example: Act1|Act2|Act3
 - **ofsc_uname:** OFSC username - clientID@instanceid (application should have access to all the apis)
 - **ofsc_password:** OFSC password: client secret key
 - **ofsc_hostname:** [api_path]
Example: https://<site address>.<domainName>
4. Make sure the **Available Properties** tab is populated with the properties as shown below.

Available Properties

Select values

Activity Type [aworktype] x

Work Order [appt_number] x Activity ID [ald] x

Activity Number [wam_work_activity_info] x

Activity Description [wam_activity_desc] x

Service History Types [wam_service_history_types1] x

Service History Types [wam_service_history_types2] x

Service History Types [wam_service_history_types3] x

Service History Types [wam_service_history_types4] x

Service History Types [wam_service_history_types5] x

Service History Types [wam_service_history_types6] x

Service History Types [wam_service_history_types7] x

Service History Types [wam_service_history_types8] x

Service History Types [wam_service_history_types9] x

Service History Types [wam_service_history_types10] x

Pickup Type [wam_pickup_type] x

wam_activity_asset_id [wam_activity_asset_id] x

Item Number [ITEM_NUMBER] x

Serial Number [Invsn] x

Inventory Type [Invtype] x Inventory Id [Invid] x

Activity Id [Inv_ald] x

Valid Measurement Types [wam_valid_measurement_types] x

Node Id [wam_node_id] x

Asset Information [wam_asset_info] x

Badge Number [wam_badge_number] x

Asset - Valid Service History Types [wam_asset_valid_service_history_types] x

Failure Information [wam_failure_info] x

Location Information [wam_asset_location_info] x

Asset Id [wam_asset_id] x

Asset Description [wam_asset_desc] x

Asset Type [wam_asset_type]	x
Building [wam_asset_location_building]	x
Room [wam_asset_location_room]	x
Site Location [wam_asset_location_siteLocation]	x
Point ID [wam_asset_location_pointId]	x
Service Area [wam_asset_location_serviceArea]	x
Asset Worked [wam_asset_worked]	x
Attached To Asset Id [wam_attached_to_asset_id]	x
Attached To Asset [wam_attached_to_asset_info]	x
Asset May Be Left In Place [wam_asset_maybeLeftInPlace]	x
Attach To Asset [wam_attach_to_asset_id]	x
Asset Installed In OFSC [wam_asset_installed_in_ofsc]	x
Asset Or Component [wam_asset_or_component]	x
Exchanged Inventory Id [wam_exchanged_inventory_id]	x
Deinstall Status [wam_deinstall_status]	x
Asset Sequence [wam_asset_seq]	x
Effective Date Time [wam_asset_effective_date_time]	x
Asset Action Taken [wam_asset_action_taken]	x
WAM Activity Id [wam_activity_id]	x
Inventory pool [invpool]	x
Is Asset Location [wam_is_asset_location]	x
Asset Attribute List [wam_asset_attribute_list]	x

Sequence Combination [wam_cu_seq_combination] x	
Action Completed in Activity [wam_action_comp_in_act]	x
Asset UDF1 [wam_asset_UDF1] x	
Asset Location UDF1 [wam_asset_location_UDF1] x	
Asset UDF2 [wam_asset_UDF2] x	
Asset UDF3 [wam_asset_UDF3] x	
Asset Location UDF2 [wam_asset_location_UDF2] x	
Asset Location UDF3 [wam_asset_location_UDF3] x	
Asset Location UDF4 [wam_asset_location_UDF4] x	
Asset UDF4 [wam_asset_UDF4] x	
Asset UDF5 [wam_asset_UDF5] x	
Asset UDF6 [wam_asset_UDF6] x	
Asset UDF7 [wam_asset_UDF7] x	
Asset UDF8 [wam_asset_UDF8] x	
Asset UDF9 [wam_asset_UDF9] x	
Asset UDF10 [wam_asset_UDF10] x	
Asset Location UDF5 [wam_asset_location_UDF5] x	
Asset Location UDF6 [wam_asset_location_UDF6] x	
Asset Location UDF7 [wam_asset_location_UDF7] x	
Asset Location UDF8 [wam_asset_location_UDF8] x	
Asset Location UDF9 [wam_asset_location_UDF9] x	
Asset Location UDF10 [wam_asset_location_UDF10] x	
Resource Id [inv_pid] x	Quantity [quantity] x
Stock Item Description	

Stock Item Description [wam_material_stockItemDetailInfo]	x
Material Id [wam_material_id]	x
Stock Item Detail Id [wam_material_stockItemDetailId]	x
Stock Code [wam_material_stockCode]	x
Stock Item Detail Id [wam_material_masterStockItemDetailId]	x
Lot Id [wam_material_lotId]	x
Stock Item Id [wam_material_stockItemId]	x
Material Is Component [wam_material_isComponent]	x
Stock Item Information [wam_material_stockItemInfo]	x
Material Unit of Measure [wam_material_uom]	x
Stock Item Category [wam_material_stockItemCategory]	x
Material StoreroomId [wam_material_storeroomId]	x
Material InvId [wam_material_invId]	x
Compatible Unit Information [wam_cu_info]	x
Location Info [wam_location_info]	x
Badge Number control [wam_badge_num_control]	x
Serial number Control [wam_serial_num_control]	x
Asset Number [wam_asset_num]	x
Asset number control [wam_asset_num_control]	x
serial number [wam_serial_number]	x
Construction Action [wam construction action]	x

Lock Unlock Activity Plugin

Handle the lock or unlocking operations of an activity for a crew to work on it.

Only on locking an activity the crew can start operations, such as asset install, replace, remove, adding timesheet, equipment, and other details. A crew member can lock the activity without starting it. Once the activity is locked by any crew, it can be unlocked by the member or from the dispatch console.

To enable/disable the Lock Unlock functionality, set the lock.functionality property in the WAMOFSC_ConfigProps lookup to “true” or “false” in Oracle Integration Cloud. When creating the work activity, if lock.functionality is set to “true”, crew can start the activity and perform operations only after locking the activity.


If it is set to “false”, the **Lock** button in Oracle Field Service is disabled. So, crew can perform all operations without locking the activity.

To import the plugin:

1. Repeat steps 1 to 5 from the [Measurement Plugin](#) section.
2. Click the **Import** drop-down box and select **Plugins** to import the Lock Unlock Activity Plugin provided in the package.



3. Make sure the **Available Properties** tab is populated with properties as shown below.



Pick Up Work Plugin

This plugin helps the crew to create work order and/or work request of types “Asset related” or “non-Asset related” from Oracle Field Service. It can be a follow up to an existing activity or a new work which is unrelated pickup.

Follow up work can include work orders and work requests. Field workers can create follow up work if the issue is related to the asset of an existing activity. Else, they can create new work.

To create a work order, field workers can use asset of an existing activity or query new asset using the **Oracle Utilities OFSC WACS Asset Query** process. After the asset details are retrieved, they can enter the necessary details related to work order and submit. The details are submitted to Oracle Utilities Work and Asset Cloud Service using the **Oracle Utilities OFSC WACS Work Order** process. After creating the follow up work order, a unique mobile activity ID is assigned to the new activity created and is sent to the Oracle Field Service dispatch console. If the inbound communication is complete,

the work order is created in Oracle Utilities Work and Asset Cloud Service/Oracle Utilities Work and Asset Management.

To create a work request, they can use the asset of an existing activity or query new asset using the **Oracle Utilities OFSC WACS Asset Query** process. This can be non-asset related too. After the asset details are retrieved, they can enter the necessary details related to work request and submit. The details are submitted to Oracle Utilities Work and Asset Cloud Service using the **Oracle Utilities OFSC WACS Work Request** process. If the inbound communication is complete, the work request is created in Oracle Utilities Work and Asset Cloud Service/Oracle Utilities Work and Asset Management.

Artifacts	Value
Integration Process Used	<ul style="list-style-type: none"> Oracle Utilities OFSC WACS Asset Query Oracle Utilities OFSC WACS Work Order Oracle Utilities OFSC WACS Work Request
OFSC BO/Operation	Activity/ Bulk Update Activity
OFSC REST URI	To create a new service request in OFS: <ul style="list-style-type: none"> Method: POST URI: /rest/ofscCore/v1/serviceRequests

Refer to the **Business Flows** section in the *Oracle Utilities Work and Asset Cloud Service Integration to Oracle Field Service Configuration Guide* for more information about the integration processes included in this release. The documentation is available on [Oracle Help Center](https://docs.oracle.com/en/industries/energy-water/integrations-index.html) at: [https:// docs.oracle.com/en/industries/energy-water/integrations-index.html](https://docs.oracle.com/en/industries/energy-water/integrations-index.html)

To import the plugin:



















- Repeat steps 1 to 5 from the [Measurement Plugin](#) section.

	Pick Up Work	pickUpWork	Type: Hosted Plugin Name: pickUpWork	115 Items Configured	...
---	--------------	------------	---	----------------------	-----

- Select the Pick Up Work plugin and enter the following details under the secure parameters:

- oic_url:** https://OIC_host:OIC_port/ic/api/integration/v2/flows/rest/project/OUTL-BA-WACS_OFSC/OUTL-BA-OFSC_WACS_ASSET_QUERY/1.0/assetQuery
- oic_url1:** https://OIC_host:OIC_port/ic/api/integration/v2/flows/rest/project/OUTL-BA-WACS_OFSC/OUTL-BA-OFSC_WACS_ASSET_QUERY/1.0/assetQueryDetailsPickup
- oic_username/oic_password:** OIC username/password
- ofsc_username:** clientID@instance ID
- ofsc_password:** client secret key
- ofsc_hostname:** [api_path]
Example: https://<site address>.<domainName>
- groupLabel:** OFSC group label


- **bucket_for_nonScheduled:** External ID of the bucket

ofsc_username	 
ofsc_password	 
ofsc_siteAddress	 
groupLabel	 
oic_url	 
oic_username	 
oic_password	 
oic_url1	 
bucket_for_nonS...	 

- **esri_mapLink:** Deep link URL to ArcGIS Field Maps
 - https://fieldmaps.arcgis.app/?itemID=<gis_map_id>&referenceContext=center¢er=

Note: Leave this parameter blank if you are not implementing the ESRI ArcGIS Field Maps integration to Oracle Field Service.

- To create a follow up work order request in Oracle Field Service, add values to the **Request Type** property in Oracle Field Service.
 - Navigate to **Configurations > Properties** and search for **Request Type**.
 - Edit the **Resource Type** property. In the **Values** section, click **Add**. In the **Service Request Type Name** field, enter “workRequest” and in the **Status** field, enter “Active”.

Properties							View ▾	Add new	Export	Import
							Total: 1			
<input type="checkbox"/>	ID ↕	Property name ↕	Property Label ↕	Type ↕	Entity ↕	GUI ↕	Actions			
<input type="checkbox"/>	549	Request type	srtype	field	Service request	combobox				

Add Service request type

☒ Active

Service request type label
workRequest

Name: English
Work Request

Name: French (European)
Work Request

Name: Portuguese (Brazil)
Work Request

Name: Greek
.....

Cancel Add

- Click the **Import** drop-down box and select **Plugins** to import the Pick Up Work Plugin provided in the package.

Available Properties

Select values

Ports [no_ports] x

Activity Number [wam_work_activity_info] x

wam_activity_latitude [wam_activity_latitude] x

wam_activity_longitude [wam_activity_longitude] x

Pickup Work Class Description [wam_pickup_work_classDesc] x

Pickup Emergency [wam_pickup_emergency] x

Pickup Work It [wam_pickup_work_it] x

Pickup Type [wam_pickup_type] x

Pickup Location Type [wam_pickup_location_type] x

Activity Type To PSH [wam_actType_psh] x

Timeout [timeout] x Activity Type [aworktype] x

Work Order [appt_number] x Activity ID [aid] x

Work Order Description [wam_work_order_desc] x

Activity Description [wam_activity_desc] x

Activity Long Description [wam_activity_long_desc] x

Activity Location Information [wam_activity_location_info] x

Required By Date [wam_required_by_date] x

Activity Type Description [wam_activity_type_desc] x

Valid Service History Types [wam_valid_service_history_types] x

Service History Types [wam_service_history_types] x

Service History Types [wam_service_history_types2] x

Service History Types [wam_service_history_types3]	x
Service History Types [wam_service_history_types4]	x
Service History Types [wam_service_history_types5]	x
Service History Types [wam_service_history_types6]	x
Service History Types [wam_service_history_types7]	x
Service History Types [wam_service_history_types8]	x
Service History Types [wam_service_history_types9]	x
Service History Types [wam_service_history_types10]	x
Pickup work class [wam_work_class]	x
Pickup Work Category [wam_work_category]	x
Pickup Related Appointment Number [wam_pickup_related_appt_number]	x
Pickup Asset Node Id [wam_pickup_asset_node_id]	x
Pickup Asset Id [wam_pickup_asset_id]	x
Pickup Asset Details [wam_pickup_asset_details]	x
Pickup Related Work Order Description [wam_pickup_related_work_order_desc]	x
Pickup Related Activity Information [wam_pickup_related_activity_info]	x
Pickup Related Location Information [wam_pickup_related_location_info]	x
Pickup Guid [wam_pickup_guid]	x
Pickup Downtime Date Time [wam_pickup_downtimeDateTime]	x
Pickup Work Priority [wam_work_priority]	x
Pickup Work Type [wam_work_type]	x

Is Asset Location [wam_is_asset_location] x	
Run To Failure [wam_asset_location_runToFailure] x	
Item Number [ITEM_NUMBER] x	
Serial Number [invsn] x	Inventory pool [invpool] x
Inventory Type [invtype] x	Inventory Id [invid] x
Activity Id [inv_aid] x	
Valid Measurement Types [wam_valid_measurement_types] x	
Node Id [wam_node_id] x	
Asset Information [wam_asset_info] x	
Badge Number [wam_badge_number] x	
Asset - Valid Service History Types [wam_asset_valid_service_history_types] x	
Failure Information [wam_failure_info] x	
Location Information [wam_asset_location_info] x	
Asset Id [wam_asset_id] x	
Asset Description [wam_asset_desc] x	
Asset Type [wam_asset_type] x	
Building [wam_asset_location_building] x	
Room [wam_asset_location_room] x	
Site Location [wam_asset_location_siteLocation] x	
Point ID [wam_asset_location_pointId] x	
Service Area [wam_asset_location_serviceArea] x	
Asset Worked [wam_asset_worked] x	
Attached To Asset Id [wam_attached_to_asset_id] x	

Attached To Asset [wam_attached_to_asset_info] x
Asset May Be Left In Place [wam_asset_maybeLeftInPlace] x
Attached To Asset [wam_attached_to_asset] x
Attach To Asset [wam_attach_to_asset_id] x
Asset Installed In OFSC [wam_asset_installed_in_ofsc] x
Asset Or Component [wam_asset_or_component] x
Asset Sequence [wam_asset_seq] x
Effective Date Time [wam_asset_effective_date_time] x
Asset Action Taken [wam_asset_action_taken] x
Asset Attribute List [wam_asset_attribute_list] x
Construction work related [wam_construction_related] x
ID [pid] x External ID [external_id] x

Materials Plugin

This plugin handles the operations related to mobile storerooms in Oracle Field Service including reporting the use of materials. The operations include Use/Undo Use Item, Install/Undo Install Asset, and Attach/Undo Attach component from truck inventories. Oracle Field Service can request an update of a mobile storeroom passing date/time of the last snapshot.

Also, field workers can perform truck storeroom synchronization that will update the inventory details of respective truck using the Oracle Utilities OFSC WACS Storeroom Sync process.

Additionally, the refresh activity operation can be performed by sending the activity details to Oracle Utilities OFSC WACS Activity Pull Update which fetches the latest activity information from Oracle Utilities Work and Asset Cloud Service.

Artifacts	Value
Integration Process Used	<ul style="list-style-type: none"> Oracle Utilities OFSC WACS Asset Query Oracle Utilities OFSC WACS Storeroom Sync Oracle Utilities OFSC WACS Activity Pull Update

Artifacts	Value
OFSC REST URI	To retrieve information about specified resource: <ul style="list-style-type: none"> Method: GET URI: /rest/ofscCore/v1/resources/{resourceId}

Refer to the **Business Flows** section in the *Oracle Utilities Work and Asset Cloud Service Integration to Oracle Field Service Configuration Guide* for more information about the integration processes included in this release. The documentation is available on [Oracle Help Center](https://docs.oracle.com/en/industries/energy-water/integrations-index.html) at: [https:// docs.oracle.com/en/industries/energy-water/integrations-index.html](https://docs.oracle.com/en/industries/energy-water/integrations-index.html)

To import the plugin:

1. Repeat steps 1 to 5 from the [Measurement Plugin](#) section.
2. After the successful import of plugin, Oracle Field Service displays the details as shown below.



3. Select the Materials plugin and enter the details for the following secure parameters:

- **oic_storeroom_sync_url:** https://OIC_host:OIC_port/ic/api/integration/v2/flows/rest/project/OUTL-BA-WACS_OFSC/OUTL-BA-OFSC_WACS_STOREROOM_SYNC/1.0/syncStoreroom
- **oic_uname/oic_password:** OIC username/password
- **oic_assetQueryDetails_url:** https://OIC_host:OIC_port/ic/api/integration/v2/flows/rest/project/OUTL-BA-WACS_OFSC/OUTL-BA-OFSC_WACS_ASSET_QUERY/1.0/assetQueryDetails
- **oic_activityUpdate_url:** https://OIC_host:OIC_port/ic/api/integration/v2/flows/rest/project/OUTL-BA-WACS_OFSC/OUTL-BA-OFSC_WACS_ACTV_UPDT_PULL/1.0/retrieveUpdates

Oracle Field Service users should configure the following:

- ofsc_uname: clientID@instance ID
- ofsc_password: client secret key
- ofsc_hostname: [api_path]

Example: `https://<site address>.<domainName>`

Plugin parameters	
Duplicate names are not allowed. Overall size should not exceed 5 KB.	
oic_storeroom_sy...	
oic_uname	
oic_password	
ofsc_uname	
ofsc_password	
ofsc_hostname	
oic_assetQueryD...	
oic_activityUpdat...	

4. Make sure the **Available Properties** tab is populated with all required properties.

Available Properties

Select values

WAM Last Completed Activity

x

[wam_last_completion_act]

Work Order [appt_number] x

Activity ID [aid] x

Activity Number [wam_work_activity_info] x

Activity Description [wam_activity_desc] x

Service History Types [wam_service_history_types1] x

Service History Types [wam_service_history_types2] x

Service History Types [wam_service_history_types3] x

Service History Types [wam_service_history_types4] x

Service History Types [wam_service_history_types5] x

Service History Types [wam_service_history_types6] x

Service History Types [wam_service_history_types7] x

Service History Types [wam_service_history_types8] x

Service History Types [wam_service_history_types9] x

Service History Types [wam_service_history_types10] x

Activity Node Id [wam_activity_node_id] x

Construction Work Activity [wam_construction_activity] x	
WAM Material Last Completed Activity [wam_mat_last_completion_act] x	
Serial Number [invsn] x	Inventory pool [invpool] x
Inventory Type [invtype] x	Inventory Id [invid] x
Activity Id [inv_aid] x	Resource Id [inv_pid] x
Changed Inventory Id [inv_change_invid] x	
Quantity [quantity] x	
Valid Measurement Types [wam_valid_measurement_types] x	
Measurements Output [wam_measurements_output] x	
Node Id [wam_node_id] x	
Asset Information [wam_asset_info] x	
Badge Number [wam_badge_number] x	
Asset - Valid Service History Types [wam_asset_valid_service_history_types] x	
Failure Information [wam_failure_info] x	
Location Information [wam_asset_location_info] x	

Asset Id [wam_asset_id]	x
Asset Description [wam_asset_desc]	x
Asset Type [wam_asset_type]	x
Building [wam_asset_location_building]	x
Room [wam_asset_location_room]	x
Site Location [wam_asset_location_siteLocation]	x
Point ID [wam_asset_location_pointId]	x
Service Area [wam_asset_location_serviceArea]	x
Asset Worked [wam_asset_worked]	x
Attached To Asset Id [wam_attached_to_asset_id]	x
Attached To Asset [wam_attached_to_asset_info]	x
Asset May Be Left In Place [wam_asset_maybeLeftInPlace]	x
Attached To Asset [wam_attached_to_asset]	x
Attach To Asset [wam_attach_to_asset_id]	x
Asset Installed In OFSC [wam_asset_installed_in_ofsc]	x
Asset Or Component [wam_asset_or_component]	x

Exchanged Inventory Id [wam_exchanged_inventory_id]	x
Deinstall Status [wam_deinstall_status]	x
Asset Sequence [wam_asset_seq]	x
Effective Date Time [wam_asset_effective_date_time]	x
Asset Action Taken [wam_asset_action_taken]	x
WAM Activity Id [wam_activity_id]	x
Attachment Count [wam_attachment_count]	x
Is Asset Location [wam_is_asset_location]	x
Other Assets [wam_other_assets]	x
Stock Item Description [wam_material_stockItemDetailInfo]	x
Material Id [wam_material_id]	x
Stock Item Detail Id [wam_material_stockItemDetailId]	x
Stock Code [wam_material_stockCode]	x
Stock Item Detail Id [wam_material_masterStockItemDetailId]	x
Lot Id [wam_material_lotId]	x

Stock Item Id [wam_material_stockItemId] x	
Material Is Component [wam_material_isComponent]	x
Stock Item Information [wam_material_stockItemInfo]	x
Material Unit of Measure [wam_material_uom] x	
Stock Item Category [wam_material_stockItemCategory]	x
Material StoreroomId [wam_material_storeroomId] x	
Material InvId [wam_material_invId] x	
Run To Failure [wam_asset_location_runToFailure] x	
Segment aid [wam_segment_aid] x	
Compatible Unit Information [wam_cu_info] x	
Construction Action [wam_construction_action] x	
Compatable Unit Id [wam_cu_id] x	
Selected Compartment Id [wam_selected_cu_id] x	
Construction Location Id [wam_cu_location_id] x	
Sequence Combination [wam_cu_seq_combination] x	
WAM Description [wam_const_info] x	

Asset Attribute List [wam_asset_attribute_list] x	
Action Completed in Activity [wam_action_comp_in_act]	x
Item Current Quantity in Segment [wam_item_curr_qty]	x
Construction work related [wam_construction_related]	x
Type [Resource type] x	ID [pid] x
Name [pname] x	External ID [external_id] x
Status [pactive] x	Resource type [ptype] x
Resource Source [wam_resource_source] x	
Resource Last Update DateTime [wam_resource_lastUpdateDttm]	x

Asset Attribute Plugin

This plugin displays the asset attribute list of an asset in Oracle Field Service. The asset can be in existing, installed, or de-installed pool. Asset attributes are characteristics that are recorded for an asset. Only characteristic types with an adhoc and predefined value types can be used as asset attributes. Each asset type records which characteristic types can be used for asset attributes for assets of that types.

When an asset is created, the process asset attribute details are sent from Oracle Utilities Work and Asset Cloud Service to Oracle Field Service as part of asset details in the asset location asset list, issued asset list, and installed asset list. Asset attribute details related to each asset are assigned to the “wam_asset_attribute_list” property and are obtained in runtime as XML string. The enumeration properties include “wam_map_validValue_description”, “wam_map_assetAttribute”, “wam_map_attribute_validValue” are used to transform and display the details.

A mobile user can view or edit the list of valid asset attributes of an asset using this plugin in Oracle Field Service. The asset attribute values are optional in Oracle Utilities Work and Asset Cloud Service. An empty value is displayed in Oracle Field Service for asset attributes with no values.

To import the plugin:

1. Repeat steps 1 to 5 from the [Measurement Plugin](#) section.

- Click the **Import** drop-down list and select **Plugins** to import the **Asset Attribute** plugin provided in the package.



- Select the Asset Attributes plugin and configure the following secure parameters:
 - ofsc_uname:** clientID@instance ID
 - ofsc_password:** client secret key
 - ofsc_hostname:** [api_path]
Example: https://<site address>.<domainName>
 - ofsc_multiDay_act_ibls:** Activity Type of the Multi-Day activity created in Oracle Field Service. If there are more than one, use the '|' separator.
Example: Act1|Act2|Act3

- Make sure the **Available Properties** tab is populated with all required properties.

Available Properties

Select values

Activity Type [aworktype] × Activity ID [aid] ×

wam_lock_uname [wam_lock_uname] ×

wam_lock_uid [wam_lock_uid] ×

Installed Assets [wam_installed_assets3] ×

Installed Assets [wam_installed_assets4] ×

Installed Assets [wam_installed_assets5] ×

Installed Assets [wam_installed_assets7] ×

Installed Assets [wam_installed_assets8] ×

Installed Assets [wam_installed_assets9] ×

Installed Assets [wam_installed_assets10] ×

Installed Assets [wam_installed_assets1] ×

Installed Assets [wam_installed_assets2] ×

Installed Assets [wam_installed_assets6] ×

Activity Status [astatus] ×

Asset Attribute List [wam_asset_attribute_list] ×

Inventory Id [invid] × Activity Id [inv_aid] ×

WAM Map Valid Values Description [wam_map_validValue_description] ×

WAM Map Asset Attribute List [wam_map_assetAttribute] ×

WAM Map Attribute ValidValue [wam_map_attribute_validValue] ×

Asset Information [wam_asset_info] ×

Inventory Type [invtype] ×

Asset Action Taken [wam_asset_action_taken] ×

Asset Id [wam_asset_id] ×

Inventory pool [invpool] × Resource Id [inv_pid] ×

Quantity [quantity] × ID [pid] ×

Asset History Plugin

This plugin displays additional details (past activity histories, measurements, and service histories) of an asset in Oracle Field Service. All these details are presented in a clear, organized table format. Field workers can filter this section to quickly narrow down the data based on specific criteria. The asset history details are displayed regardless of whether the asset is in the Existing group, Installed group, Deinstalled group, or was Issued. However, the **Asset History** button will not be visible for the asset present in the truck. This ensures field workers are informed about what has been done on the asset previously for better decision-making and asset management.

Enumeration properties “wam_service_history_category”, “wam_measurement_status” and “wam_activity_status” are used to transform and display descriptions for Service History Category, Measurement Status, and Activity Status codes that are received from Oracle Utilities Work and Asset Cloud Service.


On opening this plugin, Oracle Field Service sends only the Asset ID to the **Oracle Utilities OFSC WACS Asset Query** process. The response received from this process is transformed and represented in tabular format.

Artifacts	Value
Integration Process Used	Oracle Utilities OFSC WACS Asset Query

Refer to the **Business Flows** section in the *Oracle Utilities Work and Asset Cloud Service Integration to Oracle Field Service Configuration Guide* for more information about the integration processes included in this release. The documentation is available on [Oracle Help Center](https://docs.oracle.com/en/industries/energy-water/integrations-index.html) at: [https:// docs.oracle.com/en/industries/energy-water/integrations-index.html](https://docs.oracle.com/en/industries/energy-water/integrations-index.html)

To import the plugin:

1. Repeat steps 1 to 5 from the [Measurement Plugin](#) section.
2. From the **Import** drop-down list, select **Plugins** to import the Asset History plugin included in the package.



3. Select the Asset History plugin and enter the details for the following secure parameters:
 - **oic_url:** `https://OIC_host:OIC_port/ic/api/ integration /v2/flows/rest/project/OUTL-BA-WACS_OFSC/OUTL-BA-OFSC_WACS_ASSET_QUERY/1.0/assetQueryDetailsHistory`
 - **oic_uname:** OIC username
 - **oic_password:** OIC password

4. Make sure the **Available Properties** tab is populated with all required properties.

Available Properties

Select values

- WAM Activity Status [wam_activity_status] ×
- Measurement Status [wam_measurement_status] ×
- Service History Category [wam_service_history_category] ×
- Service Class [wam_service_class] ×
- Activity Type [aworktype] ×
- Asset Id [wam_asset_id] ×
- Valid Measurement Types [wam_valid_measurement_types] ×
- Asset Information [wam_asset_info] ×

View In Map

This is an external application type plugin and accessed as a web page in a new window or the same window in Oracle Field Service. The plugin is used to navigate to ArcGIS Field Maps from Oracle Field Service through deep link URL.

Note: Please configure this plugin only when you want to implement the ArcGIS Field Maps integration with Oracle Field Service along with the Oracle Utilities Work and Asset Cloud Service integration to Oracle Field Service.

1. Import the plugin into the Oracle Field Service environment.
2. Configure the map URL in the **Launch application URL** field both in Android and iOS.

Make sure the URL is in the following format:

```
https://fieldmaps.arcgis.app/
?itemID=<gis_map_id>dd&referenceContext=center&center={wam_activity_latitude},{wam_activity_longitude}
```

User Types

The user types are used to manage permissions for all the users. Each user type has a profile that defines security and display permissions, such as the user's login method, the ability to use certain functions, and access to menu items and properties. Screen-

configuration settings define the screens, windows, pop-up windows and other elements visible to a certain user type. They also support the context layout editor, in which the content, arrangement, and visibilities of each context are set.

Use the user types to create custom screen context layouts for Oracle Work and Asset Cloud Service integration to Oracle Field Service for utilities by accessing the screen configuration settings in specific user types created.

The user types that are part of this integration are:

- WACS_OFSC_Dispatcher_User_Type
- WACS_OFSC_User_Type

To set up the user types:

Important! Make sure to load the Properties, Activity Types, and Plugins before proceeding.

1. Login to Oracle Field Service.
2. Click the three line menu icon on the upper-left corner of the **Home** page.
3. Navigate to **Configuration** page > **Users, Security, Integrations** > **User Types**.
4. Click **Import** to import the user types.
5. On the **Choose file** field, click **Browse** to select “WACS_OFSC_User_Type”.
6. Click **Import** and verify the import is successful. Make sure that there are no “Imported with warnings” and “Not Imported” messages.
7. Click **Import** and select “WACS_OFSC_Dispatcher_User_Type”. Make sure that there are no “Imported with warnings” and “Not Imported” messages.

After the Dispatcher user type is set up, perform the following:

1. Make sure the Dispatcher user type import is successful without warnings.
2. Navigate to resources search for admin user. Note the user type configured in your environment.
3. Navigate to **Configuration** > **User, Security, Integrations** > **User types** > **WAM OFSC Dispatch Administrator**.
4. On the **General** tab, configure the display profile as “WAM OFSC Dispatch Administrator” and the profile that was configured to admin user.
5. Navigate to **Resources search** for admin and click **Edit**.
6. Set the user type as “WAM OFSC Dispatch Administrator”.
7. Enter the password and click **Submit**.

Make sure that the **Access** settings are selected for both the user types.

General		Screen configuration	Restrictions and Filters
User type info			
* Label	WAM OFSC		
* Name	WAM OFSC		
Active	<input checked="" type="checkbox"/>		
Login Policy	Default policy		
		Access settings	
		<input checked="" type="checkbox"/> Allow access via web application	
		<input checked="" type="checkbox"/> Allow access via installed application for Android	
		<input checked="" type="checkbox"/> Allow access via installed application for iOS	
		Permissions	
		<input checked="" type="checkbox"/> Manage	

General		Screen configuration	Restrictions and Filters
User type info		Access settings	
* Label	wam_ofsc_dispatch_administrator	<input checked="" type="checkbox"/> Allow access via web application	
* Name	WAM OFSC Dispatch Administrator	<input checked="" type="checkbox"/> Allow access via installed application for Android	
Active	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/> Allow access via installed application for iOS	
Login Policy	Default policy	Permissions	
		<input checked="" type="checkbox"/> Maps	

Chapter 3

Additional OFS Configurations

This chapter elaborates on the additional configuration of organization, work zones, outbound channel and UI validations in user types. It includes the following:

- [Sync Mobile Control Data Information from WACS to OFS](#)
- [Organization](#)
- [Work Zones](#)
- [Resource and Bucket Info](#)
- [Applications](#)
- [Configuring the Crew](#)
- [Offline vs Online Mode](#)
- [Crew Time](#)
- [Inventory Types](#)
- [Activity Links](#)
- [Timesheet/ Other Direct Charges Flag](#)
- [Timeout Seconds](#)
- [Checklist](#)

Sync Mobile Control Data Information from WACS to OFS

Information from Oracle Utilities Work and Asset Cloud Service must be replicated to Oracle Field Service to provide the drop-down information used in the Oracle Field Service mobile application. Create work skills, work skill properties, and work skill conditions in Oracle Field Service to match activities with resources and for crew tracking.

As part of this accelerator, Oracle Utilities WACS OFS Admin Data Sync integration flow deployed on Oracle Integration Cloud (OIC) is provided to create these configurations automatically making migration of data easier and get rid of tedious manual work.

Oracle Utilities WACS OFS Admin Data Sync needs to be run on initial installation or on a need to basis when new control data from Oracle Utilities Work and Asset Cloud Service or work skill related configurations needs to be created or updated in Oracle Field Service.

This sync integration process is manually run in Oracle Integration Cloud by scheduling the integration process to run on a scheduled date or selecting **Submit Now** from the menu of the activated sync integration process to initiate an instance of the integration. An optional language parameter can be entered, it should be an ISO 2 letter language code, to determine the description to retrieve from Oracle Utilities Work and Asset Cloud Service and in what language code the property name should be created in Oracle Field Service. If the language is not populated or blank, it is defaulted to English (en).

Refer to the **Business Flows** chapter in *Oracle Utilities Work and Asset Cloud Service Integration to Oracle Field Service Configuration Guide* included in this release. The documentation is available on Oracle Help Center at <https://docs.oracle.com/en/industries/utilities/integrations-index.html>.

The following configurations are created or updated by the Sync Process:

- Create or update the enumeration values for the Oracle Field Service properties.

OFSC Property Label	Synchronized WACS Information
wam_craft	Craft
wam_crew_shift_type	Crew Shift Type
wam_downtime_reason	Downtime Reason
wam_equipment_type	Equipment Type
wam_labor_earning_type	Labor Earning Type
wam_measurement_gauge_reason	Measurement Gauge Reason
wam_measurement_meter_reason	Measurement Meter Reason
wam_other_resource_type	Other Resource Type
wam_overtime_type	Overtime Type
wam_resource_uom	Unit of Measure-Resource
wam_material_uom	Material Unit of Measure
wam_material_stockitemCategory	Stock Item Category

OFSC Property Label	Synchronized WACS Information
wam_pickup_location_type	Pickup Location Type
wam_work_priority	Pickup Work Priority
wam_work_type	Pickup Work Type
wam_work_category	Pickup Work Category
wam_work_class	Pickup work class
wam_actType_psh	Activity Type To PSH
wam_map_assetAttribute	Asset Attributes
wam_map_attribute_validValue	Asset Attributes Valid Values
wam_map_validValue_description	Asset Attributes Valid Value Description
wam_service_history_category	Service History Category Description
wam_service_class	Service Class Description

To verify the information that is synchronized from Oracle Utilities Work and Asset Cloud Service to Oracle Field Service, navigate to the respective property and check the enumeration values. Click **Modify**.

Note: After a resource is created in Oracle Utilities Work and Asset Cloud Service, the resource code (craft code, equipment code and other resource code) cannot be changed. The sync integration process uses these resource codes to create the enumeration values for equipment type, craft and other resource type property in Oracle Field Service. Slash (/) should not be included in the resource.

The sync integration process cannot delete enumeration values added to a property in Oracle Field Service; the OFSC REST API that updates the enumeration values of a property does not allow it. One can delete an enumeration value(s) in a property by deleting the property itself, recreate the property and run the sync to get the latest values. Another alternative is to manually delete the unwanted enumeration values from the Oracle Field Service properties.

Following are the work skill related configurations:

1. A work skill is created in Oracle Field Service for each craft synchronized from Oracle Utilities Work and Asset Cloud Service. Work skill is a job-specific skill and is used as a criteria to match activities with the resources. The label format for work skill created in Oracle Field Service is:

W_ + WACS craftcode

Example: Work Skill created in Oracle Field Service

Edit work skill: "Carpenter"

Name

EnglishCarpenter

SpanishLA

French (European)

Portuguese (Brazil)

Chinese (Traditional)

Label

W_Carpenter

Sharing of the skill in teamwork

Summary

Active

☒

2. A work skill property on the activity level is created in Oracle Field Service for each craft synced from Oracle Utilities Work and Asset Cloud Service. This property will contain information about how many people with the particular work skill is needed for the activity. The label format for Work Skill property created in Oracle Field Service is:

W_ + WAM craftcode + _Nd

Example: Work skill property created in Oracle Field Service

Modify Property

General settings

Entity

Activity

Label

W_Carpenter_Nd

Name: English

Carpenter needed

Name: French (European)

Name: Portuguese (Brazil)

Name: SpanishLA

Name: Chinese (Traditional)

Type and advanced settings

Property type

String

Out

Text element

Regular expression

Line count

1

Clone property data on Reopen or Prework

☐

Formatting

If formatting is applied, the properties become read-only

☐

Regular Expression for XSLT Transformation

XSLT Transformation

Property hint

Hint: English

Hint: French (European)

Hint: Portuguese (Brazil)

Hint: SpanishLA

Hint: Chinese (Traditional)

- Work skill conditions are created in Oracle Field Service based on the craft and the configuration property value of `workSkillCond.actvtySameSkillMaxWorker.default` obtained from the `WAMOFSC_ConfigProps` lookup defined in Oracle Integration Cloud. This configuration property value contains the maximum number of people with the same work skill allowed to work simultaneously in an activity.

In this example: For work skill = Carpenter and `workSkillCond.actvtySameSkillMaxWorker.default = 3`, these are the work skill conditions created.

Example: Work skill conditions created for Work Skill Carpenter in Oracle Field Service.

Work skill conditions					View	Add New
<input type="checkbox"/>	ID	Name	Status	Work skill conditions	Actions	
<input type="checkbox"/>	34416	Carpenter(1/1)	✓	Carpenter needed in 1	Modify	
<input type="checkbox"/>	34417	Carpenter(2/2)	✓	Carpenter needed in 2	Modify	
<input type="checkbox"/>	34418	Carpenter(3/3)	✓	Carpenter needed in 3	Modify	

These configurations are used to track teams (crews) consisting of people with different work skills and make sure that activities that require several people simultaneously is assigned to the right team.

- If the `resourceTypes.default` and `createEquipmentWorkSkills.flag` properties in `WAMOFSC_ConfigProps` lookup are set to 'yes', for each equipment synchronized from Oracle Utilities Work and Asset Cloud Service work skills, work skill properties and work skill conditions are created in Oracle Field Service.

The label format for work skills created from equipment is:

WE_ + WACS equipmentcode

Example: Work skill created in Oracle Field Service

Edit work skill: "Bolt Machine" ✕

* Name

* English

Bolt Machine

SpanishLA

French (European)

Portuguese (Brazil)

Chinese (Traditional)

* Label

WE_Bolt Machine

Sharing of the skill in teamwork

Summary

Active

☒

Close

Save

- A work skill property on the activity level is created in Oracle Field Service for each equipment synced from Oracle Utilities Work and Asset Cloud Service. This property will contain information about how many people with the particular work

skill is needed for the activity. The label format for work skill property created in Oracle Field Service is:

WE_ + WAM equipmentcode + **_Nd**

Example: Work Skill Property created in Oracle Field Service.

The screenshot shows the configuration interface for a work skill property in Oracle Field Service. It is divided into two main sections: **General settings** and **Type and advanced settings**.

General settings:

- Entity:** Activity
- Label:** WE_Bolt Machine_Nd
- Name (English):** Bolt Machine needed
- Name (French (European)):**
- Name (Portuguese (Brazil)):**
- Name (SpanishLA):**
- Name (Chinese (Traditional)):**
- Property hint:**
 - Hint (English)
 - Hint (French (European))
 - Hint (Portuguese (Brazil))
 - Hint (SpanishLA)
 - Hint (Chinese (Traditional))

Type and advanced settings:

- Property type:** String
- GUI:** Text element
- Regular expression:**
- Lines count:** 1
- ☐ Clone property data on Reopen or Prework
- Formatting:**
 - If formatting is applied, the properties become read-only: ☐
 - Regular Expression for XSLT Transformation:**
 - XSLT Transformation:**

At the bottom right, there are **Cancel** and **Update** buttons.

- Work skill conditions are created in Oracle Field Service based on the equipment and the configuration property value “workSkillCond.actvtyMaxEquipment.default” obtained from the WAMOFSC_ConfigProps lookup defined in Oracle Integration Cloud. This configuration property value contains the maximum number of people with the same work skill allowed to work simultaneously in an activity.

In this example: For work skill = Bolt Machine,
workSkillCond.actvtySameSkillMaxWorker.default = 3, these are the work skill conditions created.

Example: Work Skill Conditions created for Work Skill Bolt Machine in Oracle Field Service

These configurations are used to track teams (crews) consisting of people with different work skills. Make sure that the activities that require several people simultaneously are assigned to the right team.

7. If Property assetAttributes.default in WAMOFSC_ConfigProps Lookup is set to “yes”, it populates the enum values for asset attributes characteristics types and its valid values in Oracle Field Service.

Organization

An organization can have buckets, organization units (Org Units), field resources, tools or vehicle associations. Create an organization before adding any type of resource.

To create an organization:

1. Navigate to **Configuration > Users, Security, Integrations > Organization**.
2. Click **Add New** to add a new organization.
3. Enter the name of the organization and click **Submit** to save the details.

Work Zones

Work zones are used to divide area in different zones for better scheduling of crews. Use the work zone keys to provide the Activity Service Area to facilitate the division through the Service Point information that comes from Oracle Utilities Work and Asset Cloud Service.

To add a work zone:

1. Navigate to **Configuration > General > Work Zones**.
2. Make sure the **Work Zone Key** displayed (top left corner) is “Activity Service Area”.

Work Zones						
View ▼ Travel Areas Export Import Add new						
Work Zone Key: Activity Service Area(10, case insensitive) ✎						
With 2 selected: Activate Deactivate Total: 50						
<input type="checkbox"/>	ID	Work Zone Name	Work Zone Keys	Status	Shapes	Actions
<input checked="" type="checkbox"/>	28	Alliance	North	Active	Shape	✎
<input checked="" type="checkbox"/>	1	ALTAMONTE SPRINGS	South	Active	Shape	✎

- On the **Work Zone** page, click **Add new** to add the required service area in the **Work Zone Keys** field.

* Work zone name	<input type="text" value="Stark"/>
* Work zone label	<input type="text" value="Stark"/>
Status	Active ▼
Delimiter	new line ▼
Travel Area	Sunrise Ente ▼
Work Zone Keys	32704 44720


- Click **Add** to save the new work zone.

Resource and Bucket Info

Oracle Field Service Cloud uses bucket and resources to categorize the resources. In this integration, use the bucket as a resource type to route the entire meter service tasks to workers. In the bucket, create two resources (field workers) who are assigned field activities coming from Oracle Utilities Work and Asset Cloud Service.


To create resources in the bucket:

- On the Oracle Field Service Home page, click the icon showing three horizontal linesv(on the top-left corner).



- Click **Resources** and select the resource to view its information.

- Click **Add child resource**.



- Select **Bucket** to add a new bucket in the **Resource type** drop-down list.

- Enter the required details and click **Submit**.
- Click **Add child resource** and select **Field Technician** from the **Resource type** drop-down list.
- Enter the required details and click **Submit**.
- To add work skills to this Technician, click the four lines at top-right corner and select **Work Skills**.
- Click the add icon (+).


10. Select the required work skills to this Technician. Click **Submit**.

Applications

This element is used to create a channel to communicate with Oracle Utilities Work and Asset Cloud Service through Oracle Integration Cloud. Various channel types can be chosen, but since Oracle Work and Asset Cloud Service integration to Oracle Field Service is through Oracle Integration Cloud, it is used as the channel type.

To add an application:

1. Navigate to the **Configuration** page > **Subsystems** > **Applications** icon.



2. Click **Add Application**. Enter the required details and click **OK**.

Application Name: Name of your choice (Ex: OIC)

Host: your OIC host name

User Name: OIC user name

Password: OIC password

Confirm Password: OIC password

Please note that starting Oracle Field Service 22D, the Basic Authentication support is no longer available for adding new applications to handshake with Oracle Integration Cloud. Create the application with OAuth 2.0 compliance. If you are an existing customer, the current application will work fine with Basic Auth after the upgrade. If you are a new customer, perform the following steps:

1. Select the **Oracle Integration** as the **Application Type**.
2. Enter the following details:
 - **Application Name:** Name of your choice
 - **OIC Host:** OIC host
 - **User Name:** OIC user
 - **IDCS URL:** OIC IDCS URL
 - **Client ID:** OIC Client ID from the application created
 - **Client Secret:** OIC Client Secret from the application created
 - **Key ID:** This is certificate alias, which is imported in OIC IDCS application.
 - **Scope:** Scope of the client application you created in IDCS
 - **Private Key File:** Drag and drop the private key file.
3. Click **Test Connection**, and then click **Add**.

For more information, refer to the Oracle Field Service and Oracle Integration Cloud documentation.

Configuring the Crew

To configure a crew:

1. Navigate to **Configuration** page and click **Resources, Activities, Inventories > Resource Types**.

2. Click **Add Resource Type**.

Resource Types								View	Add new
<input type="checkbox"/>	ID	Resource type name	Status	Label	Role	Icons	Actions		
<input type="checkbox"/>	3	Bucket	✓	BK	Bucket				
<input type="checkbox"/>	6	Contractor	✓	CO	Field resource				
<input type="checkbox"/>	9	Crew	✓	CR	Field resource				
<input type="checkbox"/>	1	Crew Member	✓	PR	Field resource				

3. Enter the required details and make sure the crew has 'PR' as the label. Click on **Add**.

Resource Type Info

Role
Field resource

☒ Active

Label
PR

Name: English
Required

Name: French (European)

Name: Portuguese (Brazil)

Name: Spanish (LA)

Name: Chinese (Traditional)

Load threshold

Units of measurement
number of activities

Full load
50
Enter a number greater than or equal to 0.
Quantity of activities in the route equals to or greater than value.

Empty
0
Quantity of activities in the route equals to or less than value.

Travel Allowance

Start of Day Travel
☒ Working Time does not include the Travel Time to the first activity

Features

☐ Resource is a Contingent Worker
☒ Resource can participate in team
☒ Resource can be a teamholder
☐ Share inventory in teamwork
☐ Share geolocation in teamwork
☒ Share work skills in teamwork (team-member only)
☐ Used for Quote management
☒ Routing can assign activities
☒ Enable 'Not activated in time' alert and trigger

Cost of time

Working hours cost
Normal

Overtime cost
Resource time cost is increased by 50% for the first 60 overtime minutes and by 100% afterward

Travel time cost
☐ Company does not pay for travel (Contractors, for example)
☒ Company partially pays for travel (gas reimbursement, for example)
☐ Company provides vehicle (recommended default choice for in-house employees)
☐ Travel is unusually expensive (difficult driving conditions, for example)

Statistic Parameters

Adding Crew and Crew Member

To create resources for the crew member and crew itself:

1. Navigate to the **Configuration** page > **Resources, Activities, Inventories** > **Resources Types**.
2. Click **Add**.
3. Populate the required information and click **Add**.

Resource Type Info

Role: Field resource

☒ Active

Label: CR

Name: English

Name: French (European)

Name: Portuguese (Brazil)

Name: Spanish LA

Name: Chinese (Traditional)

Load threshold

Units of measurement: number of activities

Full load: 10

Quantity of activities in the route equals to or greater than value.

Empty: 0

Quantity of activities in the route equals to or less than value.

Travel Allowance

Features

☐ Resource is a Contingent Worker

☐ Resource can participate in team

☒ Resource can be a teamholder

☒ Share inventory in teamwork

☐ Share geolocation in teamwork

☐ Share work skills in teamwork (team-member only)

☐ Used for Quote management

☒ Routing can assign activities

☐ Enable 'Not activated in time' alert and trigger

Cost of time

Working hours cost: Normal

Overtime cost

Resource time cost is increased by 50% for the first 60 overtime minutes and by 100% afterward

Travel time cost

☐ Company does not pay for travel (Contractors, for example)

☒ Company partially pays for travel (gas reimbursement, for example)

☐ Company provides vehicle (recommended default choice for in-house employees)

☐ Travel is unusually expensive (difficult driving conditions).

Travel Allowance

Start of Day Travel

☐ Working Time does not include the Travel Time to the first activity

☒ Working Time includes the Travel Time to the first activity

Working Time includes up to _____ minutes of the Travel Time to the first activity

End of Day Travel

☐ Working Time does not include the Travel Time from the last activity to the Resources End Location

☒ Working Time includes the Travel Time from the last activity to the Resources End Location

Working Time includes up to _____ minutes of the Travel Time from the last activity to the Resources End Location

Statistic Parameters

☒ Personalize the estimation of activity duration

☒ Use data reported to enhance company-wide estimations

Days out of statistic estimation: 5

Do not consider reported data of the first working days, for statistic estimations.

Cancel Add

- Repeat steps 2 and 3 to create resource types for crew members.




Adding Truck Resource Type

To add a truck resource type:

- Repeat steps 1 and 2 in the [Configuring the Crew](#) section.

2. Populate the required information and make sure the Truck has 'TR' in the label. Click **Add**.

Edit Resource Type

Resource Type Info		Features
Name		Role Vehicle   
* English	Truck	<input checked="" type="checkbox"/> Share inventory in teamwork
Spanish/LA	Camio	<input checked="" type="checkbox"/> Share geolocation in teamwork
Portuguese (Brazil)	Caminhão	<input type="checkbox"/> Share work skills in teamwork (team member only)
French (European)		<input type="checkbox"/> Working time includes first travel to activity
* Label	TR	<input type="checkbox"/> Working time includes travel to final location (if defined)
Active	<input checked="" type="checkbox"/>	
Load threshold		
Units of measurement	number of activities	
Full load	If resource has 10 or more activities	
Empty	If resource has 2 or less activities	

Travel Allowance

Start of Day Travel

☒ Working Time does not include the Travel Time to the first activity

☐ Working Time includes the Travel Time to the first activity

☐ Working Time includes up to minutes of the Travel Time to the first activity

End of Day Travel

☒ Working Time does not include the Travel Time from the last activity to the Resources End Location

☐ Working Time includes the Travel Time from the last activity to the Resources End Location


☐ Working Time includes up to minutes of the Travel Time from the last activity to the Resources End Location

Assigning Resources

To add multiple resources to a crew so that they can assess them:

1. Navigate to the **Activities** page and observe the various resources.

2. Drag and drop the resources to assign them to the crew.



3. Add activities to the crew.

4. Populate the required information and click **Submit**.

Offline vs Online Mode



When the crew is enroute to perform an activity in the field there is a possibility that the location does not have network (offline mode); if the network exists, the mode is online. When online, crew can perform the work, validate the completion of the activity, and submit the activity for completion. But, when offline, though the crew can validate and complete the activity, this completion information will be synched to server and message is sent out of Oracle Field Service only when it comes online.

Offline support is currently provided when adding service histories, planned service histories, measurements, and viewing asset attributes. User can also add attachments to a service history.

Offline support is also provided for “Materials” plugin and “Asset Component Install Exchange Undo” plugin operations, such as replace asset, undo replace asset, attach component, undo attach component, use item, undo use item, etc.. when assets/components are used from truck. However, the operations like install asset, attach component, replace asset and replace component cannot be performed when querying an asset/component from Oracle Utilities Work and Asset Cloud Service using badge number. Operations like “update truck” and “Refresh activity” are also not supported in offline mode. Once the crew is online, they can perform all the operations.

If the crew time is entered offline, crew must open the **Resource Usage** page when online before going offline. This make sure all relevant crew member information needed is available on local storage before going offline. Timesheets/equipment/others can be entered in offline mode but cannot be completed. All individual **Complete** and **CompleteAll** buttons will be disabled in offline mode. The crew should open all plugins once when online before starting the work in offline mode to sync required information in local storage.

Note: In offline mode, the “Lock Activity” option will be disabled, so the crew can perform all the mentioned operations without locking the activity. However, when the crew comes online, the “LockActivity” option will be enabled if the lock.functionality property in the WAMOFSC_ConfigProps lookup is set to “true”.



Crew Time

As part of the crew time sheet functionality, from the plugin, there is an invocation call to OFS REST API to configure the crew members under Crew.

To call OFS REST API from the plugin, set up cross-origin resource sharing (CORS) in Oracle Field Service as follows:

1. Navigate to **Configuration > Application > Additional Resources**.
2. Select **Allow Cross-origin resource sharing (CORS) from the following web domains** and provide the Oracle Field Service domain.

If the domain details are unknown, enter an asterisk (*). For the actual Oracle Field Service domain, contact the Oracle Field Service support team.

Additional restrictions

- ☐ Allow access only to certain resources
- ☐ Allow access only for certain IP-addresses
- ☒ Allow Cross-origin resource sharing (CORS) from the following web domains

*

https://plugin-hosting-yul-pod1.etadirect.com

https://demo-usdc0.etadirect.com

Each line should contain one domain name.

Example:

https://www.example.com
https://best.customer.com
https://bestcust.com

Inventory Types

The inventory types (such as asset, material, and so on) are stored in Oracle Field Service.

To add an inventory type:

1. Navigate to **Configuration > Resources, Activities, Inventories > Inventory Types**.
2. Click **Add New**.
3. Enter the details as shown below and click **Save**.

* Label	Asset
Active	<input checked="" type="checkbox"/>
Non Serialized	<input type="checkbox"/>
Model Property	Item Type [Item Type]
* Name	
* English	Assets
SpanishLA	
French (European)	[FR]Assets
Portuguese (Brazil)	
Chinese (Traditional)	
<input type="button" value="Close"/>	
<input type="button" value="Save"/>	

* Label	Material		
Active	<input checked="" type="checkbox"/>		
Non Serialized	<input checked="" type="checkbox"/>		
Decimal quantity	<input type="checkbox"/>		
Model Property	Item Category [Item Category]		
* Name		Unit of Measurement	
* English	Material	* English	quantity
SpanishLA		SpanishLA	
French (European)		French (European)	
Portuguese (Brazil)		Portuguese (Brazil)	
Chinese (Traditional)		Chinese (Traditional)	
<input type="button" value="Close"/>		<input type="button" value="Save"/>	

* Label	Equipment		
Active	<input checked="" type="checkbox"/>		
Non Serialized	<input checked="" type="checkbox"/>		
Decimal quantity	<input type="checkbox"/>		
Model Property	Item Category [Item Category]		
* Name		Unit of Measurement	
* English	Equipment	* English	Each
SpanishLA		SpanishLA	
French (European)		French (European)	
Portuguese (Brazil)		Portuguese (Brazil)	
Chinese (Traditional)		Chinese (Traditional)	
<input type="button" value="Close"/>		<input type="button" value="Save"/>	

4. Repeat step 2 for StockItem, StockAsset, issuedAsset, and issuedComponent.

The screenshot shows the configuration form for 'StockAsset'. The 'Label' field is set to 'StockAsset'. The 'Active' checkbox is checked, and the 'Non Serialized' checkbox is also checked. The 'Decimal quantity' checkbox is unchecked. The 'Model Property' dropdown is set to 'Material Id [wam_material_id]'. The 'Name' section has a table with columns for language and value. The 'English' row has 'Assets' in the first column and 'asset' in the second column. The other language rows (SpanishLA, French (European), Portuguese (Brazil), Chinese (Traditional)) are empty. At the bottom, there are 'Close' and 'Save' buttons.

* Name		Unit of Measurement	
* English	Assets	* English	asset
SpanishLA		SpanishLA	
French (European)		French (European)	
Portuguese (Brazil)		Portuguese (Brazil)	
Chinese (Traditional)		Chinese (Traditional)	

Note: Default Quantity precision is set to 2. The user can configure it according to the requirement.

The screenshot shows the configuration form for 'issuedAsset'. The 'Label' field is set to 'issuedAsset'. The 'Active' checkbox is checked, and the 'Non Serialized' checkbox is unchecked. The 'Model Property' dropdown is set to 'Item Type [Item Type]'. The 'Name' section has a table with columns for language and value. The 'English' row has 'Issued Assets' in the first column. The other language rows (SpanishLA, French (European), Portuguese (Brazil), Chinese (Traditional)) are empty. At the bottom, there are 'Close' and 'Save' buttons.

* Name	
* English	Issued Assets
SpanishLA	
French (European)	
Portuguese (Brazil)	
Chinese (Traditional)	

The screenshot shows the configuration form for 'issuedComponent'. The 'Label' field is set to 'issuedComponent'. The 'Active' checkbox is checked, and the 'Non Serialized' checkbox is unchecked. The 'Model Property' dropdown is set to 'Item Type [Item Type]'. The 'Name' section has a table with columns for language and value. The 'English' row has 'Issued Components' in the first column. The other language rows (SpanishLA, French (European), Portuguese (Brazil), Chinese (Traditional)) are empty. At the bottom, there are 'Close' and 'Save' buttons.

* Name	
* English	Issued Components
SpanishLA	
French (European)	
Portuguese (Brazil)	
Chinese (Traditional)	

Activity Links


Activity links determine the dependencies between the activities in Oracle Field Service.

To add an activity link:

1. Navigate to **Configuration > General > Link Templates**.
2. Click **Add New**.
3. Enter the **General Settings**, **Time interval between activities**, **Link for the first activity**, and **Link for the second activity** for W1AS_AfterStart. Click **Add**.

Add Link Template

General Settings



Second activity starts after the first one is finished (Finish-to-Start)

☒ Active

Time interval between activities

Minimum interval
Adjustable

Maximum interval
Unlimited

Assignment constraints
No

Scheduling constraints
No

Minutes
0

Link for the first activity

Name: English
Start Before

Name: French (European)
Start Before

Name: Portuguese (Brazil)
Start Before

Name: Greek
Start Before

Name: Chinese (Traditional)
Start Before

Label
start_before

Link for the second activity

Name: English
Start After

Name: French (European)
Start After

Name: Portuguese (Brazil)
Start After

Name: Greek
Start After

Name: Chinese (Traditional)
Start After

Label
W1AS_AfterStart

Cancel

Add

- Repeat the previous step for W1AF_AfterFinish.

Add Link Template

General Settings



Second activity starts after the first one is finished (Finish-to-Start)

☒ Active

Time interval between activities

Minimum interval
Adjustable

Minutes
0

Maximum interval
Unlimited

Assignment constraints
No

Scheduling constraints
No

Link for the first activity

Name: English
Finish Before

Name: French (European)
Finish Before

Name: Portuguese (Brazil)
Finish Before

Name: Greek
Finish Before

Name: Chinese (Traditional)
Finish Before

Label
finish_before

Link for the second activity

Name: English
Finish_after

Name: French (European)
Finish_after

Name: Portuguese (Brazil)
Finish_after

Name: Greek
Finish_after

Name: Chinese (Traditional)
Finish_after

Label
WIAF_AfterFinish

Cancel


Add

Timesheet/ Other Direct Charges Flag

This flag indicates whether a mobile worker is allowed to add a timesheet or other direct charges for an activity that has been completed.

In the Oracle Utilities Work and Asset Management master configuration, the following properties accept the **Yes** or **No** values.

- Allow Timesheet against completed activity.
- Allow ODC against completed activity.



Master Configuration: Work Management Master Configuration

Main

Master Configuration Details

Main

BUSINESS OBJECT Work Management Master Configuration

Work Order Parameters

WORK ORDER AUTO CLOSURE NUMBER OF DAYS 180

ALLOW STOCK ISSUE AGAINST COMPLETED ACTIVITY Yes

ALLOW TIMESHEET AGAINST COMPLETED ACTIVITY Yes

ALLOW ODC AGAINST COMPLETED ACTIVITY Yes

To set the value of these properties in Oracle Field Service:

1. Navigate to **Configuration > Resources, Activities, Inventories > Properties**. Search for Resource Usage Flag.

<input type="checkbox"/>	ID	Property name	Property Label	Type	Entity	GUI	Actions
<input type="checkbox"/>	1225	Resource Usage Flag	wam_ru_comp_act_flag	enumeration	Activity	combobox	

2. Click **Modify**. Go to the **Enumeration values** section. TS and ODC indicate Timesheet and Other Direct Charges respectively. Default value for both flags is “NO”.

Modify Property

General settings

Entity: Activity

Label: wam_ru_comp_act_flag

Name: English: Resource Usage Flag

Name: French (European):

Name: Portuguese (Brazil):

Name: SpanishLA:

Name: Chinese (Traditional):

Property hint

Type and advanced settings

Property type: Enumeration

GUI: Combobox

☐ Clone property data on Reopen or Prewrite

Enumeration values

ID	TL	Value	TL	Status	TL	Actions
ODCNO		ODCNO		Active		
ODCYES		ODCYES		Inactive		
TSNO		TSNO		Active		
TSYES		TSYES		Inactive		

Add

3. To change the value of flags, select or unselect the **Active** checkbox to make the corresponding enum values of YES/NO active or inactive respectively.
4. Click **Change > Update** to reflect the changes. Else, click **Cancel**.

Timeout Seconds

User can set the value of timeout variable in seconds that indicates a limit on how long they are willing to wait for a response from a service to come back on client side. This configuration is added to stop the loading spinner and display timeout message on UI if the request takes too long for response.

To set the value of this property in Oracle Field Service:

1. Navigate to **Configuration > Properties**. Search for “Timeout”.
2. To add new value for timeout, click **Modify** and go to the **Enumeration values** section.
 - a. Provide key and value in seconds.
 - b. Click **Add**.
 - c. Select or deselect the **Active** checkbox to make the corresponding enum values of timeout active or inactive respectively.

- d. Click **Change** > **Update** to reflect the changes. Else, click **Cancel**.

Modify Property

General settings

Entity: Activity

Label: timeout

Name: English: Timeout

Name: French (European):

Name: Portuguese (Brazil):

Name: Spanish LA:

Name: Chinese (Traditional):

Type and advanced settings

Property type: Enumeration

GUI: Combobox

☐ Clone property data on Reopen or Pework

Enumeration values

ID	Value	Status	Actions
60	60	Active	

Add

Note: Default value of timeout is 60 seconds. There must be only one value active at a time.

Checklist

Before proceeding to [User Operations](#) verify if the following activities are complete.

- All the Activity Types specific to customer are created
- Properties are imported
- User Types are imported
- Plugins are configured
- Make sure the quota is allocated and need not be configured
- Name of the organization
- Synchronization information from Oracle Utilities Work and Asset Cloud Service to Oracle Field Service
- Work Skills are created
- Name of the resources, work zones
- Inventory Types are created
- Details of Oracle Integration Cloud used to create the outbound channel
- If crew resource is selected while creating the activity in Oracle Utilities Work and Asset Cloud Service, make sure those resources are synchronized to Oracle Field Service also. As the crew synchronization is not available, add them manually in Oracle Field Service with same crew name and resource ID.

Chapter 4

User Operations


This chapter provides step-by-step instructions to perform user operations. It includes the following:

- [Starting the Activity](#)
- [Locking Activity](#)
- [Activity Details](#)
- [Service Histories](#)
- [Measurements](#)
- [Asset Attribute](#)
- [Asset History](#)
- [Resource Usage](#)
- [Activity Completion](#)
- [Asset Installs and Removals](#)
- [Pick Up and Follow Up Orders](#)
- [Follow Up Work Order](#)
- [Follow Up Work Request](#)
- [Mobile Inventory Management](#)

Starting the Activity

To start an activity:

1. Login to the Oracle Field Service Mobility application.
2. Access the **Mobility** page using the worker/technician's credentials. The page shows the activities in the queue of the worker.
3. Click **Start** to start the activity in the worker's queue.



4. Enter the **Start Time** and **Work Activity Number**. Click **Submit**.

Locking Activity

Activity is presented to mobile user in read only mode. To make changes to the activity, enter completion information, service histories and resource usage, you must lock the activity. Locking an activity guarantees that only one member of the crew can update the activity. After the work is done, unlock the activity so that other crew members can make their updates.

Note: The Lock functionality can be enabled/disabled by setting the lock.functionality property in the WAMOFSC_ConfigProps lookup in OIC to true/false. Refer to the [Plugins Rendering Data](#) section in [Chapter 5: Customizations](#) for more information.

Activity Details (South Crew - 12/22/21)

Search in activities or inventories

2:26 Adjust

Complete

Follow Up Work

New Work

Adjust Time

Not Done

Suspend

Activity Details

Work Order Description:

OFSC Hydrant Inspection- Asset List

Activity ID:

4278630

Activity Number:

210000029/1

Activity type:

Inspection Repair

Activity status:

Started

Description:

Hydrant Inspection

Detailed Description:

Hydrant Inspection

Location Information:

Hydrant - 311 Jamatt Ct, Naperville

Asset Information:

Hydrant, Badge Number 37998, In Service @ Hydrant - 311 Jamatt Ct, Naperville

Emergency Indicator:

No

Requestor information:

System, English

Total Risk Priority:

12

Required By Date:

2022-01-06

Duration:

2 hours 30 minutes

Navigate

Map

Book (create) activity

Nearby Activities


Materials Tracking

Knowledge


Lock Activity

Activity Details


Crew can view information about an activity, including resources required for the activity and assets to be serviced.



If any activity has dependencies, the information related to it gets displayed in the **Activity Dependencies** section.




To view resources, navigate to the **Activity Details** page and click **Resources**. Resources include planned materials, work skills, equipment and other resources defined by activity planner.



To view the list of assets for an activity, navigate to the **Activity Details** page and click **Assets**.

The following figure shows Oracle Field Service displaying all assets attached to an activity. Select the required asset to view the asset information.



Asset/Equipment Details
Pole - Wood, Badge Number AssetBN06032, Planned @ - Location type for Tracked assets, Opp Hitex Charminar, uniontown, OH...

Asset Details

Asset Information
Pole - Wood, Badge Number AssetBN06032, Planned @

Badge Number
AssetBN06032

Asset Description
Pole - Wood

Serial Number
AssetsN06032

Asset Location

Location Information
Location type for Tracked assets, Opp Hitex Charminar, uniontown, OH, 44072, US, Time Zone: US/Pacific

Service Area
North

Asset Worked: Yes

Asset Worked

Quick Links

Service History Measurements Asset Attribute

The crew can also view the details of attachments. In Oracle Field Service, click **Attachment** on the **Activity Details** page. These activity level attachments are added to Oracle Utilities Work and Asset Cloud Service while creating the activity and are sent to the Oracle Field Service through Oracle Utilities Work and Asset Cloud Service outbound messages. The user is permitted to only download the attachment but not edit or delete it at the activity level.

Service Histories

Two types of service histories can be entered for activity:

- **Planned Service Histories:** Planned service histories are requested by a person who plans an activity and must be entered by field crew. These service histories can be entered from the **Planned Service Histories** page. After they are created, they will be displayed among the asset specific service histories.
- **Asset Service Histories:** Asset service histories are additional service histories valid for that asset. They are listed in the asset's **Service Histories** page.

Planned Service Histories

Navigate to the **Activity Details** page and click **Planned Service History**. The **Planned Service Histories** page is displayed.

Activity Information: 200000021/619 - Asset replace/Install Asset/Install Asset tracked & Test FR

Asset Information: All applicable assets

Planned Service History List Entered

Service History Type	Entered
Associated Permit Numbers Required No: Entered 0	No items to display
INTQuestionnaireSHTypeDesc Required No: Entered 0	
General SH Required No: Entered 0	
Downtime Asset Level	
PM - Meter Calibration (Annual) Asset Level	
PM - Meter DO Cleaning Asset Level	
Failure Asset Level	

Quick Links

[Asset Details](#) [Activity Details](#)

To enter the planned service history details:

1. From the list of planned service histories that are part of the activity, click “+” next to the specific service history, and add the necessary details.

Activity Information: 200000021/619 - Asset replace/Install Asset/Install Asset tracked & Test FR

Asset Information: All applicable assets

Planned Service History List Entered

Service History Type	Entered
Associated Permit Numbers Required No: Entered 0	No items to display
INTQuestionnaireSHTypeDesc Required No: Entered 0	
General SH Required No: Entered 0	
Downtime Asset Level	
PM - Meter Calibration (Annual) Asset Level	
PM - Meter DO Cleaning Asset Level	
Failure Asset Level	

Quick Links

[Asset Details](#) [Activity Details](#)

Users have an option to add service histories at **Activity Level** or at **All Applicable Assets**, if the service histories are not asset specific.

- Click **Complete**. Service histories are displayed in the **Entered** pane.

The screenshot shows the 'General SH' form. At the top, there are two radio buttons: 'Activity' and 'All Applicable Assets'. The 'All Applicable Assets' button is selected and highlighted with a blue box. Below this, there is a text field for 'Effective Date/Time' with the value '21.02.23 06:09:00'. A large text area for 'Service History Comments' is below that. At the bottom, there are four buttons: 'Save', 'Complete', 'Attach', and 'Dismiss'. The 'Complete' button is highlighted with a blue box.

If **All Applicable Assets** is selected, service histories will be added at all applicable assets and will also be displayed in the **Entered** section with an indication as **Asset Level**.

The screenshot shows the 'Entered' pane. On the left, there is a 'Planned Service History List' with several items: 'Associated Permit Numbers', 'INTQuestionnaireSHTYPEDesc', 'General SH', 'Downtime', and 'PM - Meter Calibration (Annual)'. Each item has a plus icon to its right. On the right, there is a 'General SH' entry with the status 'COMPLETED' and 'Asset Level' highlighted with a blue box.

If **Activity** is selected while adding the service histories, they will be added at activity level and displayed in the **Entered** section with an indication **Activity Level**.

Note: Crew can also save the service history in 'pending' state.

- Click **Save**. The pending service histories are displayed in the **Entered** pane with the 'pending' status.

The screenshot shows the 'General SH' form. At the top, there are two radio buttons: 'Activity' and 'All Applicable Assets'. The 'All Applicable Assets' button is selected. Below this, there is a text field for 'Effective Date/Time' with the value '21.02.23 06:09:00'. A large text area for 'Service History Comments' is below that. At the bottom, there are four buttons: 'Save', 'Complete', 'Attach', and 'Dismiss'. The 'Save' button is highlighted with a blue box.

Activity Information: 200000021/619 - Asset replace/Install Asset/Install Asset tracked & Test FR
Asset Information: All applicable assets

Planned Service History List

Associated Permit Numbers Required No: Entered: 0	+
INTQuestionnaireSHTypeDesc Required No: Entered: 0	+
General SH Required No: Entered: 3	+
Downtime Asset Level	

Entered

General SH Status: COMPLETED Asset Level	✎
General SH Status: COMPLETED Activity Level	✎
General SH Status: PENDING Asset Level	✎

4. To complete a service history in 'pending' status:
 - a. Click **Edit** to edit a specific service history.

Activity Information: 200000021/619 - Asset replace/Install Asset/Install Asset tracked & Test FR
Asset Information: All applicable assets

Planned Service History List

Associated Permit Numbers Required No: Entered: 0	+
INTQuestionnaireSHTypeDesc Required No: Entered: 0	+
General SH Required No: Entered: 3	+
Downtime Asset Level	

Entered

General SH Status: COMPLETED Asset Level	✎
General SH Status: COMPLETED Activity Level	✎
General SH Status: PENDING Asset Level	✎

The completed service histories are displayed in the Entered pane. The number of times the service history was edited is also shown.

Activity Information: 200000021/619 - Asset replace/Install Asset/Install Asset tracked & Test FR
Asset Information: All applicable assets

Planned Service History List

Associated Permit Numbers Required No: Entered: 0	+
INTQuestionnaireSHTypeDesc Required No: Entered: 0	+
General SH Required No: Entered: 3	+
Downtime Asset Level	
PM - Meter Calibration (Annual) Asset Level	
PM - Meter PM's Planning	

Entered

General SH Status: COMPLETED Asset Level	✎
General SH Status: COMPLETED Activity Level	✎
General SH Status: COMPLETED Asset Level	✎

- b. Click **Attach** to attach images of various artifacts.
- c. Browse and select the file to attach. Click **Upload**.
- d. After the attachment is uploaded, a list of attachments (unsaved attachments) is shown. Click **Complete** to complete the service history.
- e. Make sure the service histories that are marked as “Required: Yes” have at least one entry.

Asset Service Histories

To enter an asset's service histories, navigate to the **Asset** page and click **Service History**.

Activity Information: 210000029/1 - Hydrant Inspection
 Asset Information: Hydrant, Badge Number 37998, In Service @ Hydrant - 311 Jamatt Ct, Naperville
 Asset Location Information: Hydrant - 311 Jamatt Ct, Naperville

Service History List

Service History Item	Entered	Planned
Hydrant Inspection Questionnaire Required: Yes Entered: 1 Planned: Yes	No items to display.	
Downtime Required: No Entered: 1 Planned: Yes		
Failure Required: No Entered: 0 Planned: No		
General SH Required: No Entered: 1 Planned: Yes		
Reset Asset Condition Service History Required: No Entered: 0 Planned: No		
General Repair SH Required: No Entered: 0 Planned: No		
PM - Hydrant Inspection Required: No Entered: 0 Planned: No		
PM Event- Annual Shutdown Required: No Entered: 0 Planned: No		
PM Event- Bi-Annual Shutdown Required: No Entered: 0 Planned: No		

Entered

No items to display.

Planned

Downtime Status: PENDING
General SH Status: PENDING
Hydrant Inspection Questionnaire Status: PENDING

Quick Links

Asset Details Activity Details Complete All

To enter the service history details:

1. Click **Service History** on the **Assets** page.
2. From the list of service histories that are part of the activity, click “+” next to the specific service history to add the required details.

Activity Information: 200000021/524 - Asset replace/install Asset/install Asset tracked
 Asset Information: Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked
 Asset Location Information: MeterFlow 650 - in WW Plant 4

Service History List

Downtime Required: No Entered: 0 Planned: Yes	
Failure Required: No Entered: 0 Planned: No	
General SH Required: No Entered: 0 Planned: Yes	
INTQuestionnaireSHTypeDesc Required: No Entered: 0 Planned: No	
PM - Meter Calibration (Annual) Required: No Entered: 0 Planned: No	
PM - Meter DO Cleaning Required: No Entered: 0 Planned: No	

Entered

No items to display.

Planned

No items to display.

Quick Links

Asset Details Activity Details Complete All

General SH

Asset Information:	Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked
Asset Location Information:	MeterFlow 650 - in WW Plant 4
Effective Date/Time*:	04/08/22 05:16:00 PM

Service History Comments:

Save
Complete
Attach
Dismiss

3. Click **Complete**. The service histories are displayed in the **Entered** pane.

Activity Information:	200000021/524 - Asset replace/Install Asset/Install Asset tracked
Asset Information:	Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked
Asset Location Information:	MeterFlow 650 - in WW Plant 4

Service History List

Downtime	+
Required: No Entered: 0 Planned: Yes	
Failure	+
Required: No Entered: 0 Planned: No	
General SH	+
Required: No Entered: 1 Planned: Yes	
INTQuestionnaireSHTypeDesc	+
Required: No Entered: 0 Planned: No	
PM - Meter Calibration (Annual)	+
Required: No Entered: 0 Planned: No	
PM - Meter DO Cleaning	+
Required: No Entered: 0 Planned: No	

Entered

General SH

Status: COMPLETED

Planned

No items to display.

Quick Links

Asset Details
Activity Details
Complete All

Note: Crew can also save the service history in 'pending' state. Click **Save**. The pending service histories are displayed in the **Entered** pane with the 'pending' status.

General SH

Asset Information: Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked

Asset Location Information: MeterFlow 650 - in WW Plant 4

Effective Date/Time*: 04/08/22 05:20:00 PM

Service History Comments:

Save the data

Save

Complete

Attach

Dismiss

Activity Information: 200000021/524 - Asset replace/Install Asset/Install Asset tracked

Asset Information: Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked

Asset Location Information: MeterFlow 650 - in WW Plant 4

Service History List

Downtime <small>Required: No Entered: 0 Planned: Yes</small>	+
Failure <small>Required: No Entered: 0 Planned: No</small>	+
General SH <small>Required: No Entered: 2 Planned: Yes</small>	+
INTQuestionnaireSHTypeDesc <small>Required: No Entered: 0 Planned: No</small>	+
PM - Meter Calibration (Annual) <small>Required: No Entered: 0 Planned: No</small>	+
PM - Meter DO Cleaning <small>Required: No Entered: 0 Planned: No</small>	+

Entered

General SH
Status: COMPLETED

General SH
Status: PENDING

Planned

No items to display.

Quick Links

Asset Details

Activity Details

Complete All

4. To complete a service history in 'pending' status:

- a. Click **Edit** to edit a specific service history.

The screenshot displays the 'Service History List' for asset 200000021/524. The list includes entries for Downtime, Failure, General SH, INTQuestionnaireSHTypeDesc, PM - Meter Calibration (Annual), and PM - Meter DO Cleaning. The 'General SH' entry is highlighted with a blue box, indicating it is the selected item. Below the list, there are 'Quick Links' for Asset Details, Activity Details, and Complete All.

Service History List

Activity Information:	200000021/524 - Asset replace/Install Asset/Install Asset tracked
Asset Information:	Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked
Asset Location Information:	MeterFlow 650 - in WW Plant 4

Service History List

Activity Information:	200000021/524 - Asset replace/Install Asset/Install Asset tracked
Asset Information:	Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked
Asset Location Information:	MeterFlow 650 - in WW Plant 4

General SH

Status: COMPLETED

General SH

Status: PENDING

Planned

No items to display.

Quick Links

Asset Details Activity Details Complete All

- b. Click **Attach** to attach images of various artifacts.

The screenshot shows the 'General SH' details page. It includes fields for Asset Information, Asset Location Information, and Effective Date/Time*. Below these fields is a 'Service History Comments' section with a text area and an 'Attach an image' button. At the bottom of the page, there are buttons for Save, Complete, Attach, Delete, and Dismiss. The 'Attach' button is highlighted with a blue box.

General SH

Asset Information: Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked

Asset Location Information: MeterFlow 650 - in WW Plant 4

Effective Date/Time*: 04/08/22 05:20:00 PM

Service History Comments: Attach an image

Save Complete **Attach** Delete Dismiss

- Browse and select the file to attach. Click **Upload**.
- After the attachment is uploaded, a list of attachments (unsaved attachments) is shown. Click **Complete** to complete the service history.

The completed service histories are displayed in the **Entered** pane. The number of times the service history was edited is also shown.

Activity Information:200000021/524 - Asset replace/Install Asset/Install Asset tracked

Asset Information:Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked

Asset Location Information:MeterFlow 650 - in WW Plant 4

Service History List

Downtime

Required: No Entered: 0 Planned: Yes

Failure

Required: No Entered: 0 Planned: No

General SH

Required: No Entered: 2 Planned: Yes

INTQuestionnaireSHTypeDesc

Required: No Entered: 0 Planned: No

PM - Meter Calibration (Annual)

Required: No Entered: 0 Planned: No

PM - Meter DO Cleaning

Required: No Entered: 0 Planned: No

Entered

General SH

Status: COMPLETED

General SH

Status: COMPLETED

Planned

No items to display.

Quick Links

Asset Details

Activity Details

Complete All

- c. Populate the details for required service histories.
- d. Make sure the service histories that are marked as 'Required: Yes' have at least one entry.
- e. Click **Asset Details** to navigate back to the **Asset Details** page.

Supported Service History Types


There are five service histories categories supported out of the box: Questionnaire, Inspection, Failure, Downtime and General. They correspond to business objects defined in Oracle Utilities Work and Asset Management. Refer to [Chapter 5: Customizations](#) for information about creating custom service history categories.

Measurements


To enter an asset’s measurements:

- 1. Navigate to the **Assets** page.


2. Click **Measurements**.



3. Click “+” on the **Measurement Mobility** page.



4. Enter the required measurement details and click **Save**.



The measurement is displayed in the list.

Activity Information: 200000021/426 - Asset replace/Install Asset/Install Asset tracked & Test FR

Asset Information: Fan - Centrifugal, Badge Number 4053_4APRI_FAN, In Service @ 4A Primary Air Fan

Asset Location Information: 4A Primary Air Fan

Activity Information (+)

Runtime Hours
Reading Date/Time: Apr 07, 2022 at 10:27 AM
Reading: 1

Quick Links

Asset Details Activity Details

- Click the edit icon to edit the measurement. You can enter multiple measurements.
- Click **Activity Details** to navigate back to the **Activity Details** page.

Asset Attribute

- Click **Asset Attribute** in the **Quick Links** section in the **Asset/Equipment** details page.
- It will navigate to the **Asset Attribute List** page. Click **Dismiss** to navigate to the **Asset Details** page.

Asset History

- Click **Asset History** in the **Quick Links** section in the **Asset/Equipment** details page.
- It will navigate to the **Asset History** page. Click the back arrow to navigate to the **Asset Details** page.

↑ Asset History

Asset Information: Pole - Wood, Badge Number AssetBN06114, In Service @ Address for MultiDay

Service History

Expand Filters Filters: Period (Months)10

Effective Date/Time	Service History Type	Category
11/06/24 01:19 AM	General SH	Maintenance
11/06/24 01:18 AM	Downtime	Downtime
11/06/24 01:17 AM	Failure	Failure
11/06/24 01:16 AM	Failure	Failure
11/06/24 01:14 AM	General SH	Maintenance
11/06/24 01:12 AM	Downtime	Downtime
11/06/24 01:09 AM	General SH	Maintenance

Measurements

Filters: Period (Months)12

Reading Date/Time	Measurement Type	Reading	Status
11/06/24 12:00 AM	Hydrogen	25.00	Final
11/05/24 06:40 AM	Methane	25.00	Final
11/05/24 03:15 AM	Hydrogen	19.00	Final
11/05/24 02:50 AM	Methane	26.00	Evaluation Alert
11/05/24 12:20 AM	Gallons Flow	20.50	Final
11/05/24 12:00 AM	Gallons Flow	22.00	Final

Activity History

Expand Filters

Filters: Period (Months)14

Activation Date/Time	Service Class	Activity Type	Activity Description	Required By	Status
11/06/24 03:25 AM	Corrective Maintenance	Activity - Minor Repair	Pole Minor Repair	11/06/24	In Progress
11/06/24 03:25 AM	Corrective Maintenance	Activity - Minor Repair	Pole Minor Repair&	11/06/24	In Progress
11/06/24 03:25 AM	Corrective Maintenance	Activity - Minor Repair	Pole Minor Repair&	11/06/24	In Progress
11/06/24 12:00 AM	Corrective Maintenance	Activity - Inspection/Repair (External)	Activity for Asset Inspection	11/07/24	In Progress
11/06/24 12:00 AM	Corrective Maintenance	Activity - Gas Leak Repair	Repair for Gas Leakage	11/06/24	Pending
01/22/24 04:59 AM	Municipal Services	MultiDay_PlannedActivity Type_for WAM-OFSC	Minor Repair Work for Asset Installation		Completed

Resource Usage

To enter resource usage details:

1. Click **Resource Usage** in the **Quick Links** section in **Activity Details** page.
2. Enter time sheets, equipment, and other details.

The user operations performed on the **Resource Usage** page are shown for both [Individual Crew](#) and [Supervisor](#).

- **Individual Crew**
 - a. Click “+” against the TimeSheet section for an individual crew to enter individual timesheets.
 - Actual time spent on the activity is defaulted in the time sheets to avoid manual entry. But, a crew can always change the time spend by manually selecting date time from the calendar.
 - When the activity is in started state, the **Work Started** field defaults to the time the crew started the activity. **Work Stopped** defaults with the time derived from the activity's start time plus its duration.
 - When the activity is completed by the crew, work started and work stopped are populated with the exact times that the activity was started and completed.
 - The **Hours** field is read-only and defaulted with the difference between **Work Stopped** and **Work Started**.

The timesheet also auto populates the crew member's craft/work skills. Additionally, the user has an option to view all the craft skills. Select the **View All Crafts** check box to view the available craft skills.

Activity Information: 200000021/524

Employee Information*: John

Date*: 05/08/22

Regular/Overtime*:

Crew Shift Type:

Labor Earning Type:

Craft*: Carpenter ForemanWD-Hour

☒ view all crafts

Hours*: 0.16

Work Started*: 04/08/22 07:21:00 AM

Work Stopped*: 04/08/22 07:31:00 AM

Travel Time: HH: 00 MM: 3

Save Dismiss

Activity Information: 200000021/523

Employee Information*: John

Date*: 28/07/22

Regular/Overtime*: Regular

Crew Shift Type:

Labor Earning Type:

Craft*: Maintenance Engineer Test no hr rate

Hours*:

Work Started*:


Work Stopped*:

Travel Time:

Save Complete

- After saving, the timesheet is created in 'pending' status.
- Click the **Edit** icon. Enter the necessary details and click **Complete** to complete the timesheet.
- Populate the entries for equipment and other.
- Navigate back to the **Activity Details** page after populating all the required resource details.
- Click **Complete** to verify the eligibility of the activity to complete.

- g. If all activities are not eligible for activity completion, the following message is displayed. Click **OK**.



- h. Else, it will navigate to the **End Activity** screen. Click **Submit**.

The completion information is sent to Oracle Utilities Work and Asset Cloud Service and the activity is completed.

- **Supervisor**

A supervisor can enter individual timesheets (highlighted in purple) or for team (highlighted in yellow). In addition, a supervisor can enter individual timesheet for himself if the secure parameter, “ofsc_sup_in_team” is set to true/yes in the plugin settings.



- Click “+” against the TimeSheet section to add an individual timesheet (highlighted in purple in the figure above).
 - Actual time spent on the activity is defaulted in the time sheets without manual entry. But, a supervisor can always change the time spent by manually selecting from the calendar.
 - When the activity is in started state, the **Work Started** field defaults to the time the crew started the activity. **Work Stopped** defaults with the time derived from the activity's start time plus its duration.
 - When the activity is completed by the crew, work started and work stopped are populated with the exact times that the activity was started and completed.
 - The **Hours** field is read-only and defaulted with the difference between **Work Stopped** and **Work Started**.


- The timesheet also auto populates the crew member's craft/work skills. Additionally, you can view all the craft skills. Select the **View All Crafts** check box to view the available craft skills.

- Enter the required information and click **Save**.
- Click the '+' icon to add timesheet for the team (highlighted in yellow in the figure above).
- After saving, the timesheets for each crew member are created in 'pending' status.
- Click the **Edit** icon. Enter the necessary details and click **Complete** to complete the timesheet.
- Populate the entries for equipment and other.

Activity Completion

To complete an activity:

1. Navigate back to the **Activity Details** page after populating all the required resource details.
2. Click **Complete** to verify the eligibility of the activity to complete.
3. If all activities are not eligible for activity completion, the following message is displayed. Click **OK**.



4. Else, it will navigate to the **End Activity** screen. Click **Submit**.

The completion information is sent to Oracle Utilities Work and Asset Cloud Service and the activity is completed.


Asset Installs and Removals

This section includes instructions to perform asset related operations, such as Install, Out Of Service, Removals, Replace, and Undo operations.


Installing Assets

To install an asset:

1. Start the activity.
2. To install an asset, click the location.



3. Click **Install Asset**.



4. Enter the **Badge Number** of the asset to be installed in this location and click **Install**.

5. The newly installed asset is shown in the **Installed** pool.


Assets/Equipment	
Existing 3	
Asset 3	
Fan - Centrifugal, Badge Number 4053_4APRI FAN_1, In Service @ Capacitor 3 - Bus 1 Capacitor 3 - Bus 1 Asset	1
Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked MeterFlow 650 - in WW Plant 4 Asset	1
Meter - Power - Tracked, MTPW-000000030, MTR030, Meter, Power, Tracked Template Capacitor 12 - Lake Substation Bus 1 Asset	1
Installed 1	
Fan - Centrifugal, Badge Number 4076_AESCANFN_1, Out of Service @ Out of Service Storeroom 4B Scanner Air Fan Asset Installed	1

To attach a component:


1. Start the activity.
2. To attach a component, click the asset.

Assets/Equipment	
Existing 3	
Asset 3	
Fan - Centrifugal, Badge Number 4053_4APRI FAN_1, In Service @ Capacitor 3 - Bus 1 Capacitor 3 - Bus 1 Asset	1
Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked MeterFlow 650 - in WW Plant 4 Asset	1
Meter - Power - Tracked, MTPW-000000030, MTR030, Meter, Power, Tracked Template Capacitor 12 - Lake Substation Bus 1 Asset	1
Installed 1	
Fan - Centrifugal, Badge Number 4076_AESCANFN_1, Out of Service @ Out of Service Storeroom 4B Scanner Air Fan Asset Installed	1


3. Click **Attach Component**.



4. Enter the **Badge Number** of the component to be attached and click **Attach**.




The attached component is shown in the **Installed Pool**.



To move an asset out of service:

1. Start the activity.
2. To move an asset **out of service**, click the asset.



- Click **Out of Service**.

↑ Assets/Equipment

Asset/Equipment Details

Fan - Centrifugal, Badge Number 4053_4APRI_FAN, In Service @ 4A Primary Air Fan - 4A Primary Air FanAsset

Remove ...

- Out of Service**
- Attach Component
- Replace
- Follow Up Work
- New Work

Asset Details

Asset Information
Fan - Centrifugal, Badge Number 4053_4APRI_FAN, In Service @ 4A Primary Air Fan

Badge Number
4053_4APRI_FAN

Asset Description
Fan - Centrifugal

Serial Number
500054

Asset Location

Location Information

- Enter the **effective date/time** and click **Submit**.

Asset Operation: Out of Service

Activity Information: 200000021/525

Asset Information: Fan - Centrifugal, Badge Number 4053_4APRI_FAN, In Service @ 4A Primary Air Fan

Effective Date Time*: 08/08/22 10:27:00 AM

Submit Dismiss


The asset moves to 'out of service' status in **Deinstalled** pool.

Installed	2
Asset	2
Brakes-Component, BRK-0001, BRK-0001, Brakes Capacitor 3 - Bus 1	Attached Component Installed 1
Fan - Centrifugal, Badge Number 4076_AESCANFN_1, Out of Service @ Out of Service Storeroom 48	Scanner Air Fan Asset Installed 1
Deinstalled	1
Fan - Centrifugal, Badge Number 4053_4APRI_FAN_1, In Service @ Capacitor 3 - Bus 1	Out Of Service Asset 1


To remove an asset/component:

- Start the activity.

- Click the asset/component to be removed.



- Click **Remove**.



- Enter the **effective date/time** and click **submit**.

Asset Operation: Remove Asset


Activity Information: 200000021/525

Asset Information: Fan - Centrifugal, Badge Number 4053_4APRI_FAN, In Service @ 4A Primary Air Fan

Effective Date Time*: 08/08/22 10:30:00 AM


Submit Dismiss

The asset/component is removed and moved to the **Deinstalled** pool.




To undo the installation:


1. To undo an installation, click the newly installed asset in the **Installed** pool.



2. Click **Undo Install Asset**.




3. Click **Submit**.




The asset/component installation is undone and it disappears from the installed pool.

To undo a newly attached component:


1. To undo attach, click the newly attached component in the installed pool.



2. Click **Undo Attach Component**.




3. Click **Submit**.




4. The attach operation is undone and the component disappears from the installed pool.

To navigate to the parent asset:

1. To navigate to the parent asset, click the newly attached component in the installed pool.




2. Click **Go to Parent Asset** to navigate to the parent asset to which the component is attached.



To undo an asset removal:


1. To undo remove, click the removed asset.



2. Click **Undo Remove**.




3. Click **Submit**.




The removal is undone and asset disappears from the deinstalled pool.

To move an asset back to service:

1. To move asset back to service, click **Asset** in **Out of Service**.



2. Click **Back to Service**.



3. Click **Submit**.

Are you sure you want to move asset back to service?

Submit Dismiss

Asset Operation: Back to Service

Activity Information: 200000021/525

Asset Information: Fan - Centrifugal, Badge Number 4053_4APRI_FAN, In Service @ 4A Primary Air Fan

The asset moves to the Existing pool.

Existing	3
Assets	3
4A Scanner Air Fan2	1
Fan - Centrifugal, Badge Number 4053_4APRI_FAN, In Service @ 4A Primary Air Fan 4A Primary Air Fan Asset	1
Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked MeterFlow 650 - in WW Plant 4 Asset	1

To replace an asset:

1. Click the asset that needs to be replaced.

Existing	3
Assets	3
Gearbox-Component-Tracked, 0000121526, GEAR-004, Gearbox, Tower Drivetrain SL-Storage, Storage Yard (out of service)Danger, 1038 Belden Ave NE Danger, Canton, OH, 44705, US, Time Zone: US/Pacific Component	1
Meter - Power - Tracked, MTPW-000000021, MTR021, Meter, Power, Tracked Template SL-Storage, Storage Yard (out of service)Danger, 1038 Belden Ave NE Danger, Canton, OH, 44705, US, Time Zone: US/Pacific Asset	1
Meter - Power - Tracked, MTPW-000000030, MTR030, Meter, Power, Tracked Template Capacitor 12 - Lake Substation Bus 1 Asset	1

2. Click **Replace**.

Asset Details

Asset Information
Meter - Power - Tracked MTPW-000000004 MTR004 Meter Power Tracked

Out of Service

Attach Component

Replace

3. Enter the badge number of the asset to be replaced with and click **Replace**.

Asset Operation: Replace

Activity Information: 200000021/525

Asset Information: Meter - Power - Tracked, MTPW-000000004, MTR004, Meter, Power, Tracked

Effective Date Time*: 05/08/22 07:17:00 PM

Select Asset

Badge Number: MTR0000

Replace Dismiss

The new asset moves to the **Installed** pool and the replaced asset moves to the **Deinstalled** pool.

Existing 2	
Asset 2	
Gearbox-Component-Tracked, 0000121326, GEAR-004, Gearbox, Tower Drivetrain VFD, Pump 9, RAS, PLTS Component	1
Meter - Power - Tracked, MTPW-000000030, MTR030, Meter, Power, Tracked Template Capacitor 12 - Lake Substation Bus 1 Asset	1
Installed 1	
Meter - Power - Tracked, MTPW-000000060, MTR060, Meter, Power, Tracked Template VFD, Pump 9, RAS, PLTS Asset Installed	1
Deinstalled 1	
Meter - Power - Tracked, MTPW-000000021, MTR021, Meter, Power, Tracked Template VFD, Pump 9, RAS, PLTS Replaced Asset	1

To replace the component:

1. Click the component to be replaced.

Existing 2	
Asset 2	
Gearbox-Component-Tracked, 0000121326, GEAR-004, Gearbox, Tower Drivetrain VFD, Pump 9, RAS, PLTS Component	1
Meter - Power - Tracked, MTPW-000000030, MTR030, Meter, Power, Tracked Template Capacitor 12 - Lake Substation Bus 1 Asset	1
Installed 1	
Meter - Power - Tracked, MTPW-000000060, MTR060, Meter, Power, Tracked Template VFD, Pump 9, RAS, PLTS Asset Installed	1
Deinstalled 1	
Meter - Power - Tracked, MTPW-000000021, MTR021, Meter, Power, Tracked Template VFD, Pump 9, RAS, PLTS Replaced Asset	1

2. Click **Replace**.

Asset/Equipment Details

Remove
Attach Component
Replace
Follow Up Work
New Work

Asset Details

3. Enter the badge number of the replacing component and click **Replace**.

Badge Number:

Replace
Dismiss

The replaced component moves to the deinstalled pool and the newly attached component moves to the installed pool.

Existing 1	
Meter - Power - Tracked, MTPW-000000030, MTR030, Meter, Power, Tracked Template Capacitor 12 - Lake Substation Bus 1 Asset	1
Installed 2	
Asset 2	
Gearbox-Component-Tracked, 0000121325, GEAR-003, Gearbox, Tower Drivetrain VFD, Pump 9, RAS, PLTS Component Installed	1
Meter - Power - Tracked, MTPW-000000060, MTR060, Meter, Power, Tracked Template VFD, Pump 9, RAS, PLTS Asset Installed	1
Deinstalled 2	
Asset 2	
Gearbox-Component-Tracked, 0000121326, GEAR-004, Gearbox, Tower Drivetrain VFD, Pump 9, RAS, PLTS Replaced Component	1
Meter - Power - Tracked, MTPW-000000021, MTR021, Meter, Power, Tracked Template VFD, Pump 9, RAS, PLTS Replaced Asset	1

To undo replace an asset:

1. Click **Installed Asset/Component**.

Installed 2	
Asset 2	
Gearbox-Component-Tracked, 0000121325, GEAR-003, Gearbox, Tower Drivetrain VFD, Pump 9, RAS, PLTS Component Installed	1
Meter - Power - Tracked, MTPW-000000060, MTR060, Meter, Power, Tracked Template VFD, Pump 9, RAS, PLTS Asset Installed	1
Deinstalled 2	
Asset 2	
Gearbox-Component-Tracked, 0000121326, GEAR-004, Gearbox, Tower Drivetrain VFD, Pump 9, RAS, PLTS Replaced Component	1
Meter - Power - Tracked, MTPW-000000021, MTR021, Meter, Power, Tracked Template VFD, Pump 9, RAS, PLTS Replaced Asset	1

2. Click **Undo Replace**.

Asset/Equipment Details

6:52 Adjust

Undo Replace Follow Up Work New Work

Asset Details

3. Click **Submit**.

Are you sure you want to undo replace?

Submit Dismiss

Asset Operation:

Undo Replace

Activity Information:

200000021/104

Main Asset Information:

Meter - Power - Tracked, MTPW-000000060, MTR060, Meter, Power, Tracked Template

The replaced asset moves back to existing pool.

Existing 2	
Asset 2	
Meter - Power - Tracked, MTPW-000000021, MTR021, Meter, Power, Tracked Template VFD, Pump 9, RAS, PLTS Asset	1
Meter - Power - Tracked, MTPW-000000030, MTR030, Meter, Power, Tracked Template Capacitor 12 - Lake Substation Bus 1 Asset	1
Installed 1	
Gearbox-Component-Tracked, 0000121325, GEAR-003, Gearbox, Tower Drivetrain VFD, Pump 9, RAS, PLTS Component Installed	1
Deinstalled 1	
Gearbox-Component-Tracked, 0000121326, GEAR-004, Gearbox, Tower Drivetrain VFD, Pump 9, RAS, PLTS Replaced Component	1

4. Repeat the above steps to undo replace for a component.

Pick Up and Follow Up Orders

Follow up orders are created for a new work related to the activity the crew is working on. Follow up work can include work orders and work requests.

To create a follow up order:

1. Navigate to the **Activity Details** page and click **Follow Up Work**.
2. Select the type of follow up work to be created.
3. Click **OK**.

Follow Up Work Order

Creating a follow up work order will result in the creation of field activity in Oracle Field Service and the related work order in Oracle Utilities Work and Asset Cloud Service solution.

To create a follow up work order for one of the assets related to activity or for a new asset:

1. Select an asset linked to the existing activity from the **Activity Asset** drop-down list.
2. To select a different asset, click **Query New Asset**. This will launch a search against the Oracle Utilities Work and Asset Cloud Service solution.
3. Enter the search criteria and click **Search**.
4. Select an asset for which the work order should be created.
5. Enter the details related to follow up work order and click **Create**.

A new activity is created in Oracle Field Service and a new related work order is created in the Oracle Utilities Work and Asset Cloud Service solution.

6. Click **OK**.

You can select the **Work It** option to assign a new activity to the crew.

Note that starting 23A release, the Planned Service History plugin is disabled for follow-up work order.

Follow Up Work Request

Creating a follow up work request will result in creation of a work request in the Oracle Utilities Work and Asset Cloud Service solution.

Note that a work request can be asset related and non-asset related.

Asset Related Work Request

Asset related work requests are created for assets.

You can specify one of the assets linked to the activity or query asset from the Oracle Utilities Work and Asset Cloud Service solution.

Enter the required information and click **Create**. A new work request will be created and sent to the Oracle Utilities Work and Asset Cloud Service solution.

Non-Asset Related Request

A non-asset related request is not linked to any asset and does not contain any asset information.

Work requests created by crew can be found on the crew **Requests History**.

Mobile Inventory Management

Mobile inventory management supports truck storerooms that contain assets and materials.

This section includes the following:


- [Overview](#)
- [Truck Materials Lifecycle Examples](#)
- [Truck Storeroom Admin Sync](#)
- [Truck Inventory Snapshot](#)
- [Assigning Truck to Crews](#)
- [Using Inventories for Activities](#)
- [Update Truck Inventories](#)

Overview

The Mobile Inventory Management functionality includes:


- Sending mobile storeroom content details from Oracle Utilities Work and Asset Cloud Service to Oracle Field Service
- Viewing the contents of a truck in a handheld device

- Recording the use of an item for an activity in a handheld device
- Updating content of Oracle Field Service truck for additional inventory
- Passing the use of items from Oracle Field Service to Oracle Utilities Work and Asset Cloud Service




Mobile storerooms (trucks) and their inventories are managed in Oracle Utilities Work and Asset Cloud Service. A truck in Oracle Field Service is linked to a Oracle Utilities Work and Asset Cloud Service mobile storeroom.

On request, the contents of the Oracle Utilities Work and Asset Cloud Service mobile storeroom is passed to Oracle Field Service and the contents of the linked Oracle Field Service truck is updated.




Loading the snapshot of the Oracle Utilities Work and Asset Cloud Service Mobile Storeroom linked to a truck should occur prior to or at the beginning of the relevant crew's shift. When a mobile storeroom snapshot is loaded into Oracle Field Service the contents of the linked Oracle Field Service truck is replaced with the details recorded in Oracle Utilities Work and Asset Cloud Service.


A crew can install assets and use material from their trucks for the activities they are working on. These truck inventory transitions are recorded in Oracle Field Service.



The content of the truck is the combination of the last mobile storeroom snapshot and the inventory transactions that have occurred since the last snapshot.




On activity completion and at the end of crew shift the use of assets and materials is sent to Oracle Utilities Work and Asset Management and the inventory of the mobile storeroom linked to the truck is updated.



During a crew's shift, the inventory of the crew's truck could get updated. For example, additional items required for an activity could be picked up from a storeroom. These updates will be recorded in Oracle Utilities Work and Asset Cloud Service. To update the truck's inventory in Oracle Field Service, the crew requests an update of the truck inventory.



The following diagram represents integration flows for mobile inventories movement:




Truck Materials Lifecycle Examples

This section describes various truck materials lifecycle examples.


Snapshot at the start of the shift



Items used in the field




Oracle Utilities Work and Asset Management updated with item use



Truck Storeroom Admin Sync


This integration process passes storeroom data from Oracle Utilities Work and Asset Cloud Service to Oracle Field Service for the storerooms with a storeroom type whose storeroom category is Truck.



The following figure shows the truck storerooms in Oracle Utilities Work and Asset Cloud Service.

	LOCATION	LOCATION TYPE	ADDRESS
1	Maintenance 1 Bucket Truck - Electric	Truck Storeroom	Maintenance 1 Bucket Truck
2	Maintenance 2 Bucket Truck - Electricity	Truck Storeroom	Maintenance 2 Bucket Truck
3	Maintenance 3 Crew Truck - Water	Truck Storeroom	Maintenance 3 Crew Truck
4	Maintenance 4 Crew Truck - Water	Truck Storeroom	Maintenance 4 Crew Truck

The following figure shows trucks created by the integration in Oracle Field Service.



Truck Inventory Snapshot

This process passes the inventory of truck storerooms from Oracle Utilities Work and Asset Cloud Service to Oracle Field Service updating the inventory of the Oracle Field

Service truck that is linked to the Oracle Utilities Work and Asset Cloud Service storeroom.

Attention! This process will delete the content of the Oracle Field Service truck and replace it with the content of the linked storeroom in Oracle Utilities Work and Asset Cloud Service. Any unprocessed inventory transaction in Oracle Field Service that is used in assets or materials will be lost.


The Truck Inventory Snapshot can be performed using one of the following three options:

- **Option 1: On Route Activation**
 - On route activation of a crew or individual, Oracle Field Service checks if there are any trucks associated with that crew or individual. If there are any, it initiates the truck inventory snapshot process.
- **Option 2: Scheduled Truck Inventory Snapshot**
 - A batch scheduled in Oracle Integration Cloud to run at a specific time initiates the truck inventory snapshot process for all truck storerooms.
- **Option 3: On Request**
 - The truck inventory snapshot process can be initiated by a dispatcher from the Truck Resource Inventory. This option can be used for exceptional situations.


Assigning Truck to Crews

A truck is assigned to a crew or individual. Once a truck is assigned, its contents are available to be used for those activities the crew or individual is working on.

In the following example, two trucks have been assigned to South Crew.



The inventory of these trucks is available to the crew member in the mobile application.



Using Inventories for Activities

You can see truck inventories on the activity's **Asset** tab.

There are two types of items in a truck's inventory:

- [Assets](#)
- [Materials](#)

Assets

You can install an asset in a truck's inventory at a location associated with the activity being worked on.

1. Select the asset you want to install and click **Install Asset**.
2. If there is more than one location associated with the activity, select the location, and if necessary, adjust the installation date and time.

An asset will be installed at the location.

Materials

You can report material that has been used for an activity.

1. Select the item you want to use and click **Use Item**.
2. Specify the number of items used and click **Use**.

The used items will appear in the **Installed** section.

Update Truck Inventories

During a crew's shift, the contents of a truck can be changed and the changes recorded in Oracle Utilities Work and Asset Cloud Service.

Example: Items can be added to a truck from a standard storeroom. The inventory can be changed. In this situation, a truck inventory update should be requested from Oracle Field Service.

On receipt of a truck inventory update request, Oracle Utilities Work and Asset Cloud Service returns the inventory changes to the truck's storeroom contents since the last snapshot. Changes to the Oracle Utilities Work and Asset Cloud Service content resulting from inventory transactions passed from Oracle Field Service are excluded.

To trigger a truck inventory update, click **Update Truck Inventory** on the **Asset** tab.

To update the inventory when transfer in or transfer out happens from the truck, navigate to crew's **Assets/Equipment > Update Truck Inventory**. Adding a new truck inventory is not included in this scenario. In Oracle Field Service, the **lastSyncDateTime** field keeps track of the date when the previous inventory synchronization happened. All the inventory transfer in or transfer out happens on or after this date when the Update Truck Inventory option is triggered. If no transfers happen, there will not be any updates to the truck.

To update the truck inventory that is newly added or transferred, in Oracle Field Service, navigate to **Admin > Resource Info > Sync Truck Inventories**. However, this data is not updated on the Oracle Field Service mobile screen.

Note: Before using Update Truck Inventory or Sync Truck Inventories options, make sure that the truck's inventory in Oracle Field Service is in synchronization with Oracle Utilities Work and Asset Cloud Service. To get the applications in synchronization, trigger the Oracle Utilities WACS OFSC Schedule Storeroom Sync flow in Oracle Integration Cloud.

Chapter 5

Customizations

Adding new properties according to the requirement and customizations help customers to enhance the functionality of the integration and increase the usability. The customizations are done in Oracle Integration Cloud, Oracle Field Service, and Oracle Utilities Customer Cloud Service depending on the fields, elements, or properties to be added and whether they are available.

This chapter focuses on a few cases about customizations.


- [Adding New Fields to Field Activity](#)
- [User Defined Fields](#)
- [Adding Custom Business Objects](#)
- [Plugins Rendering Data](#)
- [Validation for Completion](#)

Adding New Fields to Field Activity

This section provides the steps to add a new field to the field activity already available but not present in the field activity.

Oracle Field Service Configurations

1. Login to Oracle Field Service.
2. Navigate to **Configuration > Resources, Activities, Inventories > Properties**.



3. Click **Add New**. Enter the **Property name** and **Property Label**.
4. Select the entity, type of GUI, and add the enumeration values “customprop1” and “customprop2”.

 The screenshot shows the 'Add New Property' form. It has two main sections: 'General settings' and 'Type and advanced settings'.

 In 'General settings':

- 'Entity' is set to 'Activity'.
- 'Label' is 'test_customproperty'.
- 'Name: English' is 'Test Custom Property'.
- 'Name: French (European)' is empty.
- 'Name: Portuguese (Brazil)' is empty.
- 'Name: Spanish LA' is empty.
- 'Name: Chinese (Traditional)' is empty.


 In 'Type and advanced settings':

- 'Property type' is 'Enumeration'.
- 'GUI' is 'Combobox'.
- 'Clone property data on Reopen or Prewrite' is unchecked.

 Below these is the 'Enumeration values' section, which contains a table with columns: ID, Value, Status, and Actions. The table is currently empty, with a message 'No data to display.' and an 'Add' button.

5. Navigate to **Configuration > Users, Security, Integrations > User Types** and select the required user type.

6. Navigate to the screen configurations for the select user type and open the **Edit/View** activity section.



7. Add a new element by dragging and dropping a new 'Input' from the **Add New Element** section.
8. Map the element to the **Test Custom Property**. Save this configuration after mapping the field.

Oracle Utilities Work and Asset Cloud Service Configurations

1. Login to Oracle Utilities Work and Asset Cloud Service.
2. To configure with a new schema element:
 - a. Navigate to the W1-ActivityComplInboundComm business object.
 - b. Identify the data area to add the new schema element.

Example: To make changes to the **Completion Event Details** section, the data area to be changed is the custom data area created for Oracle Field Service.

- c. Extend the data area. Add the completion event details data area in the **Extended Data Area** field.

d. The new schema element is displayed in the business object schema.

```
<creationDateTime suppress="true" required="true" dataType="dateTime" default="currentDate">
<statusDateTime suppress="true" dataType="dateTime" mapField="STATUS_UPD_OTTM"/>
<version suppress="true" dataType="number" mapField="VERSION"/>
<exceptionInformation type="group" mapXML="BO_DATA_AREA">
  <messageCategory suppress="true" mdField="MESSAGE_CAT_NBR" dataType="number"/>
  <messageNumber suppress="true" mdField="MESSAGE_NBR" dataType="number"/>
  <longDescription suppress="true" mdField="DESCRLONG"/>
  <expandedMessage suppress="input" mdField="ACT_ERROR_MESSAGE"/>
  <messageParameters suppress="true" type="list">
    <parameterSequence mdField="PARAM_SEQ" dataType="number" isPrimeKey="true"/>
    <messageParameterType mdField="MSG_PARAM_TYP_FLG" dataType="lookup" lookup="MS"/>
    <messageParameterValue mdField="T1_MSG_PARAM_VLONG"/>
  </messageParameters>
</exceptionInformation>
<accessControl type="group">
  <owningAccessGroup href="T1-ACCGP" mapField="OWNING_ACCESS_GRP_CD"/>
</accessControl>
<eventInformation type="group">
  <completionDateTime dataType="dateTime" mapField="V1_EVT_OTTM"/>
  <comments mdField="COMMENTS" mapXML="BO_DATA_AREA"/>
  <crewName mdField="CREW_NAME" mapXML="BO_DATA_AREA"/>
  <custom mdField="CM_NOTES" mapXML="BO_DATA_AREA"/>
</eventInformation>
```

User Defined Fields

In Oracle Utilities Work and Asset Cloud Service, the Work Activity schema has been extended to include user defined fields. It will allow implementers to pass additional data to Oracle Field Service and other solutions without a need to change the integration layer.

Following is the list of UDF properties available in Oracle Field Service:

- wam_activity_UDF1 to wam_activity_UDF10
- wam_activity_location_UDF1 to wam_activity_location_UDF10
- wam_asset_UDF1 to wam_asset_UDF10
- wam_asset_location_UDF1 to wam_asset_location_UDF10

Currently, Process Activity and Asset Query integrations support sending the UDF data from Oracle Utilities Work and Asset Cloud Service to Oracle Field Service.

When UDF values are populated in Oracle Utilities Work and Asset Cloud Service, they are mapped to UDF/custom properties defined in Oracle Field Service at Activity, Activity Location, Asset, and Asset Location level accordingly.

Adding Custom Business Objects

After a custom business object for a service history is added in Oracle Utilities Work and Asset Cloud Service, the information is available to Service History plugin along with all other service histories as part of “wam_asset_valid_service_history_types” property.

In Oracle Field Service the new business object value is added as an enumeration value in “wam_service_history_bo” property.

If the new business object belongs to one of the predefined service history categories of Questionnaire, Inspection, Failure, Downtime and General, it is defined as such in the property.

Example: A custom business object “CM_Downtime” is entered in the “wam_service_history_bo” property as shown below. The service history plugin will automatically handle the new business object.

Modify Property

General settings

Entry: Activity

Label: wam_service_history_bo

Name: English: Service History BO

Name: French (European):

Name: Portuguese (Brazil):

Name: Spanish: LA

Name: Chinese (Traditional):

Property hint

Type and advanced settings

Property type: Enumeration

UI: Combobox

☐ Clone property data on Reopen or Prework

Enumeration values

ID	Value	Status
W1-AssetDowntime	Downtime	Active
W1-FailureServiceHistory	Failure	Active
W1-InspectionDeficiency	Inspection	Active
W1-InspectionGenWeighted	Inspection	Active

Add

If the new business object entered does not fall into any of the predefined service history categories, after the “wam_service_history_bo” property is updated, the service history plugin javascript should be updated to handle the new service history category. Create a new XSL that needed for the UI of the new service history category to be added.

Plugins Rendering Data

This section explains how each plugin renders the data.

Measurements

Valid measurement types received from Oracle Utilities Work and Asset Cloud Service are assigned to “wam_valid_measurement_types” property and are obtained in runtime as XML string and displayed in plugin.

The individualMeasurementType-to-form.xml and individualMeasurementTypeEdit-to-form.xml are used to style the UI forms to add and update measurement information.

The measurement information is consolidated into “wam_measurements_output” property and made available for validateCompletion plugin.

Measurement reason types (wam_measurement_meter_reason, wam_measurement_gauge_reason) are populated based on the measurement type selected.

Resource Usage

resourceUsage-to-form.xsl provides the summary of the **Resource Usage Details** page from where crew can add timesheets, equipment, and other resource usage. It also displays the resource usage details entered.

individualTimeUsage-to-form.xsl used to display add/update time sheet screens whereas crewTimeUsage-to-form.xsl is used to enter and update individual and crew timesheets.

individualEquipmentUsage-to-form.xsl and individualOtherUsage-to-form.xsl are used to enter equipment and other resource usages.

Upon completion of resource usage which calls Oracle Integration Cloud (Oracle Utilities OFS WACS Resource Usage Details integration flow) and update the details in Oracle Utilities Work and Asset Cloud Service.

Service History

The following XSL are applied to render the UI:

- serviceHistoryTypes-to-form.xsl to show Service History List and the Entered Service histories
- downtime-to-form.xsl for Downtime Service History form
- failure-to-form.xsl for Failure Service History form
- questionnaire-to-form.xsl for Questionnaire and Inspection Service History form
- sh-to-form.xsl for General Service History form
- entered-sht-count.xsl is used to count the entered service histories per each service history type
- shAttachment-to-form.xsl to enter attachments

For asset level service histories: The valid service histories are displayed based on the service histories hold by “wam_asset_valid_service_history_types” property.

For activity level service histories: The valid service histories are displayed based on the service histories held by “wam_valid_service_history_types” property.

The asset failure information is displayed based on the values holds in “wam_failure_info” property.

The asset downtime reason is displayed based on the values holds in “wam_downtime_reason” property.

The allowed MIME types for an attachment can be defined under **Allowed MIME types** of the “wam_upload_attachment_1” property. Also file size limit can be defined under this property.

The following BO categories are supported. (Questionnaire and Inspection are handled similarly):

- Questionnaire
- Inspection
- Failure
- Downtime
- General

For activity level service histories, failure service history is not supported.

Refer to [Adding Custom Business Objects](#) for more information.

If the completion message for service histories is greater than 655360, the message is split into multiple `wam_service_history_output(i)` for asset level and `wam_planned_service_history_output(i)` for activity level service histories respectively where “i” values ranges from 1 to 20 (size upto 640KB) properties and are made available for the `validateCompletion` plugin.

Note: For any service history type, number of attachments at asset level and activity level together combined must be less than or equal to 15. An error will be generated if the user tries to enter an attachment more than 15 times for that respective service history.

Asset Component Install Exchange Undo

The following XSL are applied to render the UI:

- `assetQuery-to-form.xml` to show Install, Attach, Replace, and Undo operation screens.
- Every operation will have “`wam_asset_effective_date_time`” property on the screen defaulted to **Current Date/Time** which can be modified by the user.
- Clicking **Search and Add** or **Search and Replace** for Install, Attach, and Replace operations calls Oracle Integration Cloud (Oracle Utilities OFS WACS Asset Query integration flow). If the response succeeds, assets details are received and the operation is performed successfully. If the response fails, a valid error message is displayed on the screen.

Validate Completion

This plugin is used to validate and construct the final completion message obtained from individual plugins that is sent out by Oracle Field Service to Oracle Utilities Work and Asset Cloud Service. Click **Complete**.

The plugin validates to check if there are any pending service histories and all the required service histories are completed.

If the validations are not successful, click **OK** and fix the issue. If the validations are successful, the completion message is written to a temporary file and navigated to the **End Activity** screen. Click **Submit** to send the completion message to Oracle Utilities Work and Asset Cloud Service.

The plugin populates “participation” node in the completion message with either “W1AW” or “W1AS” based on if the “Asset worked” was selected (checkbox selected) or not.

Lock Unlock

The index.html page provides the summary of **Lock/Unlock** status from where user can Lock or Unlock Activity.

Only on locking an activity crew can start the operations such as asset install, replace, remove, adding timesheet, equipment, and other details. A crew member can lock the activity without starting it. Once activity is locked by any crew it can be unlocked by himself or from dispatch console.

Note:

- The Lock Unlock functionality can be enabled/disabled by setting the lock.functionality property in the WAMOFSC_ConfigProps lookup to “true” or “false” in Oracle Integration Cloud. While creating the work activity, if lock.functionality is set to “true”, then crew can start the activity and perform operations only after locking the activity.
- If it is set to “false”, the **Lock** button in the Oracle Field Service is disabled. So, a crew can perform all the operations without locking the activity.
- When the lock.functionality property is set to “true”, if the activity is assigned to a supervisor and locked by the supervisor, assisting resources cannot perform any operation on this activity.
- When the lock.functionality property is set to “true” and supervisor does not lock the activity, the assisting resource can still modify the resource usage plugin. Supervisors should lock the activity to restrict the assistants to perform any operation.
- When the lock.functionality is set to “false”, assisting resource will have access to supervisor's activity. The assisting resource can perform all the operations, such as asset install, replace, remove, adding timesheet, equipment and other details, adding service histories etc...

Pick Up

- assetQuery-to-form.xsl displays the **Asset Query** page to query assets from Oracle Utilities Work and Asset Cloud Service using the asset badge number or location.
- pickupWork-to-form.xsl provides crew member with a drop-down option to choose the level from work order, work request-asset related, or work request-non-asset related.
- workOrderRequest-to-form.xsl displays a form where crew member can add details for work order or work request created.
- Clicking **Query New Asset** allows the crew to navigate to the **Asset Query** page which calls the Oracle Integration Cloud flow (Oracle Utilities OFS WACS Asset Query). The crew member can click **Clear Selection** to clear the selected asset.

Materials

- materials-to-form.xsl displays a drop-down containing list of trucks assisting the crew to update the truck inventories of selected truck.

- moveMaterials-to-activity-form.xsl displays **Use/Undo Use Item**, **Install/Undo Install Asset**, and **Attach/Undo Attach** component pages from the truck inventories.
- Click **Sync Truck Inventories** for an initial sync of truck inventories that can be performed from the dispatch console.

Asset Attribute

Asset Attributes List received from Oracle Utilities Work and Asset Cloud Service are assigned to “wam_asset_attribute_list” property and are obtained in runtime as XML string and displayed in Asset Attribute plugin.

The following XSL are applied to render the UI:

- assetAttribute-to-form.xsl to display Asset Attribute List with valid values.
- Properties “wam_map_assetAttribute”, “wam_map_attribute_validValue” and “wam_map_validValue_description” are used to fetch the attribute description and valid values for predefined characteristic types synced during Admin Sync flow.

Asset History

- assetHistory-to-form.xsl displays the asset history details received from Oracle Utilities Work and Asset Cloud Service. The details include service histories, measurements, and previous activities.
- Properties “wam_service_history_category” and “wam_service class” are used to fetch the **Service History Category Description** and **Service Class Description**. These are synchronized during the Admin Sync flow. **Measurement Status** and **Activity Status** values are hardcoded in the “wam_measurement_status” and “wam_activity_status” properties.

Validation for Completion

Validation Rules

- Basic validation is to ensure that the activity has all the necessary information to be completed.
- All pending service histories must be completed when completing the activity (mandatory).
- Required service histories must be entered for worked assets.
- For each asset that worked, loop through the list of required service history types defined on the activity.
- Find all service histories in the list of activity service histories that its service history type = current service history type being processed and either asset ID = empty or equal current asset being processed.
- If not found, issue an error that “A service history of type %1 is missing for asset %2”.

Chapter 6

Hosting Plug-Ins in OFS

Plug-ins can be hosted within Oracle Field Service or externally.

Oracle Field Service has plugins that can be hosted within Oracle Field Service.

The steps to host a plug-in within Oracle Field Service is documented in <https://docs.oracle.com/en/cloud/saas/field-service/index.html>.

The plugins can be hosted externally on:

- Any webserver (example: Tomcat) running on a virtual machine either on-premises or on cloud.
- It can be stored in Object Storage on a cloud instance by uploading the files in a public bucket.

Additionally, if the plugins are hosted externally:

1. Navigate to **Configuration > Application > Additional Resources**.
2. Select **Allow Cross-origin resource sharing (CORS)** from the available web domains and provide the domain of the server on which plugins are hosted.

Hosting Files on a Web Server

Plugins can be hosted on a webserver running on a virtual machine either on-premises or on cloud.

The mobile device or browser needs to be able to reach and communicate with the server hosting the plugin files.

Please refer to the documentation of the webserver of choice on how setup and host the static content. The unzipped files of the plugin is then hosted on the webserver. The path to the index.html or the directory containing the index.html is configured in the URL field of the plugin screen as defined in <https://docs.oracle.com/en/cloud/saas/field-service/index.html>.

The externally hosted plugin can be secured and Oracle Field Service supports authentication mechanism as defined in <https://docs.oracle.com/en/cloud/saas/field-service/index.html#Authentication-25E75B9D>.

Storing Files on Object Storage

Before storing files in Object Storage make sure that the basic administration tasks in Oracle Cloud Infrastructure related to Object Storage are completed properly, and that the compartments and buckets where the plugin files are stored are set up.

For more information on Oracle Cloud Object Storage setup for Oracle Utilities Cloud Services, refer to the latest *Oracle Utilities Cloud Services Object Storage Setup Guide* at https://docs.oracle.com/cd/F35460_01/PDF/UGBU_Cloud_Services_Object_Storage_Setup_20C.pdf.

Using Public Bucket

The unzipped plugin files can be uploaded into a public bucket in which case the files are not protected and is open to public. The URL to index.html in the public bucket is configured in URL field in Oracle Field Service.

Chapter 7

Construction Work Management Support

Construction work activities have one or more construction locations, where a construction location can be either be an asset location or a work location. Each construction location can have one or more compatible units. Within Oracle Utilities Work and Asset Cloud Service/Oracle Utilities Work and Asset Management a compatible unit can result in the creation of a location, and the creation, installation, or removal of an asset.

- [Pre-requisites](#)
- [Construction Work Activity Operations](#)
- [Interim Completion of Construction Work Activity](#)

Pre-requisites

To support the construction work activities, create the following inventory types in Oracle Field Service:

- [Construction Tasks](#)
- [Finished Tasks](#)

Construction Tasks

To create the construction_tasks inventory type:

1. Login to Oracle Field Service.
2. Navigate to **Configuration > Resources, Activities, Inventories > Inventory Types**.
3. Click **Add Inventory Type**.

4. Enter “construction_tasks” in the **Label** field.
5. Select “Item Type” from the **Model Property** drop-down list.
6. Enter the name in the **Name: English** field. Note that this is a mandatory field.
7. Click **Add**.

Finished Tasks

To create the finished_tasks inventory type:

1. Login to Oracle Field Service.
2. Navigate to **Configuration > Resources, Activities, Inventories > Inventory Types**.

3. Click **Add Inventory**.

4. Enter “finished_tasks” in the **Label** field.
5. Select “Item Type” from the **Model Property** drop-down list.
6. Enter the name in the **Name: English** field. Note that this is a mandatory field.

Construction Work Activity Operations

The following operations are supported in the construction work activities:

- [Install/Undo Install Tracked Asset](#)
- [Install/Undo Install Non Tracked Asset](#)
- [Support for Controls](#)
- [Remove Asset](#)
- [Install No Asset](#)
- [Remove No Asset](#)
- [Update Quantity](#)

Install/Undo Install Tracked Asset


Tracked assets are created in Oracle Utilities Work and Asset Cloud Service and they can be either Truck assets or Issued assets. Issued assets are present in regular storeroom. The user must request to install the same asset in Oracle Field Service. Truck assets are present in truck storeroom and they are synchronized to Oracle Field Service by **Oracle Utilities WACS OFSC Schedule Storeroom Sync** in Oracle Integration Cloud by scheduling this flow. Alternatively, you can click **Update Truck Inventory** available on the **Assets/Equipment** page in Oracle Field Service. Click **Install Asset** to view the assets in the **Issued Asset** and **Truck Asset** drop-down lists.


Construction Tasks 4
Pole at 2345 Main Street COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install Install Asset
Pole at 2345 Main Street INSPP1PH / Insulator, Line - 2.4 KV Porcelain, 7.2 KV Rated and Pole Top Pin Single Phase / Install Update Quantity
Pole at 2345 Main Street PW403 / Pole - Wood, 40 Foot, Class 3 / Install Pole - Wood, Badge Number 1505_Non_Tracked_1, Planned @ Pole at 2345 Main Street Install Asset
Pole at 2345 Main Street REMOVE RT / REMOVE RT ASSET / Remove Remove Asset

Install Issued Asset

The field worker can install the issued asset on the location. The location type and asset type should be same. Else, the assets will not be shown in the **Issued Asset** drop-down list.

Pole at 2345 Main Street
COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install
[Install Asset](#)

Asset/Equipment Details		Install Asset	Follow Up Work	...
Pole at 2345 Main Street - COMPT UNIT RT 003 / COMPT UNIT RT 003 / InstallInstall Asset				
				
Location				
Location Information				
Pole at 2345 Main Street				
Service Area				
North				
Construction Task				
Compatible Unit Information				
COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install				

Asset Operation:	Install Asset
Activity Information:	230000071/24
Location Information:	Pole at 2345 Main Street
Compatible Unit Information:	COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install
Effective Date Time*: 08/14/23 04:22:00 PM 	
Issued Assets:	<div> <div></div> <div> 1505_Issued_CWA_1, Gearbox - Tracked 1505_Issued_CWA_2, Gearbox - Tracked </div> </div>
<div>Install</div> <div>Dismiss</div>	

The real time asset verification call will go to Oracle Utilities Work and Asset Cloud Service. After the successful response, the asset will be moved to Install pool in Oracle Field Service.

Installed 2

Assets 2

Gearbox - Tracked, Pending Disposition, BN: 1505_Issued_CWA_1, SN: 1505_Issued_CWA_1
Pole at 2345 Main Street [Asset Installed](#)

Pole - Wood, Badge Number 1505_Non_Tracked_1, Planned @ Pole at 2345 Main Street
Pole at 2345 Main Street [Asset Installed](#)

Install Truck Asset

The field worker can install a truck asset on the location. The compatible unit asset type and asset type should be same> Else, the assets will not be shown in the **Asset** drop-down list. Select the truck from the **Truck** drop-down list to view the assets in that truck.

Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific
COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install
[Install Asset](#)

Asset/Equipment Details

Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific - COMPT UNIT RT 003 / COMPT U...

<p>Location</p> <p>Location Information Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific</p> <p>Construction Task</p> <p>Compatible Unit Information COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install</p>
--

Asset Operation:	Install Asset
Activity Information:	230000150/288
Location Information:	Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific
Compatible Unit Information:	COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install

Effective Date Time*:	11/01/24 10:53:00 AM
-----------------------	----------------------

Issued Assets:	<input type="text"/>
----------------	----------------------

Truck:	Truck_RB
Assets:	<input type="text"/>

Badge Number:	<input type="text"/>
---------------	----------------------

The asset will be removed from respective Truck inventory pool and moved to Install pool in Oracle Field Service.

📦 Installed 1

Gearbox - Tracked, In Store, BN: AssetBN12022, SN: AssetSN12022
 Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific [Asset Installed](#)

The field worker can install the truck asset from the inventory itself using the Materials plugin. Navigate to the respective asset in truck inventory pool. Click **Install Asset** to view the **Location** drop-down list containing unique combination of location and compatible unit.

Asset/Equipment Details STOCK_ITEM_1202_1 (STOCK_ITEM_1202_1) - AssetBN12022	Install Asset Follow Up Work New Work Book (create) activity
--	--

Item Details Stock Item Code STOCK_ITEM_1202_1 Stock Item Description STOCK_ITEM_1202_1 - Truck_RB, (STOCK_ITEM_1202_1), Inventory Tracked Badge Number AssetBN12022 Quantity 1 asset Unit of Measurement Gallon

Action:	Install Asset
Activity Information:	230000150/288
Asset Information:	STOCK_ITEM_1202_1 - Truck_RB, (STOCK_ITEM_1202_1), Inventory Tracked
Badge Number:	AssetBN12022

Effective Date Time*:	11/01/24 11:50:00 AM
Location:	Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install

Install Dismiss

After successful verification, the inventory quantity will be reduced to '0', and asset will be moved to Install pool in Oracle Field Service.

Installed 1

Gearbox - Tracked, In Store, BN: AssetBN12022, SN: AssetSN12022
 Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific [Asset Installed](#)

Install a Non-Issued Asset

The field worker can install a non-issued tracked asset on the location using the **Badge Number** field. The real-time asset verification call is sent to Oracle Utilities Work and Asset Cloud Service. After successful response, asset type of the asset will be validated to match the asset type of the compatible unit. Then, the asset will be moved to Install pool in Oracle Field Service.

Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific
 COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install
[Install Asset](#)

↑ Assets/Equipment

Asset/Equipment Details

Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific - COMPT UNIT RT 003 / COMPT U...

<p>Location</p> <p>Location Information</p> <p>Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific</p>
<p>Construction Task</p> <p>Compatible Unit Information</p> <p>COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install</p>

Asset Operation:

Install Asset

Activity Information:

230000150/288

Location Information:

Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific

Compatible Unit Information:

COMPT UNIT RT 003 / COMPT UNIT RT 003 / Install

Effective Date Time*:

11/01/24 11:24:00 AM

Issued Assets:

Truck:

Assets:

Badge Number:

AssetBN011102

Install

Dismiss

Installed 1

Gearbox - Tracked, In Store, BN: AssetBN011102, SN: AssetBN011102
Linear, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific [Asset Installed](#)

Undo Install Tracked Asset

The field worker can undo an asset installation from the Install pool. The asset that is undone will be put into the existing pool if it is an issued asset. Else, it will be put into the respective truck inventory pool in Oracle Field Service.

Asset/Equipment Details

Gearbox - Tracked, Pending Disposition, BN: 1505_Issused_CWA_2, SN: 1505_Issused_CWA_2 - Pole at 2345 Main StreetAssetInst...

Asset Details

Asset Information

Gearbox - Tracked, Pending Disposition, BN: 1505_Issused_CWA_2, SN: 1505_Issused_CWA_2

Badge Number

1505_Issused_CWA_2

Asset Description

Gallons Flow

Undo Install Asset

Follow Up Work

New Work

Are you sure you want to undo install?

Ok

Dismiss

Asset Operation:	Undo Install
Activity Information:	230000071/24
Asset Information:	Gearbox - Tracked, Pending Disposition, BN: 1505_Issued_CWA_2, SN: 1505_Issued_CWA_2

Install/Undo Install Non Tracked Asset

Non tracked assets are created in the Oracle Utilities Work and Asset Cloud Service application storeroom and they are installed in Oracle Field Service. Select the asset from the **Issued Asset** drop-down list on the installation screen.

Install Non Tracked Asset

A field worker can install the non tracked asset on the location. The field worker has provision to provide the badge number, serial number, and asset number. The real time call will be sent to Oracle Utilities Work and Asset Cloud Service. After successful response, the asset will be put into the Install pool.

Pole at 2345 Main Street
PW403 / Pole - Wood, 40 Foot, Class 3 / Install
Pole - Wood, Badge Number 1505_Non_Tracked_1, Planned @ Pole at 2345 Main Street [Install Asset](#)

Asset/Equipment Details

Pole at 2345 Main Street - PW403 / Pole - Wood, 40 Foot, Class 3 / Install - Pole - Wood, Badge Number 1505_Non_Tracked_1, Pl...

Asset Details

Asset Information

Pole - Wood, Badge Number 1505_Non_Tracked_1, Planned @ Pole at 2345 Main Street

Badge Number

1505_Non_Tracked_1

Asset Description

Pole - Wood

Serial Number

1505_Non_Tracked_1


Install Asset


Follow Up Work


New Work


Construction Work Management Support 7 - 9
Oracle Field Service Configurations for Oracle Work and Asset Cloud Service Integration to Oracle Field Service Setup Guide

Asset Operation:	Install Asset
Activity Information:	230000071/24
Asset Information:	Pole - Wood, Badge Number 1505_Non_Tracked_1, Planned @ Pole at 2345 Main Street
Location Information:	Pole at 2345 Main Street
Compatible Unit Information:	PW403 / Pole - Wood, 40 Foot, Class 3 / Install

Effective Date Time*:	08/14/23 04:25:00 PM	
-----------------------	----------------------	---

Badge Number:	1505_Non_Tracked_1	
Serial Number:	<input type="text"/>	
Asset Number:	<input type="text"/>	

 **Installed 2**

 **Assets 2**


Gearbox - Tracked, Pending Disposition, BN: 1505_Issued_CWA_1, SN: 1505_Issued_CWA_1
Pole at 2345 Main Street [Asset Installed](#)

Pole - Wood, Badge Number 1505_Non_Tracked_1, Planned @ Pole at 2345 Main Street
Pole at 2345 Main Street [Asset Installed](#)

Undo Install Non Tracked Asset

The field worker can undo an asset installation from the Install pool. The asset that is undone will be put into the existing pool in Oracle Field Service.

Asset/Equipment Details
Pole - Wood, Badge Number 1505_Non_Tracked_1, Planned @ Pole at 2345 Main Street - Pole at 2345 Main StreetAssetInstalled



Asset Details

Asset Information
Pole - Wood, Badge Number 1505_Non_Tracked_1, Planned @ Pole at 2345 Main Street

Badge Number
1505_Non_Tracked_1

Asset Description
Gallons Flow

[Undo Install Asset](#)
[Follow Up Work](#)
[New Work](#)

Are you sure you want to undo install?

OkDismiss

Asset Operation:	Undo Install
Activity Information:	230000071/24
Asset Information:	Pole - Wood, Badge Number 1505_Non_Tracked_1, Planned @ Pole at 2345 Main Street

Support for Controls

Use the asset, badge, and serial number controls passed from Oracle Utilities Work and Asset Cloud Service when installing a planned asset in Oracle Field Service.

The **Badge Number**, **Serial Number**, and **Asset Number** fields should be displayed and validated based on the value of the corresponding control element:

- **W1NP (Not Present):** Should not be included on the screen.
- **W1DO (Display Only):** Should be present but display only.
- **W1OP (Optional):** Should be present and the value able to be changed. When the entered details are validated. If the value is blank, no error should occur.
- **W1RQ (Required):** Should be present and the value able to be changed. When the entered details are validated. If the value is blank, an error should occur.

Asset Operation:	Install Asset
Activity Information:	220000040/1
Location Information:	Pole at 2345 Main Street
Compatible Unit Information:	2X1/OTRIPLEX / Double run of 1/0 Triplex / Install
Asset Information:	2X Pole

Effective Date Time*:	22/02/2023 18:33:10
-----------------------	---------------------

Asset Details

Badge Number:	ABC001178
Serial Number:	870421470481A
Asset Number:	

Remove Asset

The field worker can remove an asset from the location which is already installed. When removing an asset as part of a construction work activity, limit the assets that can be selected for removal to those at the asset location.

The asset to be removed should be selected from the assets in the installedAsset list where:

- The asset type in the installedAsset list matches the compatible unit's asset type; and
- The asset has not already been removed (and so in the Deinstalled group); and
- The node identifier in the installedAsset list matches the location's node identifier.

The removed asset will be moved into the Deinstall pool in Oracle Field Service.

Pole at 2345 Main Street REMOVE RT / REMOVE RT ASSET / Remove Remove Asset
--

Asset/Equipment Details

Pole at 2345 Main Street - REMOVE RT / REMOVE RT ASSET / RemoveRemove Asset

Remove Follow Up Work New Work

Location

Location Information
Pole at 2345 Main Street


Service Area
North

Construction Task

Compatible Unit Information
REMOVE RT / REMOVE RT ASSET / Remove


Construction Task Hierarchy
RT REMOVE JUL 10 / RT REMOVE JUL 10 / Remove
• REMOVE RT / REMOVE RT ASSET / Remove

Asset Operation:	Remove Asset
Activity Information:	230000071/24
Location Information:	Pole at 2345 Main Street
Compatible Unit Information:	REMOVE RT / REMOVE RT ASSET / Remove

Effective Date Time*: 

Installed Assets:

Gearbox - Tracked, Installed, BN: Const_1505_2002_1, SN: Const_1505_2002_1



Deinstalled 1

Pole at 2345 Main Street [Removed Asset](#)

Install No Asset

This construction task does not require any action from the field worker. It is displayed in the **Finished Tasks** group.

Pole - Wood, Badge Number , In Service @ 2183 N High S Residence PW403 / Pole - Wood, 40 Foot, Class 3 / Install 2183 N High S Residence [Asset No Asset Install](#)

Remove No Asset

This construction task does not require any action from the field worker. It is displayed in the **Finished Tasks** group.

Gearbox - Tracked, Pending Disposition, BN: FR DEMO BN003, SN: FR DEMO SN003 REMOVE RT / REMOVE RT ASSET / Remove 2183 N High S Residence [Asset No Asset Removal](#)

Update Quantity

Field worker can update any extra quantity of equipment that is required apart from the planned quantity and quantity completed is divided into two fields, Quantity Completed prior to this shift (sum of previous segments quantity for multiday activities and 0 for normal activity) and Quantity completed in this shift.

Location

Location Information

Above Ground / Plant, Pole for wood 1505, Opp Hitex Charminar, Hyd, FL, 50070, US, Time Zone: US/Pacific

Construction Task

Compatible Unit Information

INSPP1PH / Insulator, Line - 2.4 KV Porcelain, 7.2 KV Rated and Pole Top Pin Single Phase / Install

Quantity Planned for the Activity

1

Quantity Completed Prior to this Shift

0

Update Quantity

Compatible Unit Information

INSPP1PH / Insulator, Line - 2.4 KV Porcelain, 7.2 KV Rated and Pole Top Pin Single Phase / Install

Quantity Planned for the Activity

1

Quantity Completed Prior to this Shift

0

Quantity Completed in this Shift

12



Dismiss

Submit


Interim Completion of Construction Work Activity

Interim completion will allow the details of installation, removal, service histories, and measurements to be sent from Oracle Field Service to Oracle Utilities Work and Asset Cloud Service when an individual segment is completed. In this release, it is applicable to Construction Work Activities.

1. Planned Service Histories and Service Histories that have been sent to WACS/WAM in previous segments are available in View mode only. They cannot be edited.

Activity Information:

230000150/262 - WACS-OFS 24B FR ACTIVITY-2


Planned Service History List

General SH

Required: Yes Entered: 2

Downtime

Asset Level

Entered

General SH

2024-07-24 COMPLETED Activity Level

General SH

2024-07-24 COMPLETED Activity Level

Latest Segment

Activity Information:

230000150/262 - WACS-OFS 24B FR ACTIVITY-2

Planned Service History List

General SH

Required: Yes Entered: 2

Downtime

Asset Level

Entered

General SH

2024-07-24 COMPLETED Activity Level

General SH

2024-07-24 COMPLETED Activity Level

2. Measurements that have been sent to WACS/WAM in previous segments are available in View mode only. They cannot be edited.

Previous Segment

Activity Information

Gallons Flow

Reading Date/Time: Jul 23, 2024 at 5:06 PM

Reading: 124

Quick Links

Asset Details

Activity Details

Latest Segment

Activity Information

Gallons Flow

Reading Date/Time: Jul 23, 2024 at 5:06 PM

Reading: 124

Quick Links

Asset Details

Activity Details

3. **Percent Complete** in WACS/WAM shows how much percentage the activity is completed.

Planner

North Planner (Hill)

Service Class

Construction - Capi

Percent Complete

25.05

Locked To Crew

Member

4. **Undo** option will not be available for operations (installation, removal, material usage) once details have been sent to Oracle Utilities Work and Asset Cloud Service/ Oracle Utilities Work and Asset Management in previous segments.
5. For Update Quantity task, quantity completed will be sent to Oracle Utilities Work and Asset Cloud Service/Oracle Utilities Work and Asset Management in each segment's interim completion, not when all segments have been completed.

Note: For Interim Activity Completion, do not start the successor segments of activity until either previous segments details are sent to

Oracle Utilities Work and Asset Cloud Service/Oracle Utilities Work and Asset Management or completion flow errors out for previous segments.