

Oracle® FCCM Automated Scenario Calibration Cloud Service Using Automated Scenario Calibration



Release 26.02.01

G25333-09

February 2026

The Oracle logo, consisting of a solid red square with the word "ORACLE" in white, uppercase, sans-serif font centered within it.

ORACLE®

Oracle FCCM Automated Scenario Calibration Cloud Service Using Automated Scenario Calibration, Release 26.02.01
G25333-09

Copyright © 1994, 2025, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface

Audience	i
Documentation Accessibility	i
Diversity and Inclusion	i
Related Resources	i
Conventions	ii
Comments and Suggestions	ii

1 Overview

2 Getting Started

User Profile	2
--------------	---

3 Admin Notebook Activity

ASC Instance Initialization for Admin Notebook	1
Import Templates for ASC Analysis	2
Create Scenario Definition and Import Templates	2

4 User Notebook Activity

PreProd Scenario Analysis	1
Threshold	1
ASC Instance Initialization for Threshold	1
Create Threshold Set	2
Scenario Execution	3
ASC Instance Initialization for Scenario Execution	4
Specify Execution Parameters	5
Trigger Scenario Execution	9
PreProd Analysis	12
ASC Instance Initialization for PreProd Analysis	12
Attach to an Existing Definition Version	12

Data Loading	13
Create/Add New Feature	14
Computing Recommended Threshold	15
Show Recommended Thresholds	19

Preface

Using Automated Scenario Calibration Cloud Service simplifies and automates the tuning and optimization of scenarios.

Audience

This document is intended for the Data Scientists and Users who are working in the Financial Crime and Compliance Management.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

Related Resources

For more information, see these Oracle resources:

- Oracle Public Cloud: <http://cloud.oracle.com>
- Community: Use <https://community.oracle.com/customerconnect/> to get information from experts at Oracle, the partner community, and other users.
- Training: Take courses on Oracle Cloud from <https://education.oracle.com/oracle-cloud-learning-subscriptions>.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which user supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that user enter.

Comments and Suggestions

Please give us feedback about Oracle Applications Help and guides! You can send an e-mail to: <https://support.oracle.com/portal/>.

1

Overview

Automated Scenario Calibration Cloud Service is designed to simplify and automate the tuning and optimization of Scenarios.

In this service, you can:

- Simulate events from any scenario for a chosen threshold set on demand.
- Use an industry standard methodology to determine thresholds for new scenarios based on historical data.
- Carry out Pre-prod analysis to determine initial thresholds for scenarios.

2

Getting Started

This topic provides step-by-step instructions to log in to the application.

Prerequisites

Before using Automated Scenario Calibration (ASC), you must configure the scenario pipelines to calculate “Overall Risk”. This is a key risk indicator that ASC uses to suggest adequate parameters depending on the “Overall Risk” of the customer.

To Add Overall Risk in pipelines:

1. In the Pipeline Designer, duplicate the Out of the Box pipeline, as described in the [Copying Pipelines](#).
2. Open the newly created pipeline, then open the **Risk Indicator** widget.
3. Add the **Overall Risk** Indicator, as described in [Managing Risk Indicators](#).
4. Save the modified pipeline.

ASC is available with the following scenarios:

- Anomalies in ATM Bank Card - Foreign Transactions - Customer Focus
- Focal High Risk Entity - Customer Focus
- High Risk Counter Party - Customer Focus
- Large Reportable Transaction - Customer Focus
- Possible Currency Transaction Report - Customer Focus
- Rapid Loading and Redemption of Stored Value Cards - Customer Focus
- Rapid Movement of Funds - Customer Focus
- Single or Multiple Cash Transactions - Large Significant Transactions - Customer Focus
- Structuring - Avoidance of Reporting Thresholds - Customer Focus
- Structuring - Deposits Withdrawals of Mixed Monetary Instruments - Customer Focus
- Structuring - Potential Structuring in Cash and Equivalents - Customer Focus

Accessing Automated Scenario Calibration

To access the application:

1. Enter the URL in the web browser. The Oracle Cloud Login page is displayed.
2. Enter your **User Name** and **Password**.
3. Click **Sign In**. The Application Landing page is displayed.
4. In the left pane, click the **Oracle Financial Services Crime and Compliance Management Anti Money Laundering Cloud Service** module. The menu options are displayed.
5. Click **Applications**, then click the **Automated Scenario Calibration**. The **Workspace Summary** of the Automated Scenario Calibration Landing page is displayed with pre-seeded workspace based on the logged in user.

User Profile

This topic provides information about functionality of users in ASC.

Post Provisioning

In case you encountered errors during the provisioning process, perform the following steps:

1. Log in as an Administrator.
2. From the home page, click **Business Process**, click **Batch Administration**, and then click **Scheduler Service** to open the **Scheduler Service, Scheduler Service Dashboard**.
3. On this page, click the **Define Batch** tab.
4. Click the **Create** icon to open the **Create Batch** window.

Figure 2-1 Create Batch Window

Create Batch

Batch Details

Batch Batch Group

Name * ASCCSPostProvisioning

Code * ASCCSPostProvisioning

Description ASCCSPostProvisioning

Service Url Name asccs

Service URL asccs-service/asccs-service

Cleanup URL

Pin Batch

Notify on mail On Error only

Save Close

5. Populate the create batch form as tabulated, you can also use the above image as an example of populating the fields:

Table 2-1 Create Batch Form

Field	Description
Name	Enter the name as <i>ASCCSPostProvisioning</i> .
Code	Enter the code as <i>ASCCSPostProvisioning</i> .
Description	Enter the description as <i>ASCCSPostProvisioning</i> .
Service URL Name	The service URL name must only be <i>asccs</i> .
Service URL	Enter the service URL as <i>asccs-service/asccs-service</i> .
Cleanup URL	You can leave this field blank.
Pin Batch	Click this check box if you want to pin the batch.
Notify on Mail	Select the <i>On Error only</i> option from the drop-down list.

6. Click **Save** after filling in the details.
7. Click the **Define Task** tab to open the **Create Task** window.

Figure 2-2 Create Task

Create Task

v Task Details

Task Name *

Task Code *

Task Description

Task Type

Component *

Batch Service URL

Task Service Url

v Task Parameters +

\$RUNSKEY\$


8. Populate the create task form as tabulated, you can also use the above image as an example of populating the fields. You must create the following tasks with the corresponding details in this window:

Table 2-2 Create Batch Form

Field	Description
Task Name	Enter the following names for the tasks: <ul style="list-style-type: none"> • pushFilesToObjectStore • updateCondaMemory • createWorkspace • createObjective • importNotebook • createDatastore
Task Code	Enter the following codes for the tasks: <ul style="list-style-type: none"> • pushFilesToObjectStore • updateCondaMemory • createWorkspace • createObjective • importNotebook • createDatastore
Task Description	Enter the following descriptions for the tasks. <ul style="list-style-type: none"> • pushFilesToObjectStore • updateCondaMemory • createWorkspace • createObjective • importNotebook • createDatastore
Task Type	Select <i>REST</i> as the task type from the drop-down list.
Component	Select the component as <i>Custom</i> from the drop-down list.
Batch Service URL	Enter the service URL.
Task Service URL	Enter the respective task service URLs that correspond to the created tasks: <ul style="list-style-type: none"> • push-files/push (For task <i>pushFilesToObjectStore</i>) • update-conda-memory/update(For task <i>updateCondaMemory</i>) • workspace/create(For task <i>createWorkspace</i>) • objective/create(For task <i>createObjective</i>) • import-notebook/import(For task <i>importNotebook</i>) • datastore/create(For task <i>createDatastore</i>)
Notify on Mail	Click this check box if you want to pin the batch.

9. For the created tasks, click **Add or remove precedence** to add precedence for *importNotebook* with the parent as *createObjective* and for *createObjective* the parent as *createWorkspace*.

Figure 2-3 Add or Remove Precedence



10. Click the **Schedule Batch** tab and run the newly created batch.
11. Click the **Monitor Batch** tab to monitor the batch.
12. Click the **Home** icon.

After completing the post provisioning steps, you can log in and proceed with using the application.

Admin User (Graph Studio Administrator)

To create the Conda environment:

1. Log in as an Administrator.
2. On the home page, click **Application Administration**, and then click **Automated Scenario Calibration**.
3. On the **Dashboard** page, click **Modeling**, and then click **Pipelines**.
4. Navigate to the notebook by clicking **ASC** and then **Conda** to view the Conda notebook. If you have upgraded from an older version to the latest version of the application, then multiple Conda notebooks will be present. You must run the latest notebook
5. Click **Notebook** and then click the **Run Paragraphs** button to execute all the pre-seeded paragraphs in the notebook to create the conda environment.

Analyst User (ASC Analyst User)

An Analyst user is mapped with **ASC** workspace to automate and simplify the scenario tuning process. For Analyst action, see the following sections:

- [Admin Notebook Activity](#)
- [User Notebook Activity](#)

3


Admin Notebook Activity

The ASC Admin Notebook provides import analysis template for PreProd scenarios.

To access the ASC Admin Notebook:

1. Launch the **ASC** Workspace.
2. On the Dashboard page, click **Modeling** and select **Pipelines**.
3. Click **ASC** Objective and then click **Admin** to view the ASC Admin Notebook.

Figure 3-1 ASC Admin Notebook



ASC Instance Initialization for Admin Notebook

Users can import the necessary packages and create an instance for the Admin Notebook.

Activate Conda Environment

To execute the notebook, users should select the **ASC Conda Environment** from the **Python Runtime Parameters** in the **Pipeline** tab.

ASC Instance Initialization

To create an instance, execute the following.

```
%python-pgx

from ds_interpreter_client.context.ds_context import PyDataStudioContext
ds = PyDataStudioContext()

from ofs_auto_ml.model_deployment.output_tracking import *;
from ofs_auto_ml.db_connection import *
from ofs_aif.ofs_asc.asc import asc
asc = asc()
```

Import Templates for ASC Analysis

This **asc.import_analysis_templates** provides a functionality to create a set of analysis templates that would require to execute PreProd scenarios.

Navigate to the **Configure Analysis and Import Templates** paragraph and run this paragraph to import the following analysis templates:

- **PreProd Scenario**
 - Scenario Execution
 - PreProd Scenario
 - Threshold

Create Scenario Definition and Import Templates

You can create and import the scenario definition for analysis.

To create the analysis definition:

1. Navigate to **Create Scenario Definition** paragraph.
2. From the **Scenario** drop-down list, select the scenario.
3. Enter the **Definition Name** (folder name in which templates will be imported).
4. From the **Analysis** drop-down list, select the analysis type. The available options are **Prod** and **PreProd**.
5. From the **Overwrite** drop-down list, select the option. The available options are:
 - True:** Select when you want to delete and recreate the existing definition.
 - False:** Select when you want to create the definition.
6. **Run** the paragraph to create definition or recreate the existing definition.

Figure 3-2 Create Scenario Definition

▶ 🏠 🗨️ ↶ ↷ ☰ 👁 ⚙️

Create Scenario Definition

Scenario Large Reportable Transaction - Customer Focus	Analysis PreProd	Definition Name PREPROD_LRT_02DEC
Overwrite False		


📄 📄 🔄 ⬇️

Successful run: No result returned.

Run the **Import Templates** paragraph to import templates based on the selected analysis and created the definition under specific path. The scenario definition path should be `Home/ASC/<Analysis>/<Definition Name>`.

Figure 3-3 Import Templates

Import Templates



```
Template imported successfully - 'Threshold' .  
Template imported successfully - 'Scenario Execution' .  
Template imported successfully - 'PreProd Analysis' .  
Creating the definition for analysis under Home/ASC/Analysis/PREPROD_LRT_02DEC
```

4

User Notebook Activity


Users can navigate to the respective analysis folder, where they can define the scope and parameters of the specific scenario.




PreProd Scenario Analysis

Preprod Scenario Analysis is a crucial phase where preliminary assessments and preparations are conducted before actual production. It involves defining the scope and parameters of the scenario, collecting and preprocessing data, establishing assumptions and constraints, and performing initial modeling and simulations.

You can see the imported template for PreProd Analysis as shown in the following figure.

Figure 4-1 PreProd Analysis



<input type="checkbox"/>	Objective Name	ID	Owner	Tags
<input type="checkbox"/>	 PreProd Analysis Finding thresholds for pre-prod scenarios	1735818884278	ASCANALYST	...
<input type="checkbox"/>	 Scenario Execution Execute scenario to generate events for Prod and Pre-Pr...	1735818882367	ASCANALYST	...
<input type="checkbox"/>	 Threshold Threshold Set	1735818880561	ASCANALYST	...

Threshold

Creating threshold set can assess scenario performance, identify areas for improvement, and ensure that the calibrated scenarios meet predefined standards and requirements.

ASC Instance Initialization for Threshold

You can import the necessary packages and create an instance for threshold set.

Navigate to the Threshold Notebook and the path is Home / Modeling / Pipelines / ASC / Analysis / PreProd / Threshold Notebook.

Activate Conda Environment

To execute the notebook, users should select the **ASC Conda Environment** from the **Python Runtime Parameters** in the **Pipeline** tab.

ASC Instance Initialization

```
%python-pgx

from ds_interpreter_client.context.ds_context import PyDataStudioContext
ds = PyDataStudioContext()

from ofs_auto_ml.model_deployment.output_tracking import *;
from ofs_auto_ml.db_connection import *;
from ofs_aif.ofs_asc.asc import asc;
asc = asc()
```


Create Threshold Set

Users can create threshold set for scenario that will be used for further analysis.

You can select available scenario from the **Select Scenario** drop-down list.

Figure 4-2 Choose Scenario


Choose Scenario



You can view the list of existing threshold set names in the **Existing Threshold Set Names** paragraph. Enter the Threshold Set Name in the **Input Threshold Set Name** paragraph and run it.

Figure 4-3 Input Threshold Set Name

Input Threshold Set Name



You will see parameters for threshold set in the **Threshold Set Parameters** paragraph.

Figure 4-4 Threshold Set Parameters

Threshold Set Parameters		
vDataOrigin RDS	dMisDate 2015-11-30	Age 90
Activity_Risk 5	Effective_Risk 5	Min_New_High_Trxn_Amount 1000
Min_New_Low_Trxn_Amount 1000	Min_Seasoned_Med_Trxn_Amount 1000	Min_Seasoned_Low_Trxn_Amount 1000
Min_Seasoned_High_Trxn_Amount 1000	Min_New_Med_Trxn_Amount 1000	Minimum_Transaction_Amount 3000
nLookback 14	nFrequencyPeriod 7	JURISDICTION AMEA

If you want to update threshold set parameters, make the necessary changes in the required fields, and then run the paragraph. This will generate updated threshold values, and you can view the updated threshold set parameters. This threshold set is used to run scenarios in the **Scenario Execution** notebook.

Scenario Execution

This topic describes how to generate tuning alerts by executing a scenario using specified thresholds for any time window.

The first step of the tuning process is to create tuning alerts by setting thresholds to some suitably low value. This generates a population of alerts below the current threshold, which can then be analyzed.

Note

If you want to evaluate multiple thresholds sets for a given jurisdiction or group of jurisdictions, this should be done across different versions within the same definition. Within a single definition version, you should create only one threshold set per jurisdiction.

For example, if you want to evaluate threshold sets for jurisdictions AMEA, APAC and US, then you can create as mentioned in the following table. This assumes you want to apply the same thresholds for AMEA and APAC.

Table 4-1 Threshold Sets for Jurisdiction

Model Group Name	Definition ID	Version	Threshold Set ID	Thresholds
SIG CASH – 2024	123	1	1	{“Min_Trans_Amt”: 15000, “Min_Trans_Ct”:5 , “Incl_Jrscdn_Cd: [“AMEA”, “JAPAC”]}}

Table 4-1 (Cont.) Threshold Sets for Jurisdiction

Model Group Name	Definition ID	Version	Threshold Set ID	Thresholds
SIG CASH – 2024	123	1	2	{"Min_Trans_Amt": 12000, "Min_Trans_Ct": 3, "Incl_Jrscdn_Cd": "US"}
SIG CASH – 2024	456	2	1	{"Min_Trans_Amt": 13000, "Min_Trans_Ct": 2, "Incl_Jrscdn_Cd": ["AMEA"."JAPAC"]}
SIG CASH – 2024	456	2	2	{"Min_Trans_Amt": 12500, "Min_Trans_Ct": 6, "Incl_Jrscdn_Cd": "US"}

ASC Instance Initialization for Scenario Execution

You can import the necessary packages and create an instance for the scenario execution.

Navigate to the Scenario Execution Notebook and the path is Home / Modeling / Pipelines / ASC / Analysis / PreProd / Scenario Notebook.

Activate Conda Environment

To execute the notebook, users should select the **ASC Conda Environment** from the **Python Runtime Parameters** in the **Pipeline** tab.

ASC Instance Initialization

To create an instance, execute the following.

```
%python-pgx

from ds_interpreter_client.context.ds_context import PyDataStudioContext
ds = PyDataStudioContext()

from ofs_auto_ml.model_deployment.output_tracking import *;
from ofs_auto_ml.db_connection import *;
from ofs_aif.ofs_asc.asc import asc;

asc = asc()
setattr(asc, 'objectiveId', objectiveId)
```

Scenario

The notebook itself shows the scenario with which the analysis has been attached to.

Specify Execution Parameters


The scenario can be executed for single or multiple thresholds for a given scenario. User must give the number of Threshold Set IDs to be executed for a given scenario.

Select Number of Threshold Sets





Depending on the number of thresholds selected by the user, that number of drop-downs will appear in the next paragraph, where different Threshold Set IDs can be selected for the scenario.

Figure 4-5 Select Number of Threshold Sets

Select Number of Threshold Sets



Number Of Threshold Set Ids
2

Icons:    


Successful run: No result returned.

Select Threshold Set IDs

You can choose the base Threshold Set ID or Threshold Set ID which was generated through Threshold Utility Notebook depending on the requirement of the analysis.





Figure 4-6 Select Threshold Set IDs

Select Threshold Sets



Threshold Set Id1
LRT_CUST_25

Threshold Set Id2
LRT_TSHLD_2DEC

Icons:    

Successful run: No result returned.

Select Run Dates and Batch Name

Figure 4-7 Select Run Dates - Date Strings

Select Run Dates/Batch Name

Select Run Dates
Date Strings

Batch Name
DLY

Successful run: No result returned.

- When Select Run Dates is **Date Strings** the input text box takes the comma separated dates. When Run Dates are passed as a **comma separated**, all possible combinations with Threshold Set IDs will be created. For example: If Run Dates are passed as a comma separated **20211007, 20211014, 20211022** then Threshold Set IDs are **116000048, 118860048, 78**. The possible combinations are:

```
{
  "20211007": [116000068, 118860048, 78],
  "20211014": [116000068, 118860048, 78],
  "20211022": [116000068, 118860048, 78]}

```

Note

Make sure that you enclosed keys of dictionary into the double quotes.

Figure 4-8 Select Dates - Date Strings

Select Dates

Input Dates
20151130

Re-run/Update-run
False

Provide comma separated dates in format YYYYMMDD.....

Ex: 20211007,20211014,20211022

Parameters Selected.....

- Scenario :** Large Reportable Transaction - Customer Focus
- Threshold Set Id :** ['LRT_CUST_25', 'LRT_TSHLD_2DEC']
- Batch Name :** DLY
- Re-run/Update-run :** False
- Date Strings :** [20151130]

The other option is selective **run date - threshold set id** combinations by passing **dictionary**, as an input.

For example:

```
{"20211007": [116000068],  
  "20211014": [118860048, 78],  
  "20211022": [116000068, 118860048, 78]}
```

Note

Ensure that you enclosed keys of dictionary into the double quotes.

- **Re-run/Update-run** should be **True** if you are re-executing the scenarios for **failed** run_dates/threshold_set_ids or **appending** any new run_dates/threshold_set_ids to existing version.
 - Re-run/Update-run is only applicable when Input Run Dates is selected as **Date Strings**.
 - The run_dates can be passed either **comma separated or dict of (run_dates,threshold_set_id)** combinations.
 - If it was re-executed with flag is **False**, then entries into **DB tables will not be updated**. However, scenario would be executed.
- When Select Run Dates is **Date Ranges** the input text box takes date format as shown in the following figure.
The description for date range inputs are as follows:
 - **From Date**: Enter the starting date. This field is mandatory. For example - 20211007.
 - **To Date**: Enter the ending date. If it is **None**, then the count should be mandatory to pass. This field is optional. For example, 20211022.
 - **Frequency**: Frequency of a scenario. By default, it is **Monthly**. This field is mandatory. For example, Weekly.
 - **Count**: The maximum number of recurrences to generate. This field is optional.
 - **By Month Day**: Integer or a sequence of integers, meaning the month days to apply the recurrence. This field is optional.
 - **Re-run/Update-run**: A Boolean flag (True/False) is provided to re-run the failed run dates or append the new run dates with the existing definition. The value is either True or False.

The selected parameters are as follows:

- **From Date**: 20211007
- **To Date**: 20211022
- **Frequency**: Weekly
- **Count**: None
- **By Month Day**: None
- **Re-run/Update-run**: False

Show Selected Parameters

```
%python-pgx
asc.show_scenario_parameters()
```

Note

You must examine all parameters carefully especially **Run Dates** before these are feeding to Scenario Execution Notebook. In case of any discrepancies, set the “Run Dates” again and verify using this API.

Create Definition

You can create a definition that will be used to track all data that is to be generated by executing this scenario and any analysis to be carried out thereafter on this data.

Figure 4-9 Create Definition

Create Definition

Save With New Version
False

Clean Results
False

Version
None

- To use an existing definition and overwrite the existing results, set **Save With New Version = False, Clean Results = True** and set **Version** to the version you want to clean up the existing results and start again. If the **Version** is set to **None**, the most recent version will be cleaned up.
- To use an existing definition and merge results to the existing results, set **Save With New Version = False, Clean Results = False** and set **Version** to the version you want to merge. If the **Version** is set to **None**, the most recent version will be used.
- To create a new version and map the results to this version, set **Save With New Version = True** and **Version** to the version you want to create. If you set **Version** to **None**, a new version will be created after incrementing the most recent version by 1. **Clean Results** will have no impact when creating a new version.

Show Definition

To show definition, execute the following.

```
%python-pgx

asc.show_definition()
```

Trigger Scenario Execution

Execute scenario for given combination of Run Dates and Threshold Set IDs.

Execute Scenario

To execute the scenario, run the following.

```
%python-pgx


if run_flag == True:
    asc.asc_cleanup4rerun()

asc.execute_scenario()
```

Execution Status

You can verify the execution status for each Run Date using the Execution Status paragraph.

Figure 4-10 Execution Status



There are two types of execution status as follows:

- **Current Executions:** It shows only executions which are currently running in the notebook python session.
- **All Executions:** It shows current executions along with executions from the previous runs/ sessions for the same Definition ID and version.

Detailed Execution Status

If it is **True**, then it gives detailed status of runs for each Job IDs. It shows error in case execution is failed, start time, end time and execution time for each job.

i Note

If a scenario has multiple Job IDs, the status of each Job ID must be COMPLETED for the execution of the given Run Date to be considered as COMPLETED. Otherwise, it will be marked as FAILED. The error log will display any errors that occurred in the paragraph from the Utility Scenario Notebook

On successful completion of each run, the post processing step can be completed as described below. This moves the generated events into a table in the schema which can be retrieved for further analysis.

Re-run/Update Flag and All Execution Status

The user may want to execute the failed Run Dates again, considering the post-processing which was not yet executed for the current definition ID and version. The Run Dates status in **All Execution Status** would be updated with the latest status of the Run Dates, whether the `run_flag` is True or False.

Only after executing post-processing, the `asc_runid_lookup` table gets entry for the current definition ID and version.

Users must use the **Re-run/Update** flag is set to **True** for making any updates to existing Run Dates or the addition of any new Run Dates to the existing definition and version in the `asc_runid_lookup` table.

On completion of each run, only the **COMPLETED** Run Dates will be considered for the post processing step, which is described below. This moves the generated events into a table in the schema, which can be retrieved for further analysis.

Show Available Scenario Bindings

To show available scenario bindings, execute the following.

```
%python-pgx  
  
asc.show_scenario_bindings()
```

Set Expression for Tunable Parameters

To set expression for tunable parameters, you must specify the parameters to be analyzed. This must be expressed in the same form as the scenario logic.

Note

For many scenarios, the available bindings include both a **Base** and **Func** versions of a parameter. In such cases, determine the **Curr_Type** the scenario has been configured to use. If it has been set to **F**, the **Func** version of the parameter should be used; otherwise, the **Base** version should be used.

To set expression for tunable parameters, execute the following.

```
%python-pgx  
tunable_parameters = "TOTAL_DEPOSIT_AMOUNT | TOTAL_WITHDRAWAL_AMOUNT"  
setattr(asc, 'tunable_parameters', tunable_parameters)
```

Note

Using `setattr` method, the expression for tunable parameters is stored into class object for PreProd analysis.

Post Execution Activity

To perform post processing activity, execute the following.

```
%python-pgx
asc.scenario_post_processing()
```

This API perform the post scenario execution activities as follows:

1. Creating a unique **asc_run_id** in the **ASC_RUNID_LOOKUP** table.
2. Loading ATL alerts for given run_id in the **ASC_INVESTIGATED_ENTITIES** table.
3. Loading scenario data for given Run Dates into **ASC_EVENT_MASTER** table.

Review Results

You can review the results of scenario execution. The summary of the event volumes is generated as shown below.

Event Volume

You are provided with multiple groups options across run dates as follows:

- **RUN_DATE**: Aggregate alerts by different run dates.
- **EVENT_TAG**: Aggregate alerts by event tag (ATL or BTL).
- **RUN_DATE_AND_EVENT_TAG**: Aggregate alerts by RUN DATE and EVENT TAG.
- **JURISDICTION_AND_RUN_DATE**: Aggregate alerts by JURISDICTION and RUN_DATE.
- **RUN_DATE_AND_THRESHOLD_SET_ID**: Aggregate alerts by RUN DATE and THRESHOLD SET ID.
- **EVENT_TAG_AND_THRESHOLD_SET_ID**: Aggregate alerts by EVENT_TAG and THRESHOLD SET ID.
- **THRESHOLD_SET_ID**: Aggregate alerts by THRESHOLD SET ID.
- **ALL**: Aggregate alerts by all inputs together (by SEGMENT_ID, RUN_DATE, EVENT_TAG).

Figure 4-11 Event Volume

Event Volume

Group By: THRESHOLD_SET_ID

Type to search

TSHLD_SET_NAME	ALERT_VOLUME	MEAN_ALERT_VOLUME	STD_ALERT_VOLUME	MIN_ALERT_VOLUME	MAX_ALERT_VOLUME
LRT_CUST_25	52	52	0	52	52
LRT_TSHLD_2DEC	259	259	0	259	259

```
asc.save_object()
```

Save Object

It saves the current ASC object in DB tracking table for later use in ATL, BTL, Impact and PreProd Analysis notebooks.

To save object, execute the following:

```
%python-pgx  
  
asc.save_object()
```

PreProd Analysis

PreProd Analysis Notebook provides thresholds for preprod scenarios.

ASC Instance Initialization for PreProd Analysis

You can import the necessary packages and create an instance for the PreProd analysis.

Navigate to the PreProd Analysis Notebook and the path is Home / Modeling / Pipelines / ASC / Analysis / PreProd / PreProd Analysis Notebook.

Activate Conda Environment

To execute the notebook, users should select the **ASC Conda Environment** from the **Python Runtime Parameters** in the **Pipeline** tab.

ASC Instance Initialization

To create an instance, execute the following.

```
%python-pgx  
  
from ds_interpreter_client.context.ds_context import PyDataStudioContext  
ds = PyDataStudioContext()  
  
from ofs_auto_ml.model_deployment.output_tracking import *;  
from ofs_auto_ml.db_connection import *;  
from ofs_aif.ofs_asc.asc import asc;  
  
asc_obj = asc()  
setattr(asc_obj, 'objectiveId', objectiveId)
```

Attach to an Existing Definition Version

You must load the same object version which was used during Scenario Execution.

Figure 4-12 Load Existing ASC Object

Load Existing ASC Object



Event Volume

Events volume by different inputs as follows:

- **RUN_DATE**: Aggregate alerts by RUN_DATE.
- **JURISDICTION**: Aggregate alerts by JURISDICTION.
- **JURISDICTION_AND_RUN_DATE**: Aggregate alerts by JURISDICTION and RUN_DATE.
- **JURISDICTION_AND_THRESHOLD_SET_ID**: Aggregate alerts by THRESHOLD_SET_ID and JURISDICTION.
- **THRESHOLD_SET_ID**: Aggregate alerts by THRESHOLD_SET_ID.

Figure 4-13 Event Volume

Event Volume

Group By		Event Tag		
JURISDICTION_AND_RUN_DATE		BTL		
TSHLD_SET_NAME	ALERT_VOLUME	MEAN_ALERT_VOLUME	STD_ALERT_VOLUME	MIN_ALERT_VOLUME
LRT_CUST_25	52	52	0	52
LRT_TSHLD_2DEC	259	259	0	259

Data Loading

You can get data for selected Threshold Set IDs.

Getting Data

It retrieves the data from DB tables for selected tunable parameters. The tunable_parameters input is optional .

- Input expression will be taken from class variable **asc.tunbale_parameters** if it was set during scenario execution.
- Input text box will only appear for user, if class variable **asc.tunable_parameters** is **None**. User can then set the expression again.

For example:

```
tunable_parameters = "Trans_Base_Amt | Trans_Ct"
```

Include/Exclude Threshold Set IDs

Use the **Include/Exclude Threshold Set IDs** paragraph to include or exclude relevant Threshold Set IDs. If **None** of the Threshold Set IDs are selected, all Threshold Set IDs will be included.

Figure 4-14 Include/Exclude Threshold Set IDs

Include/Exclude Threshold Set Ids

Event Tag
BTL

Include Threshold Set Ids

LRT_CUST_25 LRT_TSHLD_2DEC

Exclude Threshold Set Ids

LRT_CUST_25 LRT_TSHLD_2DEC

Successful run: No result returned.

Note

The PreProd analysis only supports the **BTL** event_tag. Selecting other options may result in an error.

Get Data

To get the data, execute the following.

```
%python-pgx

evented_data_pdf = asc.get_data(tag = event_tag,
                                tunable_parameters = tunable_param,
                                include_threshold_set_ids =
include_threshold_set_ids,
                                exclude_threshold_set_ids =
exclude_threshold_set_ids,
                                is_pre_prod_analysis=True)
z.show(evented_data_pdf.head())
```

Create/Add New Feature

You can create new features and add to the existing dataframe.

Create New Feature

To create a new feature, execute the following.

```
%python-pgx

import pandas as pd
def custom_feature(X, key_var='EVENT_ID'):
    V =
```

```
abs(X["TOTAL_DEPOSIT_AMOUNT"].fillna(0)+X["TOTAL_WITHDRAWAL_AMOUNT"].fillna(0)
)
return pd.DataFrame({key_var : X[key_var], 'AVG_TRXN_PER_CT' : V})

df = custom_feature(evented_data_pdf)
```

Most scenarios use simple parameters which trigger an alert when the parameter value is greater than a threshold. However, some scenarios employ more complex parameters, which trigger an alert only when the parameter value is within a range. Such complex parameters, for example, Min_Percentage in the Rapid Movement of Funds scenario have to be appropriately transformed before the default scenario tuning methodology can be applied.

View Newly Created Feature

To view the newly created feature, execute the following.

```
%python-pgx

z.show(df.head())
```

Add New Feature with Existing Dataframe

A new feature will be added to the existing dataframe; therefore, expression should also be updated. Use the **tunable_parameters** parameter to update the existing expressions for the tunable parameters. Based on the expression, the strata will be determined.

If it is **None**, then it would use the same expression which would have set in the Scenario Execution Notebook.

To add a new feature with existing dataframe, execute the following.

```
%python-pgx

asc.add_to_event_dataset(df_list=[df])
```

Get Updated Dataframe

To get an updated dataframe, execute the following.

```
%python-pgx

evented_data_pdf = asc.get_event_dataset()
z.show(evented_data_pdf.head())
```

Computing Recommended Threshold

This topic provides option for choosing appropriate outlier technique and threshold computing technique.


Select Parameters for Tuning

In this option, you need to select the parameters for which thresholds will be calculated. The default parameters are taken from the expression that the user must have set in the Scenario Execution Notebook. The parameters are stored in the class variable **asc.tunable_parameters_list**.

Limitation

The Select Parameters for Tuning paragraph might fail due to a missing class object before the variable is used.

Figure 4-15 Error Message - Select Parameters for Tuning



```

Fail to execute line 18: features_list = tunable_parameters_list
Traceback (most recent call last):
  File "/tmp/python6477048722814463574/zeppelin_python.py", line 181, in <module>
    exec(code, _zcUserQueryNameSpace)
  File "<stdin>", line 18, in <module>
NameError: name 'tunable_parameters_list' is not defined

```


To resolve this issue, add another paragraph above the failed paragraph with the following and run the paragraph.

```

%python-pgx
tunable_parameters_list = asc.tunable_parameters_list

```

Figure 4-16 Select Parameters for Tuning



```

%python-pgx
tunable_parameters_list = asc.tunable_parameters_list

```

Successful run: No result returned.

Select parameters for tuning

Include Features

TOTAL_DEPOSIT_AMOUNT

TOTAL_WITHDRAWAL_AMOUNT AVG_TRXN_PER_CT

Exclude Features

TOTAL_DEPOSIT_AMOUNT

TOTAL_WITHDRAWAL_AMOUNT AVG_TRXN_PER_CT

Check Data Distribution

You can see the data distribution for selected Threshold Set ID and parameters and decide on the outlier techniques for calculating the thresholds to use.

Parameter Sample Fraction can be used to take the subset of data. The Parameter Sample Fraction value is between 0 to 1.

Figure 4-17 Check Data Distribution




Check Data Distribution

Select Threshold Set
ALL

Figure-size(Width,Height)
12,10

Plot
True

Sample Fraction (between 0 to 1)
0.1

Select Outlier Detection Method

You are provided with out-of-box univariate outlier methods. The outlier methods are divided into two groups based on the type of population. For each of the method, you can select the tail either **RIGHT**, **LEFT** or **BOTH** for removing outliers.

For Normal Population



- **zscore**: Outliers are number of standard deviations away from the mean.
 - Parameter **nstdev**. Default is 3.
- **IQR**: Inter-Quantile-Range (Q75-Q25). Outliers are considered which is away from $Q75 + IQR * iqr_cut_off$.
 - Parameter **iqr_cut_off**. Default is 3.
- **percent_outliers**: Percent of data points are considered to be outliers.
 - Parameter **outliers_proportion**. Default is 5%.

For Skewed Population

- **robust_zscore**: It is similar to Z-score method with some changes in parameters.
 - Parameter **nstdev**. Default is 3.
 - Since mean and standard deviations are heavily influenced by outliers, instead of them it uses median and absolute deviation from median.
 - Also called Median Absolute Deviation (MAD) method.
- **adjusted_boxplot**: It is similar to IQR method with some changes in parameters.
 - It customizes the range of valid data for both side of tails differently.
 - Exponential model is used for fitting the data.

Figure 4-18 Select Outlier Detection Method**Select Outlier Detection Method**

Select Outlier Method
None


Note: Outlier technique is None. No any outlier technique will be used in final threshold computing methods.

Select Threshold Computing Techniques

You are provided with following two out-of-boxes threshold computing techniques:

- **Percentile:** Thresholds are calculated based on the percentiles.
 - parameter **perc_list**. Default is [85,90,95]
 - User can pass its own percentile's list.
 - If **None** is passed, then threshold will be set at 85%, 90% and 95% for HR, MR and RR respectively.

Figure 4-19 Select Threshold Computing Techniques



- **Jump:** Thresholds are calculated based on the highest peaks found within the range defined.
 - Parameter **range**. Percentile range in which peaks will be found. It works similar like a range method in python.
 - If **range** is **None**:
 - * Default range (85,100,0.1) is used.
 - * Highest peak is found for HR between 85-90%, MR between 90-95% and RR between 95-99.9%.
 - * If none of the peaks is found in range specified, then threshold is set at minimum percentile at 85%, 90% and 95% for HR, MR and RR respectively.
 - * If any peak is missing for any range specified, then threshold for missing peak is set at same to last peak found. For example, if no peak is found for RR, then the threshold for RR will be set to same threshold as of MR.
 - If **range** is **not None**:
 - * Range is passed as a **tuple**.
 - * Three highest peaks will be found between the range defined by the user. For example, (80,100) and (85,100,0.2).
If none of the peaks is found in range specified, then thresholds for all will be set at minimum percentile. For example, 85%.
 - If any peak is missing for any range specified, then threshold for missing peak will be set at same to last peak found. For example, if no peak is found for RR, then the threshold for RR will be set to same threshold as of MR.
 - * Range is passed as a **dict**
 - * Highest peak will be found as per the range defined by the user for each risk level.

- * For example, {'HR':(80,90,0.2),'MR':(90,95),'RR':(95,99,0.1)}, {'HR':(85,90),'MR':(90,95,0.1),'RR':(95,100,0.2)}
- * If none of the peaks is found in range specified, then threshold will be set at minimum percentile passed by the user in specified range.

Compute Recommended Thresholds

The API takes all the parameters (tunable parameters, outlier technique, and threshold computing technique) as an input and calculates the thresholds for each of the tunable parameters across the selected threshold set ids.

```
%python-pgx
```

```
asc.compute_initial_thresholds(features=features_list,
                              outlier_method=outlier_method,
                              technique=technique,
                              outliers_proportion=outliers_proportion,
                              nstdev=nstdev,
                              robust_zscore_cut_off=robust_zscore_nstdev,
                              iqr_cut_off=iqr_cutoff,
                              anomaly_proportion=anomaly_proportion,
                              perc_list=perc_list,
                              search_range=search_range,
                              tail=tail)
```

Show Recommended Thresholds

You can select the calculated thresholds for selected Parameters, Threshold Set IDs and Risk Levels.

Figure 4-20 Select Options

Select Options

<p>Select Parameters</p> <p><input type="checkbox"/> TOTAL_WITHDRAWAL_AMOUNT</p> <p><input type="checkbox"/> TOTAL_DEPOSIT_AMOUNT</p>	<p>Select Threshold Set Ids</p> <p><input type="checkbox"/> LRT_CUST_25 <input type="checkbox"/> LRT_TSHLD_2DEC</p>	<p>Select Risk Level</p> <p><input type="checkbox"/> HR <input type="checkbox"/> MR <input type="checkbox"/> RR</p>
---	---	---

Successful run: No result returned.

After selecting the options, run the paragraph to view the recommended thresholds.

Figure 4-21 Show Thresholds

