

Oracle® Insurance Loss Modeller

Installation Guide



Release 8.1.2.8.0

G48837-01

June 2025

The Oracle logo, consisting of a solid red square with the word "ORACLE" in white, uppercase, sans-serif font centered within it.

ORACLE®

Oracle Insurance Loss Modeller Installation Guide, Release 8.1.2.8.0

G48837-01

Copyright © 2024, 2025, Oracle and/or its affiliates.

Primary Authors: (primary author), (primary author)

Contributing Authors: (contributing author), (contributing author)

Contributors: (contributor), (contributor)

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

1	Introduction to Oracle Insurance Loss Modeller	
2	Oracle Insurance Loss Modeller (OILM) Release 8.1.2.8.0	
	Pre Installation Requirements	1
	Installing this Maintenance Level Release	1
	Post Installation Configurations	3
	Configure Server.xml for Tomcat 9x	3
	Configure the OILM Configuration Tables	3

1

Introduction to Oracle Insurance Loss Modeller

The application projects future cash flows based on the various actuarial methods. The output of the application is useful in different processes such as Capital Modeling, Business Planning, Reserving, AvE, IFRS17 computation, and so on.

The overall application is segregated into two parts; the Landing Page and the Projection Page. The Landing Page is a dashboard that summarizes the Key Performance Indicators such as GWP, Exposure, Losses, Loss Ratios, Major Drivers, Incurred Loss Frequency and severity, etc. with an option to customize and view them at Business Unit, Line of Business, Product, Sub Product, and further coverage levels.

The Projection Page facilitates the working space for the Projection Calculation under various approaches such as Chain Ladder, BF, etc. at Business Unit, Line of Business, Product, Sub Product, and further coverage levels.

2

Oracle Insurance Loss Modeller (OILM) Release 8.1.2.8.0

Oracle Insurance Loss Modeller v8.1.2.8.0 Maintenance Level (ML) release includes all the bug fixes and minor enhancements since the previous release v8.1.2.1.0.

Pre Installation Requirements

The prerequisites are as follows:

- The minimum patch set level must be 8.1.2.0.0 and 8.1.2.1.0.
- Update the OFSAA 8.1.1.x Java 8 Instance to Java 11. For more information on updating the Java instance, see the OFS AAI Installation Guide.

For more information on the OFS AAI requirements, see OFS Advanced Analytical Applications Infrastructure Application Pack 8.1.2.0.0 Release Notes in [OHC Documentation Library](#).

Installing this Maintenance Level Release

Oracle Linux 9 Server Support

The OFS AAI 8.1.2.5.x release supports Oracle Linux 9 Server in addition to the continued support on Oracle Linux 8 and Oracle Linux 7.

Note

The Oracle Linux 9 Server Configuration section applies to upgrade installation of OFS AAI and the New Installation of OFS AAI 8.1.2.0.0 with Oracle Linux 9 Server section applies to new installation of OFS AAI.

New Installation of OFS AAI 8.1.2.0.0 with Oracle Linux 9 Server: To install the OFS AAI 8.1.2.0.0 base installer with Oracle Linux 9 Server, follow the instructions in the My Oracle Support [Doc ID 3067623.1](#) and then upgrade to OFS AAI 8.1.2.5.0.

Installing this Maintenance Level Release

To install this Maintenance Level Release, follow these steps:

1. Login to [My Oracle Support](#) and search for **37369908** under the **Patches & Updates** tab.
2. Download the Erwin data model patch **37369984**.
3. Download the *OFSAA 8.1.2.8.0 OILM* archive file and copy it to your OFSAA server in Binary mode.

Note

There are different archive files for different operating systems such as Solaris, and RHEL/OEL.

4. Stop all the OFSAAI services. For more information, see the Start/Stop Infrastructure Services section in [Oracle Insurance Loss Modeller Installation Guide Release 8.1.2.0.0](#).
5. Login to the OFSAA server as a non-root user and navigate to the \$FIC_HOME folder.
6. Assign WRITE permission to the file/folders such as common scripts, EXEWebService, ficapp, ficweb, and find them in the \$FIC_HOME folder by executing the command:
`chmod -R 775 *`
7. If you have to Unzip utility, skip to the next step or download the Unzip utility (OS-specific) and copy it in Binary mode to the directory that is included in your PATH variable, typically \$HOME path or directory in which you have copied the 8.1.2.1.0 ML.
 - Uncompress the unzip installer file using the command:
`uncompress unzip -a OFS_OILM_8.1.2.1.0_<OS>.zip`

Note

If you notice an error message "*uncompress: not found [No such file or directory]*" when the package is not installed, contact your UNIX administrator.

8. Give EXECUTE permission to the utility by using the command:
`chmod 755 unzip_<os>`
9. Extract the contents of the 8.1.2.8.0 ML archive file by using either of the following commands:
`unzip <name of the file to be unzipped>`
10. Update the configuration file `params.conf` File present in the `OFS_OILM_PACK/appsLibConfig/conf` Folder before triggering the installation. The update instructions are present in this file itself.
In case of customized Data Model upload, then update the `params.conf` file present in the `OFS_OILM_PACK/appsLibConfig/conf` Folder accordingly.
11. Give EXECUTE permission to the ML patch installer script. Navigate to the `OFS_AAI` directory and execute the command:
`chmod 755 OFSAAIUpdate.sh`
12. Execute the following command:
`./OFSAAIUpdate.sh`
13. Verify if the ML is applied successfully by checking the log files generated in `OFS_OILM_PACK/OFS_OILM/logs` Directories. You must also verify the Data Model Logs, the path can be found in the `silent.props` file. You can ignore `ORA-00001` and `ORA-02292` in the log file. In case of any other errors, contact [My Oracle Support](#).
14. After successful installation of the ML, perform the following steps:
 - Clear the application cache. Navigate to the following path depending on the configured web application server and delete the files.
 - **Tomcat:** `<Tomcat installation folder>/work/Catalina/localhost/<Application name>/org/apache/jsp`

- **Weblogic:** <Weblogic installation location>/domains/<Domain name>/servers/<Server name>/tmp/_WL_user/<Application name>
 - **Websphere:** <Websphere installation directory>/AppServer/profiles/<Profile name>/temp/<Node name>/server1/<Application name>/<.war file name>
15. Delete the existing EAR/WAR file available in the folder \$FIC_HOME/ficweb.
 16. Generate the application EAR/WAR file and redeploy the application onto your configured web application server. For more information on generating and deploying the EAR/ WAR File, see [Create and Deploy the EAR or WAR Files](#) in OFS AAI Release 8.1.2.0.0 Installation and Configuration Guide.
 17. Restart all the OFSAAI services. For more information, refer to the [Start/Stop Infrastructure Services](#) Section in OFS AAI Release 8.1.2.0.0 Installation and Configuration Guide.

Post Installation Configurations

This section provides information on the post-installation configurations.

Configure Server.xml for Tomcat 9x

Perform the following step to configure server.xml for Tomcat9x:

Edit the server.xml File that is present under the \$TOMCAT_DIRECTORY/conf/ Directory with the following changes that is required for Connection Pooling.

```
<Context path="/" $CONTEXTNAME$ " docBase=" $APP_DEPLOYED_PATH$ "
debug="0" reloadable="true" crossContext="true">
<Resource auth="Container" name="jdbc/ $INFODOM_NAME$"
type="javax.sql.DataSource"
driverClassName="oracle.jdbc.driver.OracleDriver" username="
$ATOMICSCHEMA_USERNAME$" password="$ATOMICSCHEMA_PASSWORD$"
url="$JDBC_CONNECTION_URL"
maxTotal="300" maxIdle="30" maxWaitMillis="10000"
removeAbandonedOnBorrow="true" removeAbandonedTimeout="60"
logAbandoned="true"/>
</Context>
```

For more information, refer to the Define JDBC Connection Pooling Section in the [OFS AAI Installation Guide](#).

Configure the OILM Configuration Tables

Perform the following steps to configure the OILM Configuration Tables.

1. In the Atomic Schema, populate the FSI_OILM_CONFIGURATION_DETAILS Table as tabulated:

SI No	Column Name	Parameters
1	OBJECT_ID	The serial number. Example: 1, 2,3 for every row.
2	APP_ID	The default value is OFS_OILM.
3	USER_ID	The application username. Example: OILMUSER and SYSTEM must be given as default users.
4	DIMENSION_MAP_KEY	By default, the SYSTEM and USERID must be inserted with a different DIMENSION_MAP_KEY. Example: Only Numeric values such as 1,2,3.
5	TRIANGLE_DECIMAL	For the Triangle decimal column, the mandatory value should be between the ranges of 1 to 6.

This table is used to map different dimension's DIMENSION_MAP_KEY for the respective application user.

- The dimensions mapped in the dimension selection on the OILM configuration landing page will be updated in the FSI_OILM_CONF_DIMENSION_MAPPING table.

SI No	Column Name	Parameters
1	DIMENSION_MAP_KEY	The serial number. Example: 1, 2,3 for every row.
2	DIMENSION_NAME	By default for each application user, the first dimension must be the Legal Entity The User can map 10 dimensions, including the Legal Entity Dimension, out of 20 Dimensions available in the OILM Application. The list of Dimension can be referred to from the REV_DIMENSIONS_TL Seeded Data Table.
3	ORDER_ID	For the selected 10 Dimensions, the first dimension must always be Legal Entity and the DIMENSION_MAP_KEY must be 1.

This table is used to map different dimension's for the respective application user.