Oracle® Fusion Middleware

Using Oracle GoldenGate Studio 12c (12.2.1.2.6)

E80175-01

December 2016

This document explains how to configure, customize, and run the Oracle GoldenGate Studio to create and manage the replication of data.



Oracle Fusion Middleware Using Oracle GoldenGate Studio, 12c (12.2.1.2.6)

E80175-01

Copyright © 2015, 2016, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface						
	Doc	rumentation Accessibility	vi			
Related Information						
	Cor	ventions	vi			
1	Introducing Oracle GoldenGate Studio					
	1.1	Introduction	1-1			
	1.2	How Do I Get Started?	1-1			
2	Usir	ng the Interface				
	2.1	Understanding the User Interface Basics	2-1			
		2.1.1 Oracle GoldenGate Studio Repository Login	2-2			
		2.1.2 Menu Options	2-3			
	2.2	Setting Your Preferences	2-7			
		2.2.1 How to Set Preferences	2-7			
	2.3	Navigation Using the Keyboard	2-7			
	2.4	Using the Projects Navigator	2-8			
	2.5	Using the Editor Area	2-9			
	2.6	Using the Resources Navigator	2-9			
		2.6.1 Add a New Database Connection	2-10			
		2.6.2 Add a New Big Data System Connection	2-12			
		2.6.3 Add a New Global Mapping Group	2-13			
		2.6.4 Add a New Oracle GoldenGate Instance	2-14			
	2.7	Using the Properties Inspector	2-15			
		2.7.1 How to Use the Properties Inspector	2-15			
3	Wor	king with Solutions and Deployment Profiles				
	3.1	Understanding Projects	3-1			
		3.1.1 Creating a Project	3-1			
	3.2	Understanding Solutions	3-1			
		3.2.1 Creating a New Solution	3-2			
	3.3	Understanding Deployment Profiles	3-3			

	3.3.1 Components of the Deployment Profile	3-3	
	3.3.2 Consolidation of Capture	3-5	
	3.3.3 Toolbars in the Deployment Profile	3-6	
	3.3.4 Creating a New Deployment Profile	3-7	
4	Working with Mappings Groups		
	4.1 Understanding Mapping Groups	4-1	
	4.1.1 Schema and Table Mapping	4-1	
	4.1.2 Column Mapping	4-3	
	4.1.3 Automap	4-5	
	4.2 How to Create a Mapping Group	4-5	
	4.3 How to Assign Mapping Groups to Replication Path	4-6	
	4.4 How to Copy And Share Mapping Groups	4-6	
5	Deploying and Monitoring Your Solutions		
	5.1 Deploying Solutions	5-1	
	5.1.1 How to Deploy a Solution		
	5.2 Overview	5-2	
	5.2.1 Definition	5-2	
	5.2.2 Deployment History	5-2	
	5.2.3 Monitoring	5-2	
	5.2.4 Deployment Configuration		
	5.2.5 Oracle Data Pump	5-4	
6	Managing Security		
	6.1 Understanding Security in Oracle GoldenGate Studio	6-1	
	6.2 Using the Security Navigator	6-1	
	6.2.1 Adding a New User	6-1	
	6.2.2 Modifying an Existing User	6-2	
	6.2.3 Deleting an User	6-3	
7	Troubleshooting		
	7.1 Positioning of Docked Windows	7-1	
	7.2 Performance Issues While Using Oracle GoldenGate Studio	7-1	
	7.3 Privilege Issue with Oracle GoldenGate Studio	7-1	
	7.4 Syntax Errors with Generated Code	7-1	
	7.5 Not Able to Add Resources	7-2	
Α	Concepts and Terminology		
В	Relating Properties Inspector Options to Oracle GoldenGate Commands and		
	Parameters		
	B.1 Commands with Options	B-1	

	B.1.1 ADD EXTRACT Commands	B-1
	B.1.2 ADD REPLICAT Commands	B-3
	B.1.3 ADD EXTTRAIL Command	B-4
	B.1.4 ADD RMTTRAIL Command	B-4
	B.1.5 REGISTER EXTRACT Command	B-5
	B.1.6 START EXTRACT Command	B-5
	B.1.7 START REPLICAT Command	B-5
	B.1.8 ADD TRANDATA Command	B-6
B.2	Parameter Category Names	B-7
B.3	Units of Measure	B-8
B.4	Opposites	B-9
B.5	Other Oracle GoldenGate Parameters/Options	B-17

Preface

This preface describes the document accessibility features and conventions used in *Oracle GoldenGate Studio Help*.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

Related Information

The Oracle GoldenGate Product Documentation Libraries are found at

Oracle GoldenGate

Oracle GoldenGate Application Adapters

Oracle GoldenGate for Big Data

Oracle GoldenGate Director

Oracle GoldenGate Plug-in for EMCC

Oracle GoldenGate Monitor

Oracle GoldenGate for HP NonStop (Guardian)

Oracle GoldenGate Veridata

Oracle GoldenGate Studio

Additional Oracle GoldenGate information, including best practices, articles, and solutions, is found at:

Oracle GoldenGate A-Team Chronicles

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Introducing Oracle GoldenGate Studio

This chapter introduces Oracle GoldenGate Studio and includes the following sections:

- Introduction
- How Do I Get Started?

1.1 Introduction

Oracle GoldenGate Studio enables you to design and deploy high-volume, real-time replication by automatically handling table and column mappings, allowing drag and drop custom mappings, generating best practice configurations from templates, and contains context sensitive help. With Oracle GoldenGate Studio, users new to Oracle GoldenGate can start replicating data with minimal effort while experienced users have access to GoldenGate's advanced replication options. Users new to Oracle GoldenGate can start replicating data with minimal questions.Oracle GoldenGate Studio provides you with the following abilities:

- Quickly create, modify, validate, deploy, and reuse GoldenGate best practice designs.
- Define data flows once and deploy to literally thousands of locations.
- Graphically filter, map, and transform data.
- Apply global rules and exceptions.

1.2 How Do I Get Started?

Oracle recommends that you familiarize yourself with Concepts and Terminology and Relating Properties Inspector Options to Oracle GoldenGate Commands and Parameters so that you have an understanding of what you will encounter in the product and documentation.

You can follow the basic steps outlined in the following table to create and deploy your replications:

Roadmap of Tasks

Begin by adding new database and GoldenGate connections to your Global Resource Library, see Understanding Projects.

Use the wizards to create a Project, Replication Solution, and Deployment Profile. By default each wizard will invoke the next. Solutions define the replicat process. The Solution and Deployment Profile wizards provide you with pre-configured templates, see Understanding Solutions.

Roadmap of Tasks

Solution objects own Mapping groups, which describe the logical view of the replication process. Use AutoMap or manually map schema, table, and column mappings then assign them to your replication paths, see <u>Understanding Mapping Groups</u>.

Create a Mapping Groups and assign to the appropriate replication paths. You can reuse Solution Mapping Groups in multiple replication paths for that solution and Global Mapping Groups across in multiple replication paths across Project, see <u>Understanding Mapping Groups</u>.

Add, remove, and fine tune any Oracle GoldenGate option or parameter, see Using the Properties Inspector.

Deploy the Solution online to live Oracle GoldenGate instances or generate the parameter and obey files locally for manual deployment, see, Understanding Deployment Profiles

Define any additional physical resources and assign them to your deployment profiles via drag and drop from the Global Resource Library to the Deployment Profile diagram, see Understanding Deployment Profiles

Solutions also own one or more Deployment Profiles which describe the physical attributes of a particular replicat deployment. You can create multiple deployment profiles. For example, separate profiles for development, testing and production for a single Solution, see Understanding Deployment Profiles

Start, stop, and monitor all physical processes, see Monitoring

View deployment history information, see Understanding Deployment Profiles

Export solutions and mappings to XML files that can be imported by other Oracle GoldenGate Studio users, see Using the Projects Navigator.

Using the Interface

This chapter describes the Oracle GoldenGate Studio user interface and includes the following sections:

- **Understanding the User Interface Basics**
- **Setting Your Preferences**
- Using the Projects Navigator
- Using the Editor Area
- Using the Resources Navigator
- Using the Properties Inspector

2.1 Understanding the User Interface Basics

Oracle GoldenGate provides highly optimized user interface for easy creation, modification, and deployment of Oracle GoldenGate replication solutions.

There are two visible sections that appear when Oracle GoldenGate Studio is started. The Project Navigator to the left and the Start Page to the right.

Screens shown in this guide may differ from your implementation, depending on the skin and icons used. Any differences are cosmetic.




Figure 2-1 Oracle GoldenGate Studio Main Window

The interface includes the tabbed editor area with a selection of other windows. The primary windows used with the editor area when designing and deploying GoldenGate replication solutions are:

- Projects Navigator
- Resources Navigator
- Properties Inspector
- Components Window
- Log Messages Window
- Security Navigator

You can also use the **Tab** key to change focus within a component and keyboard shortcut **Ctrl+Tab** to change focus between different components.

2.1.1 Oracle GoldenGate Studio Repository Login

This is used to connect to Oracle GoldenGate Studio. The required connection details are:

- **LoginName**: Name of the login defined to the repository.
- User: Oracle GoldenGate Studio user name.
- Password: Oracle GoldenGate Studio user password.

You can click **New** to create a new Oracle GoldenGate Studio login. When you save your first repository connection definition you can save it using a secure wallet. The secure wallet itself is password protected.

Click Edit to modify the existing Oracle GoldenGate Studio login with the Repository Connection Information Editor.

Click **Copy** to copy a current login definition.

Click **Delete** to delete the existing Oracle GoldenGateStudio login.

For more information on repository database tables, see SNP_REV Tables Reference.

Note:

To improve performance, the repository database needs to be in the same LAN as the machine using Oracle GoldenGate Studio.

2.1.2 Menu Options

The menu options available in Oracle GoldenGate are as follows:

2.1.2.1 The File Menu

This menu is mainly used for file related activities such as:

- New: Used to create a new project, solution, deployment profile, mapping group, data server connection, Oracle GoldenGate instance connection, and global mapping group.
- Open: Used to open file.
- **Close**: Used to close the current editor tab.
- **Close All:** Used to close all the open editor tabs.
- Delete: Used to delete the currently selected object. If nothing is selected, this is grayed out.
- Save: Used to save any changes done in the current editor tab.
- **Save All**: Used to save the changes in all open editor tabs.
- Page Setup, Print, Print Preview, Print Area: Used to set up the print options.
- Exit: Used to quit Oracle GoldenGate Studio.

2.1.2.2 The Edit Menu

The Edit menu is mainly used for editing locally generated parameter and obey files. Any edits to these files will not be retained in the repository and will be overwritten the next time files are generated. Functions include:

- **Cut**: Used to cut the selected item.
- **Copy**: Used to copy the selected item.
- **Paste**: Used to paste the selected item.
- **Delete**: Used to delete the selected item.
- **Duplicate Selection**: This is grayed out.

- **Multi-Cursor**: Used to enable multi-cursor functionality. This menu is available when a text file is opened in editor.
- Select All: Used to select all the available on screen items.
- **Block Selection**: Used to select a text block. This menu is available when a text file is opened in editor.
- Properties: Used to open the Properties Inspector for an item.

2.1.2.3 The View Menu

The View menu is mainly used for viewing of toolbar, status bar and related viewing areas. Functions include:

- Editor: Used to display the options for editor.
- **Show Toolbars**: Used to view different toolbars such as Main, Code Editor, Properties, and Structure.
- **Show Status Bar**: Used to display the status bar.
- **Refresh:** Used to refresh the viewing area. If refresh is done on an editor tab, a dialog box is displayed to confirm if you wish to revert back to the last saved copy. It can be used as an alternative to undo.
- Full Screen: Used to display the product in full screen mode.
- Show Only Editor: Used to display only the editor area.

2.1.2.4 The Search Menu

The Search menu is used to find individual items in Oracle GoldenGate Studio. The available options are:

- Find: Used to find a particular item.
- **Find Next**: Used to find the next instance of a particular item.
- **Find Previous**: Used to find the previous instance of a particular item.

2.1.2.5 The Diagram Menu

The Diagram menu is used to view and optimize the diagrams. This menu is visible only when Solution Editor or Deployment Profile editor is selected. The options include:

- **Generate GoldenGate Files...**: Used to generate the GoldenGate files. The specified location must exist to complete this operation.
- **Deploy**: Used to deploy the solution. The status of the deployment action is displayed in the Messages log. Online deployment is possible at solution level, Oracle GoldenGate instance level, host level, and processes level. This option is enabled only when an Oracle GoldenGate instance is associated with an actual Oracle GoldenGate instance resource.
- **Validate Deployment Profile**: Used to validate the deployment profile. The validation checks if any database specific options were incorrectly used.

For example, if you indicated in the GoldenGate connection that the database was Oracle but tried to deploy to SQL Server, the validation will connect to the GoldenGate instance and a warning is displayed in Messages log if any Oracle specific options like integrated capture were used.

- Synchronize Profile with solution: Used to synchronize the deployment profile with a solution. This option is enabled only when the profile is not synchronized with the solution.
- **Start**: Used to start the selected process.
- **Start...**: Used to start the selected process with additional options.
- **Stop**: Used to stop the selected process.
- Kill: Used to kill (terminate) the selected process.
- Optimize Graphic Size: Used to set the optimal size of the graphic element.
- **Bring to Front**: Used to bring the selected graphic to the top layer.
- **Send to Back**: Used to send the selected graphic to the bottom layer.
- **Zoom**: Used to select the selected graphic to the required zoom level. You can select a defined zoom level, zoom in, zoom out, fit window, or zoom to a selected level.

2.1.2.6 The OGG Menu

The OGG (Oracle GoldenGate) menu includes the following:

- **Connect**: Used to connect to the repository.
- **Disconnect**: Used to disconnect from the repository.
- **Repository Information**: Used to display detailed information about the Studio Connection and Database Connection. The Studio Connection includes the Studio Login Name and password that was defined while creating the repository. One account can have the SUPERVISOR privilege while other accounts are non supervisor. SUPERVISOR is able to create and modify other users. The Database Connection includes the database user name for the repository schema and associated password, Driver Name which is always oracle.jdbc.OracleDriver and the JDBC URL.
- Change Current User's Password: Used to change the password for the current user. User have to type both the existing and new password.
- **Solution**: Used to synchronize all profiles for a solution.
- **Deployment**: Used to online deploy, generate the Oracle GoldenGate parameter and obey files for offline deploy, and to validate the deployment profile.

2.1.2.7 The Tools Menu

The Tools menu includes the following:

• **Preferences**: Used to set the preferences. See Preferences section for more information.

2.1.2.8 The Window Menu

The window menu is used to display different window within the editor. The available options are:

- Projects Navigator: Used to display the Projects Navigator window. You can view
 all the available projects, solutions, deployment profiles, and mapping groups.
- Security Navigator: Used to display the Security Navigator window.

This is grayed out for non supervisor user.

- **Components**: Used to display the Components window. Components are only displayed when the Solution diagram editor is selected.
- Extension Diagnostics: Used to display the extension logs.
- Log: Used to display the Log Messages Explorer.
- **Properties**: Used to display the Properties Navigator window.
- **Resources**: Used to display the Resources Navigator window. The main components are Global Mappings, OGG Instances, and Database Connections.
- **Structure**: Used to view the structural representation of data of the currently selected profile. The Structure window is enabled only when the Solution and Deployment Profile diagrams are selected.
- **Thumbnail**: Used to display a representation of the current diagram for quick navigation to a specific element on the diagram.
- **Configure Window**: This menu item consists a list of sub menu items to set the window behavior such as minimize, maximize, float and so on.
- Reset Windows To Factory Settings: Used to reset all windows to their default layout.
- **Assign File Accelerator**: Used to assign the file accelerators.
- Close Profile *profile name*: Used to close the active window. This menu item depends on what is selected.
- Close All Documents: Used to close all open documents within the editor.
- Close other documents: Used to close other documents.
- **Documents**: Used to display the documents window which lists all available documents. You can switch to a particular document, sort, save, or close a document.

2.1.2.9 The Help Menu

The help menu includes the following options:

- **Search**: Used to search the online help system.
- Table of Contents: Used to display the table of contents for the online help system.
- **Documentation Library**: Used to open a browser window with a link to the related documentation.

- Start Page: Used to display the Oracle GoldenGate product information page. You can learn and explore the tutorials and help topics from this page.
- OGG Studio Forum: Used to open a browser window with a link to Oracle GoldenGate studio forum posts.
- Oracle Technology Network: Used to open a browser window with a link to Oracle Technology Network.
- **About**: Used to display the About dialog box with version information.

2.2 Setting Your Preferences

You can set the preferences for Oracle GoldenGate Studio including the environment, audit behavior, and display.

The main components of this window are:

- Environment: Used to set the undo level, navigation level, and look and feel. All warning messages can be reset from here.
 - Log: Each activity can be logged. You can set the directory for saving log files, maximum number of log lines, and log color options.
- Audit: This is grayed out.
- Code Editor: Used to open the editor.
- Database: Used to configure different database options. You can also select the JDBC driver from the list of registered drivers, add a new driver, or delete an existing driver.
- Diagrams: Used to set the options for diagrams.
 - Annotation: Used to set the annotation options like color and font.
- Parameter Editor: Used to open the parameter editor.
- Web Browser and Proxy: Used to configure web browsers, proxy settings and internet files.
 - Web Browsers: Used to set the default web browser.
 - Proxy Settings: Used to configure the proxy settings such as no proxy, system default proxy, automatic proxy settings, and manual proxy settings.
 - Internet Files: Used to enable cookies and clear all existing cookies.

2.2.1 How to Set Preferences

To set preferences, do the following:

- **1.** In the Oracle GoldenGate Studio window, navigate to **Tools > Preferences**.
- **2.** Modify individual items as per requirement.

2.3 Navigation Using the Keyboard

The following section describes the common methods of moving the cursor in Oracle GoldenGate Studio.


- · Cursor control
- Operate Buttons
- Select Checkboxes
- Dropdown Lists and Combo Boxes
- List Boxes
- Radio Buttons
- Shuttles
- Sliders
- Spin Controls
- Text Fields
- Navigating Complex Controls

For more information, see OLINK:OJDUG172

2.4 Using the Projects Navigator

The Projects Navigator is used to browse and select existing solutions and solution components such as **Deployment Profiles**, and **Mapping Groups**. The list of all active projects are available through the **Project** drop-down option. You can refresh the current project using the **Refresh Projects Window** button.

Figure 2-2 Projects Navigator



You can perform the following project related tasks using the **Project Menu**:

- Open project: Opens the editor for the currently selected project. If no project is selected, this is grayed out.
- New project: Create a new project.
- Duplicate project: Duplicate an existing project and edit it after duplication.
- Delete project: Delete an existing project.
- Import project: Import a project XML file that was exported from Oracle GoldenGate Studio.
- Export project: Export a project to an XML file.

2.5 Using the Editor Area

The editor area is used to visualize the organization and flow of the logical replication solution with the physical objects for the physical deployment profile. You can add data server and replication path components visually using drag-and-drop to evolve the solution. The deployment profile architecture can be changed by selecting any part of the replication path in the deployment profile diagram and selecting the desired architecture template from the Properties Inspector.

Both the solution and deployment profile editors have an **Overview** tab. The solution overview tab contains the solution definition and description and deployment summary for all deployment profiles associated to that solution. The deployment profile editor overview tab contains the deployment profile description, deployment history for this profile only, monitoring, and deployment configuration options.


2.6 Using the Resources Navigator

The resources navigator, or the global resource library lists all the available resources such as:

- Big Data System: All the available Big Data Systems.
- Database: All the available databases.
- Global Mapping Group: Global mapping groups can be assigned to any replication path of any solution across all projects. Mapping groups created for a solution in the Projects Navigator can be copied to the global mapping groups or created directly from the Resources Navigator.
- Oracle GoldenGate Instance: The available Oracle GoldenGate instances.

The Resources Navigator looks like:

Figure 2-3 Resources Navigator



There are three ways to add a new global resource. If any type of resource is not added then you can add it by selecting the **New** button in the Resources Navigator toolbar, select the New button in the Oracle GoldenGate Studio toolbar, or select New under File menu, and then select the resource type you want to add. If a resource type has already been added, you right-click the resource category and select New Resource

Type. You can also add a Global Mapping Group by right-clicking a mapping group in the Projects Navigator and selecting Copy to Global Resource Library.

Figure 2-4 Adding New Resources through Resources Navigator




You can change the properties of existing resources by using the **Properties** context menu. You can also use the keyboard shortcut **Ctrl+Tab** to navigate to Resources Navigator, use the **Tab** and **arrow** keys to select the particular resource, and use **Shift** + **F10** to view the context menu.

2.6.1 Add a New Database Connection

New database connections are used only for table metadata to facilitate table mapping and are not used to define connections used by capture and apply processes. Capture and apply connections are defined in the Properties Inspector in the Deployment Profile.

A new database connection wizard looks as follows:

Figure 2-5 New Database Connection



- 1. Select the Database resource type in the Resources Navigator window and rightclick to select **New Database Connection**.
- **2.** In the New Data Server Connection window, add the following:
 - **a.** Connection Name: The name of the new connection. The resource is listed in the Resources Navigator with the name mentioned here.
 - **b.** Connection Type: Connection types are Oracle (JDBC), Generic JDBC, MySQL, SQLServer, DB2 UDB, and Teradata. Changing of database type is not supported after connection is created.
 - c. The User name and Password to connect to the database. If you uncheck Save Password check box during connection creation and if you want to expand the Database node after re-connecting to repository, Database node expansion will ask you to enter the password to show all the nodes under database connection.
 - **d.** The role as SYSDBA or SYSOPER. This can be left blank when the user is not SYS. Else, you have to select the role.
 - **e.** The JDBC settings.

By default, Oracle GoldenGate Studio provides drivers for Oracle, MySql, SQLServer, Informix, Sybase and DB2 UDB. Additional database drivers that are not provided with the product can be configured by using **Tools** menu, then **Preferences**, **Database**, and **JDBC Driver Options**. Once a data server connection is created, you can browse objects under the database in the Resources Navigator and the information from the database navigator can be used for viewing the metadata and mapping.

To add the Teradata connection, you have to load the Teradata drivers as follows:

- i. In the New Data Server Connection window, select Teradata as the connection type.
- ii. Click the select Library button.
- iii. In the Select Library window, click the **New...** button.
- iv. In the Create Library window that opens, click on Add Entry... button.
- v. In the Select Path Entry window that opens, browse to the location where the Teradata drivers are stored and select the drivers. Click the **Open** button.
- vi. Click **OK** if the drivers are correctly added under Class path.
- vii. In the Select Library window, you can see the newly added Teradata drivers. Click **OK**.
- **viii.** Provide a valid Username and Password and click **Test Connection** to perform a connection test or **OK** to proceed with the connection.




Figure 2-6 The Select Library Dialog

3. Click OK to create a new Database resource.

You can also test the connection using **Test Connection** button before creating the new resource.

Note: Teradata is supported as a target only database but you can drag-and-drop Teradata tables as a source database in the mapping editor. This is possible as mapping is a logical concept and no check is performed by Oracle GoldenGate Studio.


Note: The generate to function for Teradata and DB2 UDB tables depend on JDeveloper functionality. DB2 UDB to DB2 UDB and Teradata are not supported.

2.6.2 Add a New Big Data System Connection

A new Big Data system can only be used as a target. Properties for the connection can be defined in the Properties Inspector in the Deployment Profile.

A new Big Data system connection wizard looks as follows:

Figure 2-7 New Big Data System Connection




- Select the Big Data System resource type in the Resources Navigator window and right-click to select New Big Data System Connection.
- In the New Data Server Connection window, add the following:
 - Name: The name of the new connection. The resource is listed in the Resources Navigator with the name mentioned here.
 - Description: A short description about the new Big Data System.
- Click OK to create a new Big Data System resource.

2.6.3 Add a New Global Mapping Group

The New Global Mapping Group wizard defines a container for table mappings but does not guide you through the table mapping process. To learn more about defining table mapping see Understanding Mapping Groups

A new Global Mapping Group wizard looks as follows:

Figure 2-8 New Global Mapping Group



To add a new Global Mapping Group:


- 1. Click the **New** button on the Resources Navigator window or right click on the database icon and select **New Global Mapping Group Connection**.
- **2.** Enter the name of the new connection.
- **3.** Enter a short description to identify the resource.
- 4. Click OK.

2.6.4 Add a New Oracle GoldenGate Instance

The Add a New Oracle GoldenGate Instance dialog defines a connection to an existing GoldenGate installation. That installation must already have the GoldenGate manager and jAgent processes running

A new Oracle GoldenGate Instance dialog looks as follows:

Figure 2-9 New Oracle GoldenGate Instance Connection



To add a new Oracle GoldenGate Connection:

- **1.** Click the **New** button on the Resources Navigator window or right click on the database icon and select **New Oracle GoldenGate Instance Connection**.
- **2.** Under **General** section enter the name and description for the new connection.
- **3.** Under **Host Information** enter Host Name. It is the DNS name of the server where Oracle GoldenGate is installed.
- **4.** Under **Oracle GoldenGate Information** enter the following:
 - GoldenGate Version: You can also select the version from the drop down list while working offline. If there is an active connection and incorrect version is

entered, the correct information is updated to overwrite the incorrect version when the **Test Connection to GoldenGate** button is placed.

- GoldenGate Database Type: The database type for which the connection is created. It gets automatically updated when Test Connection to GoldenGate is clicked. You can also select the version from the drop down list while working offline.
- GoldenGate Port: The port number for the Oracle GoldenGate manager process.
- Agent Username: The JAgent name as specified by the jAgent.username property in the config.properties file of the jAgent at the time of installation.
- Agent Password: The password for the corresponding username.
- Agent Port: The jAgent port as specified by the jagent.jmx.port property in the config. properties file of the jAgent. If the agent mode is OEM, then you have to use jagent.rmi.port, if the agent mode is OGGMON then you have to use jagent.jmx.port.
- **5.** Click **Test Connection to GoldenGate** to verify if the connection is working. The version and database type is automatically updated on successful connection.

2.7 Using the Properties Inspector

The Properties Inspector is used to view and edit the attributes of the selected artifacts in the solution diagram, deployment profile diagram, and mapping editor. You can view a tool tip with a description of that particular parameter with a right-click in Properties Inspector of the Deployment Profile. The Properties Inspector is dynamic and the attributes correspond to the different types of items selected in the editor.

Map 1 - Properties Q Find ? **∃** General Map 1 Name: Description: ■ DDL Replication **⊞ Column Match ⊞ DML Conversion**

Figure 2-10 Properties Inspector

Relating Properties Inspector Options to Oracle GoldenGate Commands and Parameters contains a list of all of the options that can appear in the Properties Inspector of the Deployment View.

2.7.1 How to Use the Properties Inspector

To use the Properties Inspector, do as follows:

- **1.** In Oracle GoldenGate Studio, navigate to **Window** menu and select **Properties** to display the Properties Inspector.
- **2.** In the Solution Editor, Mapping Editor, or Deployment View select an item for which you want to change the property.
- 3. In the Properties Inspector, change the corresponding properties for that particular item. Some items, such as conflict resolution in the mapping editor, requires clicking a dynamic gear icon that appears to the far right when you mouse over the attribute.
- **4.** Save the changes using the **Save** button on the toolbar or using the **Save** under **File** menu. The changes in process parameters are available only after redeployment or after regeneration of parameter files.

Working with Solutions and Deployment Profiles

This chapter explains how to use solutions and deployment profiles to configure and manage your replication solutions using Oracle GoldenGate Studio and includes the following sections:

- Understanding Projects
- **Understanding Solutions**
- Understanding Deployment Profiles

3.1 Understanding Projects

A project is a container for a replication solution. Once created, they are presented as a drop-down list at the top of the Projects Navigator. For more information, see Using the Projects Navigator.

3.1.1 Creating a Project

- 1. Click the **New** button on the toolbar, from the **File** menu, select **New**, or select New Project... from the Project Menu drop down list in the Projects Navigator.
- **2.** Select **Create New Project**, then click **OK**.
- **3.** Enter a name for you project. You can add a description as well.
- 4. (Optional) You can deselect the Continue to Solution Wizard if you do not want to immediately create a solution for your new project.
- 5. Click OK.

Your project is created and is displayed in the list of projects.

3.2 Understanding Solutions

Solutions represent the replication patterns supported by Oracle GoldenGate and are contained in a project. The concept of replication paths and mapping groups are all part of the logical definition of a solution. Once the logical design is in place, you can create multiple deployment profiles each with its own deployment template to match the physical elements of your replication environments. A single Oracle GoldenGate project can have multiple solutions.

One solution and its table mapping groups can be deployed to any number of physical locations.

A typical solution contains:

- Deployment Profiles: Describes the deployment architectural template, physical resources and additional deployment options.
- Mapping Groups: A collection of source and target table mappings and associated replication logic such as filtering and conflict detection rules. Table must be dragand-dropped from the Resources Navigator to the Mapping Editor. Then, source and target table mapping associations can be automatically generated using Automap or created by drag-and-drop from source to target and target to source. Additionally, wildcard characters (*) can be used in the mappings at the schema and table level. For Oracle multitenant support you must edit the schema name manually to include the database name.


Readily available solution templates are available in Oracle GoldenGate Studio and they greatly reduce the time required to create and deploy a solution.

3.2.1 Creating a New Solution

You can create a new solution as follows:

1. In the Projects Navigator, right-click and select New.

Figure 3-1 New Solution Dialog



- 2. Provide a name for the solution with an optional description, then click Next.
- **3.** Select a solution template from Unidirectional, Bidirectional, or Hub and Spoke. If Hub and Spoke is selected then enter the number of spokes.

A description appears for the selected template.

Create New GoldenGate Solution - Step 2 of 2 × Solution Template Select a GoldenGate Solution template design. Solutions can be customized Solution subsequently. Solution Template ⊶ Unidirectional Captures changes from a source data store and applies them to a target data store. 🗫 Bidirectional 🞇 Hub and Spoke Continue to Deployment Profile Wizard <u>F</u>inish Cancel <u>H</u>elp < Back

New Solution Template Figure 3-2


- 4. (Optional) You can deselect the Continue with Deployment Profile Wizard if you do not want to immediately create a deployment profile for your new solution.
- 5. Click Finish.

Your solution is created in the open project and is displayed in the Solutions Navigator.

3.3 Understanding Deployment Profiles

The deployment profile is part of the Oracle GoldenGate Studio solution. It describes the physical attributes of the replication solution. There can be more than one deployment profile per solution. For example, one deployment profile for the development environment, one for the test environment, and one for production.

Figure 3-3 Sample Deployment Profile Logical View



3.3.1 Components of the Deployment Profile

The different components of the deployment profile are:

3.3.1.1 Name of the Oracle GoldenGate profile

This is used to add a name and optional description to the deployment profile.

3.3.1.2 Deployment Architecture Template

This is used to define the architecture of deployment profile. When using the Deployment Profile wizard the selected architecture template is applied to each and every replication path in the solution. However, in the Properties Inspector, individual replication paths may have different architecture templates.

The available architecture templates are:

Source, Target: The source and target deployment environments contain Oracle GoldenGate instances local to the data servers. Capture and apply will both be done locally.

Target Only (Remote Source): There is only one Oracle GoldenGate instance and it is local to the target data server. Capture will be done remotely from the target.

Source Only (Remote Target): There is only one Oracle GoldenGate instance and it is local to the source data server. Apply will be done remotely from the source.

Hub Only (Remote Source and Target): There is only one Oracle GoldenGate instance and it is on a stagging server. Capture and apply are both done remotely.

Source, Hub, Target: There are three Oracle GoldenGate instances. One is local to the source data server and one is local to the target data server. Capture and apply are both done locally and data will be transmitted through a third Oracle GoldenGate instance on a hub between the two.

Hub, Target (Remote Source): There are two Oracle GoldenGate instances, one on a staging hub and one on the target data server. Capture is done remotely from the hub while apply is done locally at the target.

Source, Hub (Remote Target): There are two Oracle GoldenGate instances, one is on the source data server and one is on a staging hub. Capture is done locally from the source data server while apply is done remotely from the target data server from the

Single Host (Local Source and Target): There is only one host and it contains both the Oracle GoldenGate instance and source and target data servers.

3.3.1.3 Assign Physical Resources

This is used to assign your resources to the source, the target, and the hub (if applicable) of the replication path.

The resource assignment section contains:

Replication Path: It describes the data store mapping information.

Source: Select the Data Server and Oracle GoldenGate Instance to use as the source of each replication path.

Target: Select the Data Server and Oracle GoldenGate Instance to use as the target of each replication path.

Hub: Select the Data Server and Oracle GoldenGate Instance to use as the hub of each replication path.

Note:

Resource assignment can be done through the Deployment Profile editor by dragging and dropping resources from the Resources Navigator to the appropriate diagram elements and through the Properties Inspector.

3.3.1.4 Deployment Configuration

This is used to select several additional options such as initial load of all targets, and starting of Oracle Data Pump.

Deployment Settings:

Initial load of all targets: Select if data must be copied between systems before changes to the data are applied.

Start All Oracle GoldenGate Processes: Select which (or all) processes should be started after deployment:

- **Start Capture Process**
- Start Pump Process
- Start Apply Process

Note:

Processes can be started only during online deployment.

Replication Path Settings:

- Replication Paths: Display the selected replication path.
- OGG Initial Load: Start Oracle GoldenGate initial load processes.
- ODP Initial Load: Start the Oracle Data Pump initial load processes.

Oracle Data Pump Settings:

- Remote Link: Enables an export from a (source) database identified by a valid database link. The data from the source database instance is written to a dump file set on the connected database instance.
- Parallelism: Specifies the maximum number of threads of active execution operating on behalf of the export job. This execution set consists of a combination of worker processes and parallel I/O server processes.

3.3.2 Consolidation of Capture

Oracle GoldenGate Studio uses a single capture for a single database. This result in significant performance enhancement.

Single capture is mainly used in Hub and Spoke solution template and the following deployment architecture template:

- · Source, Target
- Source Only
- Source, Hub, Target
- · Source, Hub
- Single Host

To use multiple capture for a single database, multiple solutions must be created.

3.3.3 Toolbars in the Deployment Profile

The toolbar buttons are described in sequence with the following image:

Figure 3-4 Deployment Profile Toolbar



Some buttons like validate and start are context sensitive and change color when enabled.

- **Zoom In**: Click to increase size of the on screen components
- **Zoom Out**: Click to decrease size of the on screen components.
- **Percent View**: Click to set the view to a predefined percentage value.
- **Perform Layout**: Click to automatically rearrange the components in the deployment view in a organized way. You can save the layout using the **Save** button in the toolbar or selecting **Save** under **File** manu. The data flow is from left to right.
- **Synchronize Profile with Solution**: Click to synchronize the deployment profile with a solution. This option is enabled only when the profile is not synchronized with the solution.
- **Deploy Solution**: Click to deploy the solution. The status of the deployment action is displayed in the Messages log. Online deployment is possible at solution level, Oracle GoldenGate instance level, host level, and processes level. This option is enabled only when an Oracle GoldenGate instance is assigned with an actual Oracle GoldenGate instance resource.
- Validate Deployment Profile: Click to validate the deployment profile. The
 validation checks if any database specific options were incorrectly used. For
 example, if you indicated in the GoldenGate connection that the database was
 Oracle but tried to deploy to SQL Server, the validation will connect to the
 GoldenGate instance and a warning is displayed if any Oracle specific options like
 integrated capture were used. Validation warnings, if any, are displayed in the
 Messages log.
- **Generate GoldenGate Files:** Click to choose a local directory in which GoldenGate files will be generated.
- *Start the Selected Process*: Click to start the selected process.
- **Stop the Selected Process**: Click to stop the selected process.
- Kill the Selected Process: Click to kill the selected process.

3.3.4 Creating a New Deployment Profile

To create a new deployment profile:

- 1. Name your Deployment Profile: Provide a name for the deployment profile and click Next. Clicking Finish creates a profile that defaults the Replication Path, Source, and Target using automatically generated names and settings for the solution.
- **2. Deployment Template**: Select an architecture to be used as the template for the solution. The deployment architecture template describes where Oracle GoldenGate is installed in relation to data servers. The selected template is applied to all replication paths and can be customized on a replication path-by-replication path basis subsequently. You can change a previously selected deployment architecture template by clicking the template link in the Deployment View and selecting a new template in the Properties Inspector.

Deployment Architecture Template	Description
Source, Target	The source and target deployment environments contain Oracle GoldenGate instances local to the data servers. Capture and apply will both be done locally.
Target Only (Remote Source)	There is only one Oracle GoldenGate instance and it is local to the target data server. Capture will be done remotely from the target.
Source Only (Remote Target)	There is only one Oracle GoldenGate instance and it is local to the source data server. Apply will be done remotely from the source.
Hub Only (Remote Source and Target)	There is only one Oracle GoldenGate instance and it is on a stagging server. Capture and apply are both done remotely.
Source, Hub, Target	There are three Oracle GoldenGate instances. One is local to the source data server and one is local to the target data server. Capture and apply are both done locally and data will be transmitted through a third Oracle GoldenGate instance on a hub between the two.
Hub, Target (Remote Source)	There are two Oracle GoldenGate instances, one on a staging hub and one on the target data server. Capture is done remotely from the hub while apply is done locally at the target.
Source, Hub (Remote Target)	There are two Oracle GoldenGate instances, one is on the source data server and one is on a staging hub. Capture is done locally from the source data server while apply is done remotely from the target data server from the hub.
Single Host (Local Source and Target)	There is only one host and it contains both the Oracle GoldenGate instance and source and target data servers.

Select the deployment architecture template from the list of available templates and click Next.

Create New GoldenGate Deployment Profile - Step 2 of 4 Deployment Template Select your Deployment Architecture Template. The Deployment Architecture Deployment Profile Template describes where GoldenGate is installed in relation to the data servers (such Deployment Templat as, databases, Java, or big data). The template is applied to all replication paths and can be customized on a path-by-path basis subsequently. Physical Resources ■ gg ■ gg Source, Target Deployment Options The source and target deployment environments contain data store instances and OGG instances. 🗐 🛢 🙎 Target Only (Remote Source) gg Source Only (Remote Target) ■ gg Hub Only (Remote Source and Target) 🗎 gg gg 🗎 gg Source, Hub, Target gg gg Hub, Target (Remote Source) <u>H</u>elp < Back Next ><u>F</u>inish Cancel

Figure 3-5 Deployment Architecture Template

The contents of the Physical Resources step is populated based on your deployment template selection.

3. Assign Physical Resources: Use this to assign your resources to the source, target, and hub (if applicable) of the replication path.

Source

Select the Data Server and Oracle GoldenGate Instance to use as the *source* of each replication path.

Target

Select the Data Server and Oracle GoldenGate Instance to use as the *target* of each replication path.

Hub

Select the Data Server and Oracle GoldenGate Instance to use as the *hub* of each replication path.

Note:

Resource assignment can also be done through the Deployment Profile editor by dragging and dropping resources from the Resources Navigator to the appropriate diagram elements and through the Properties Inspector.

The deployment template is the same for all replication paths in a given solution. Some templates do not require data stores.




Figure 3-6 Physical Resources in Deployment Profile

4. Deployment Options: Select or deselect any applicable Oracle GoldenGate starting process deployment options.

Initial load of all targets

Select if data must be copied between systems before changes to the data are applied.

Start All Oracle GoldenGate Processes

Select which (or all) processes should be started after deployment:

- Capture Processes
- Pump Processes
- **Apply Processes**

Note:

Processes can be started only during online deployment.

Create New GoldenGate Deployment Profile - Step 4 of 4 **Deployment Options** Select Deployment Options. Deployment Options describe the deployment options Deployment Profile for your deployment. This applies to all replication paths in the deployment. You can Deployment Template modify these options subsequently under the Deployment Configuration tab in the Deployment Profile Overview Editor. Physical Resources Initial load of all targets **Deployment Options** ✓ Start All GoldenGate Processes ✓ Start Capture Processes ✓ Start Pump Processes ✓ Start Apply Processes

<u>F</u>inish

Cancel

Figure 3-7 Deployment Options

<u>H</u>elp

Click Finish. Your deployment profile is created and added to the Solution.

< Back

Working with Mappings Groups

This chapter explains how to use local and global mappings groups to configure and manage your replication options using Oracle GoldenGate Studio and includes the following sections:.

- Understanding Mapping Groups
- How to Create a Mapping Group
- How to Assign Mapping Groups to Replication Path
- How to Copy And Share Mapping Groups

4.1 Understanding Mapping Groups

In Oracle GoldenGate Studio, the term mapping group is used to explain a collection of source and target table mappings and associated replication logic such as filtering and conflict detection rules. First, the tables must be drag and dropped or added using the keyboard shortcuts from the Resources Navigator to the Mapping Editor. Then, source and target table mapping associations can be automatically generated using Automap or created by drag-and-drop or using keyboard shortcuts from source to target and target to source. Additionally, wildcard characters (*) can be used in the mappings at the schema and table level. If you drag and drop the schema name it will automatically use a wildcard, indicating all tables. For more on wildcard logic see the Orcale GoldenGate Reference manual. For Oracle multitenant support you must edit the schema name manually to include the pluggable database name.

Only the metadata from the database connections are used when creating mapping groups. This means mapping groups are logical constructs which can be assigned to multiple replication paths. Mapping groups local to a solution can be associated with any replication path in that solution, while global mapping groups located in the global resource library, can be used for any replication path for any solution across all projects. When a mapping group is modified that change will be reflected in all replication paths referencing that mapping group. More than one mapping group can be assigned to a replication path.

For example, if you have 100 stores with the same application schema reporting back to a central data warehouse, you only have to define that mapping group once and you can apply it to all 100 replication paths. Any changes to that mapping group will only needs to be made once and will be reflected in all 100 replication paths.

4.1.1 Schema and Table Mapping

Schemas are not directly mapped to other schemas. Tables in the schemas are mapped other tables. To map all tables in a schema you can either highlight all of the tables in the global resource library and drag and drop them into the mapping editor or you can drag and drop the schema name, which will then use a wildcard (*) for all tables. If

you're replicating DDL and want to capture new tables then always use a wildcard. Wildcard can also be used with schema names. However, when using a wildcard for schema names, some system schemas will automatically be excluded. To see which schema names will be implicitly excluded when using wildcards, refer Oracle GoldenGate installation document for that database. When using a wildcard for the schema name, the implicitly excluded schemas can be overridden by explicitly listing the schema names.

To map tables or wildcards you can click the **Automap** button and any unmapped target table will be mapped to a source table if the table names are the same regardless if they are in different schemas. Alternatively, in the mapping editor you can drag and drop source and target table names on each other to create the association.

Once tables are mapped you will see the **Source** table name in the **Target** column **Mapped From**. Only the Source table names are listed in this column but a tool tip will provide the source schema name. Double clicking the Target table name or Mapped From table name will take you to the column mapping editor.

In the schema and table mapping editor you can define properties and logic for the entire mapping, source tables, and target tables. The following figure and the table show which properties can be edited based on where you click in the mapping editor.

To use a pluggable database, you have to manually edit the database name to the schema name followed by the database name as schema.database. To use the replicat process from one pluggable database to another, you have to edit the sourcecatalog parameter in the Properties Inspector for the extract and replicat process. To use the replicat process for multiple pluggable databases, you have to edit the mapping editor schema to add the plugabble database name for the replication process.

Oracle Data Pump replication are usually done through databases, tablespaces, schema and table types. Currently, only table type is supported. It requires both the schema name for source and target as well as the table name.

Note: Wildcard mapping are not supported with Oracle Data Pump. No errors are shown during deployment but the data on target side are not loaded.

AutoMap Show All

Source

NORTH

Target

Mapped From

Target

Mapped From

TCUSTORD

T

Figure 4-1 Schema and Table Mapping

ID	UI Element	Properties
1	Map Breadcrumbs	Name and description, DDL replication, global column matching, DML conversions, and global replication error
		responses.

ID	UI Element	Properties
2	Source schema name	Database name, schema name, and exclude schema from source capture. The exclude schema is used when you have used a wildcard for all schemas but want to explicitly exclude certain schemas that would otherwise be included with the wildcard.
3	Source table name	Table name, exclude table from source capture, filter, Where clause, custom SQL execution, event actions, and additional custom properties.
4	Target schema name	Target schema name and exclude schema from target apply
5	Target table name and Mapped From	Target schema name and exclude table from target apply, exception handling, filter, DML conversion, Where clause, table specific replication error responses, custom SQL execution, coordinated apply thread (if applicable), coordinated apply thread range (if applicable), event actions, more settings, and additional custom properties.

When you exclude table on source side a tableexclude parameter is written on source side but corresponding map statements are not be written to target side. Similarly, when you exclude table on target side a mapexclude parameter is written on target side, but corresponding table statements are not written to source side.

Note:

When you have more than one table mapped you will need to drill into column mapping and select the table name to edit all the properties except exclude property. This allows you to apply different logic to different tables.

4.1.2 Column Mapping

You can navigate to the column mapping from the table mapping editor. Double click the Target table name or the **Mapped From** column, or right-click anywhere on the target row that contains the table name and chose Edit Column Mapping from the context menu.


The Oracle GoldenGate runtime engine automatically maps matching column names so column mapping is not required. Column mapping works in the same way as table mapping and you can use Automap and drag-and-drop between Source and Target.

In the column mapping editor you can define properties and logic for Source and Target tables and columns. The following figure and the table show which properties can be edited based on where you click in the mapping editor. It also shows how to select individual table mappings when more than one table is mapped to a target table and how to navigate back to the schema and table mapping editor.

Note:

Selecting the table name in the column mapping editor provides the same options as clicking the table name in the schema and table mapping editor when there is only one source table mapped to the target table.

Figure 4-2 Column Mapping



ID	UI Elements	Properties
1	Map Breadcrumbs showing mapping group name	Selecting here returns to the schema and table mapping editor.
2	Map Breadcrumbs showing table mapping name	If there is more than one source table mapped to this target table, selecting here provides a drop down list of those other mappings and you can navigate to them.
3	Source table name	Table name, exclude table from source capture, filter, Where clause, custom SQL execution, event actions, and additional custom properties
4	Source column name	Column name, exclude column from source capture, force column to be used as (part) of the primary key.
5	Target table name	Target table name, exclude table mapping from target apply, force specific columns to be used as the key, exception handling, conflict detection, conflict resolution, filter, DML conversion, Where clause, table specific replication error responses, custom SQL execution, coordinated apply thread (if applicable), coordinated apply thread range (if applicable), event actions, more settings, and additional custom properties.
6	Target column name and Mapped From	Column name, mapped from (which can contain source column names or custom logic), force column to be used as (part) of the primary key, enable this column for update conflict detection, and enable this column for delete conflict detection.


Note:

Primary key column overrides, conflict detection, and conflict resolution are only present in the column mapping editor.

4.1.3 Automap

The Automap feature automatically maps similarly named tables. Automapping assignments are created from the source to target and not the reverse. The mapping window looks as follows:

Figure 4-3 Automap



4.2 How to Create a Mapping Group

To create a new local or global mapping group:

1. To create a mapping group that is local to the solution, select the Mapping Groups under that solution and right-click to select New. To create a global mapping group, right-click to Global Mapping Group in the Resources Navigator. If the Resources Navigator has no global mapping groups then click the plus icon +in the Resources Navigator, select Global Resource Library, and then select Global Mapping Group.

The Create New Mapping Group or New Global Mapping Group window opens.

- 2. Provide a name and optional description for the Mapping Group and click **OK**.
- **3.** If the mapping editor window does not open automatically, double click the new mapping group in the Projects Navigator or Resources Navigator.
- **4.** Add tables from the Global Resource Library by dragging and dropping them from the library into the source and target panes of the mapping editor.
 - To select a list of tables you can use Shift-click on the first and last table in the set, use Control-click to select multiple individual tables, or use the + button in the source and target mapping editor panes to manually add schema and table names. In the column mapping editor the equivalent + button allows you to add columns manually.
- 5. Drag and drop the table or schema names from either the Source or Target pane to the other pane to create a source/target table mapping. If you drag the tables to a white area it will do an exact 1:1 mapping. If you drag a table name from one pane to the other and drop it directly on the other table name, it will create an explicit mapping.

For example, if Table EMP1 in Source is to be mapped with EMP_BACK1 in Target, drag EMP1 from Source and drop it on EMP_BACK1 at Target. EMP_BACK1 appears as a **Mapped From** table for EMP1 indicating a successful mapping.

You can also use the keyboard to perform the same action. When a source or target schema does not have a reference to any specific Resources Navigator schema and

the name matches a particular database name in the Resources Navigator, a confirmation dialog is displayed to associate the resource. You can select **Yes** to complete the mapping.

If you select a table as target in the Mapping Editor which is not mapped, the Properties Inspector displays a **Mapped From** text box. You can enter the source table name which will be validated against a valid source table references and can be mapped to target table if the source table is valid.

6. You can also use the **AutoMap** button to automatically create mappings for table names that are same between **Source** and **Target**. Source tables can be mapped to more than one Target table and more than one Source table can be mapped to a single Target table.

4.3 How to Assign Mapping Groups to Replication Path

Mapping group is assigned in the solution editor. To assign a local or global mapping group to a replication path, drag the mapping group from the Projects Navigator or Global Resource Library and drop on the replication path or data server in the solution editor. If dropped onto a data server, the mapping group will be automatically associated with every replication path connecting that data server. If dropped on the replication path arrow, the association will be only for that path. You can drag the same mapping group and drop on multiple paths and data servers. These associations are by reference and not copies. Any change to the mapping group is automatically reflected in every replication patch associated with that mapping group.

To remove a mapping group from a replication path, select the replication path in the solution editor and in the Properties Inspector you will see a list of all replication path mapping associations. Select the desired mapping group name and click the red **X** icon to delete. A confirmation dialog appears.

In the Properties Inspector of the replication path, there is a green + icon, which provides an alternative way to add an association between a mapping group and replication path. When the + icon is selected, through a dialog box you can add association for local and global mappings to this replication path.

4.4 How to Copy And Share Mapping Groups

When you right click a local solution mapping group you can see options to copy it to the Global Resource Library, make a copy (duplicate) of the selection within the same solution, and export it to an XML file. The XML file can be used for import in another Oracle GoldenGate Studio repository. You can right-click the global mapping group and export to an XML file that can be imported by other Oracle GoldenGate users outside of your shared environment. The export map dialog supports character set and encryption settings.

You can import both local and global exported mapping groups by right-click to the appropriate Mapping Groups node in the Projects Navigator and selecting **Import**.

The different **Import Types** are:

- Duplication: This mode creates a new object (with a new internal ID).
- Synonym Mode INSERT: This mode tries to insert the same object (with the same internal ID).
- Synonym Mode UPDATE: This mode tries to modify the same object (with the same internal ID).

Synonym Mode INSERT_UPDATE: If no object exists in the target Repository with an identical ID, this import mode will create a new object with the content of the export file. Already existing objects (with an identical ID) will be updated.

Deploying and Monitoring Your Solutions

This chapter describes how to deploy and monitor your solutions and includes the following sections.

- Deploying Solutions
- Overview

5.1 Deploying Solutions

You can choose to deploy your solution either in Online of Offline mode in Oracle GoldenGate Studio.

Online Deploy: Online deployments require that the Oracle GoldenGate instances associated in the deployment profile have both the manager and Oracle GoldenGate Monitor JAgent is installed and running.

See olink:GGAIN

Offline Deploy: Oracle GoldenGate Studio will generate the GoldenGate replication parameter and obey files and save them in a local directory.

The online deployment implicitly runs a validation check by pinging the GoldenGate instances that have been assigned as resources in the deployment profile and ensures that the minimum required parameters have been set for those data server types. Any parameter that is set and is not related to the data server type to which you are deploying will be ignored when generating the parameter and obey files.

You can also explicitly run a validation by selecting the green check mark icon in the deployment profile toolbar.

Before writing the configuration and command files, the JAgent backs up any files it is about to overwrite to the dirtmp directory of the Oracle GoldenGate instance. Any conflicting process will be stopped. If you did not deselect the start option in the Deployment Configuration options the process will be started once the new configuration files are created.

Once a deployment profile has been deployed you can view the deployment history and some simple monitoring matrixes in the Overview tab under Deployment Profile next to the Deployment View tab. Deployment Configuration options can also be found in the Overview tab under Deployment Profile. Those options include starting all GoldenGate processes and performing full initial loads. Currently partial initial loads are not supported.

5.1.1 How to Deploy a Solution

A solution can be deployed in several ways as follows:

Through Deployment Profile Toolbar.

- **2.** Through the context menu in Deployment Profile editor.
- 3. Through the Projects Navigator Deployment Profile Node.

For example, to deploy a solution through the Projects Navigator:

- **1.** In the Projects Navigator, select the Deployment Profile you want to deploy and right-click to select **Deploy**.
- 2. Select between Deploy or Generate GoldenGate Files. Deploy is used for online deployment while the files generated by Oracle GoldenGate are used for offline deployment.
- **3.** Follow the on screen instructions to continue with deployment.

For offline deployment, you can select a directory to save the deployment files.

5.2 Overview

This tab is used to edit information regarding the name and description of the deployment profile, deployment history, and deployment configuration.

5.2.1 Definition

Use this tab to edit high level details of the deployment profile. The available fields are:

- Deployment Profile Name: You can view and edit the name of the deployment profile.
- Description: You can add or edit the description of the deployment profile.

5.2.2 Deployment History

It provides a historical record of past deployments for a project, solution, deployment, or a single deployment profile. You can use the **Select Columns** icon in the table's toolbar to tailor your view of the deployment history information. Columns can be reordered as per requirement.

The available columns are:


- Last Deployed
- Deployment Status
- · Deployed By
- Comments
- Process Name
- Process Type
- Instance Name

5.2.3 Monitoring

Detailed information on the status of every process can be viewed under Monitoring. Additionally, you can monitor the status of each process currently deployed on an Oracle GoldenGate instance, such as the status, type, and mode of processes.

The tab looks as follows:

Figure 5-1 Monitoring Tab



The available columns are:

- Status
- Process Name
- Type
- Last Operation Lag
- Mode
- last Operation Timestamp
- last Checkpoint Timestamp
- **Total Inserts**
- **Total Deletes**
- **Total Updates**
- Working Directory
- Start Time
- End of File
- **Total Ignores**
- **Total Truncates**
- **Total Executed DDLs**
- **Total Discards**
- **Total Operations**
- Input Checkpoint
- **Output Checkpoint**

5.2.4 Deployment Configuration

Use this tab to view or edit the deployment options and physical resources.

You use the Deployment Settings check boxes to control which processes to start automatically. The following settings can be configured:

Deployment Settings

- Start All GoldenGate Processes: Select this check box to start the Capture, Pump, and Apply processes.
- Start Pump Processes: Select this check box to start the Pump processes.
- Start Apply Processes: Select this check box to start the Apply processes.

Initial Load Settings

- Oracle GoldenGate: Select this check box to start the Oracle GoldenGate initial load process.
- Oracle Data Pump: Select this check box to start the Oracle Data Pump initial load process.

If you select the **Start process** in deployment configuration screen, then the Change Data Capture (CDC) process will start automatically at the successful completion of Oracle Data Pump Initial Load. If you do not select the **Start process** in deployment configuration screen, then the CDC process will not start automatically at the successful completion of Oracle Data Pump Initial Load.

If Oracle GoldenGate Studio is closed before the automatic start of CDC process, then the CDC process will not start automatically. You can start the CDC process manually using System Change Number (SCN), or starting the CDC process manually from the monitoring screen. The SCN increments by one with every commit.

You can add the **Remote Link** (network link) and **Parallelism** in this dialog. By default, parallelism is set to one.

5.2.5 Oracle Data Pump

Oracle GoldenGate Studio uses the Oracle Data Pump API for the initial load. Oracle Data Pump API can transfer data using different methods. In Oracle GoldenGate Studio, the IMPORT of data using flashback SCN is used. The **Remote Link** (network link) is used to access the source Database.

During Online Deployment with Oracle Data Pump Initial Load , Oracle GoldenGate Studio starts a PL/SQL procedure in the target database. This PL/SQL block invokes Oracle Data Pump job, providing it with Database Link to copy the data from source, SCN of source database, number of parallel threads to be launched, and log filename to log its activity. You have to provide the Database Link and Parallel values in the configuration screen while SCN of source database and log file name are provided by Oracle GoldenGate Studio. Oracle GoldenGate Studio also assumes DATA_PUMP_DIR directory to be created in target database, as this directory is used to create the log file. Oracle Data Pump table shows the current state of the Oracle Data Pump job. You can click on **View Activity Log** to view the content of the ODP Job OGG_LOG log file.

In parallel , CDC captures and replicat processes are deployed in Oracle GoldenGate. The capture processes are started to capture the online transactions while Oracle Data Pump is progressing. Oracle GoldenGate Studio waits for Oracle Data Pump job to complete. After completion of the Oracle Data Pump job, if **Start Replicat** option was selected, Oracle GoldenGate Studio starts the replicat processes with the related SCN number shown in the Oracle Data Pump page of the particular process. If not, you have to manually start the process by clicking on **Start CDC Replicat** in the Oracle Data Pump window.

If you shut down Oracle GoldenGate Studio after completion of Deployment in Oracle GoldenGate but before Oracle Data Pump job is complete, you have to manually starts

the Replicat by clicking on **Start CDC Replicat** in the Oracle Data Pump page or **Start with..** using the SCN shown in Oracle Data Pump page.


You can select the **Replication Paths** from the drop-down list and the status as **Not Started**, **Running**, **Error**, **Finished**, and **Replicat Started**. The status is displayed in tabular format. You can also use the toolbar to search, start the CDC Replicat, view the activity log, refresh table, and add or remove additional table columns.

The following table columns are displayed by default:

- Replication Paths
- Start Time
- End Time
- SCN
- Status
- % Complete
- Time Remaining

The **Time Remaining** column can be empty when Oracle Data Pump is running. This is not related to the normal functioning of the product.

The Oracle Data Pump window looks as follows:



Managing Security

This chapter explains how to manage your the security of your replications using Oracle GoldenGate Studio and includes the following sections:


- Understanding Security in Oracle GoldenGate Studio
- Using the Security Navigator

6.1 Understanding Security in Oracle GoldenGate Studio

The Security Navigator is used to manage the Security in Oracle GoldenGate Studio. It is also used to create users, manage password, and to set an account expiration date. Users in Oracle GoldenGate Studio can be Supervisor or Administrator and non supervisors. There can be only one SUPERVISOR account that is created using RCU. Non supervisor users cannot access the Security Navigator window.

The Security Navigator looks as follows:

Figure 6-1 Security Navigator



6.2 Using the Security Navigator

The Security Navigator is available only for user with SUPERVISOR privilege which is the account created during repository creation. Non supervisor accounts can only change their own password using **Change Password** menu option under **OGG** menu.

You can do the following tasks using the Security Navigator:

6.2.1 Adding a New User

To add a new user, do as follows:

- 1. Click on the user button and select New User.
- 2. Click on Change Password, type the New Password, type the same password in Confirm Password. You can also set the Allow Expiration Date to set a password expiration date (optional). If this is set, the user needs to change the password in the log in after the expiry date.
- 3. Click the Save button in the toolbar.

The change password dialog looks like:

Figure 6-2 Change Password Dialog



Note: You can set the **Allow Expiration Date** under **Account Expiration** to prevent the user from using the product after the expiry date. This is different from the **Allow Expiration Date** under **Change User Password** dialog.

Note: Care should be taken when setting the expiry date for the **SUPERVISOR** user. Once expired, the **SUPERVISOR** user account cannot be enabled again.

6.2.2 Modifying an Existing User

To modify an existing user, do as follows:

- 1. Right click on the user and select **Open**.
- **2.** Modify the user name under **Name**.
- 3. Click the Change Password, type the new password and expiration date (optional).
- 4. Click the Save button in the toolbar.

Note: This option is available only for users with **SUPERVISOR** privilege. It is identified by a red icon. Non-supervisor users are identified with a green icon.

6.2.3 Deleting an User

To delete an existing user, do as follows:

- **1.** Highlight the user, right click and select **Delete**.
- **2.** In the confirmation dialog box, click **Yes**.

Note: The user with supervisor privilege can delete any user with non supervisor privilege. **SUPERVISOR** account cannot be deleted.

Troubleshooting

This chapter describes common issues that may occur and how you can solve them.

- Positioning of Docked Windows
- Performance Issues While Using Oracle GoldenGate Studio
- Privilege Issue with Oracle GoldenGate Studio
- Syntax Errors with Generated Code
- Not Able to Add Resources

7.1 Positioning of Docked Windows

Issue: Multiple docked windows like Projects Navigator, Component pallets and so on are misplaced and do not fit the main application window properly.

Solution: Navigate to Window menu and click Reset Windows To factory Settings.

7.2 Performance Issues While Using Oracle GoldenGate Studio

Issue: Severe performance issue when using Oracle GoldenGate Studio.

Solution: Ensure that the repository is installed in the same LAN.

7.3 Privilege Issue with Oracle GoldenGate Studio

Issue: Only SUPERVISOR user have object level privilege.

Solution: To prevent contention against the same set of objects, it is recommended that Projects and Solutions are well planned in terms of who is working on the same objects.

7.4 Syntax Errors with Generated Code

Issue: Syntax errors are present.

Solution: Check is the version and database values of the data servers assigned to the deployment profiles. Generated Code will be compatible with the assigned data servers.

Next, check is to see if the code can be successfully parsed by Oracle GoldenGate Core product. If the syntax is successfully parsed by that tool, then the Oracle GoldenGate Studio and Core files are compatible.

If it is not successfully parsed and the error is not in the mapping syntax, then you can contact Oracle Support.

7.5 Not Able to Add Resources

Issue: Not able to set add resources using drag-and-drop.

Solution: Ensure that you are dropping the resources to correct targets and to solution editor links instead of Mapping Group to Deployment Profile links. You can add physical resources only to the Deployment Profile view. The **Big Data System** and **Teradata** are target only databases. You can drag-and-drop target only databases as a source database in the mapping editor. This is possible as mapping is a logical concept and no check is performed by Oracle GoldenGate Studio.

Concepts and Terminology

The table in this appendix describes the concepts and terms that are used in the Oracle GoldenGate Studio product and documentation.

Term	Description
Apply	An Oracle GoldenGate process that will write the changes captured in a trail file to a target data server.
AutoMap	Functionality that makes mapping recommendations based on pattern matching of schema, table and column names and data types.
Bidirectional	Name of a solution template that has a single source and single target with replication paths in both directions.
Business Entity	Logical representation of data that records a business or agency activity, usually regarding the sale, distribution or development of a product or a service.
Capture	An Oracle GoldenGate process that writes records relating to change data from a source system (database or JMS queue) into binary files (trails).
CDR	Conflict Detection and Resolution. A specific use case of error detection and response logic found typically in bidirectional and Active-Active solutions.
Column Mapping	The mapping of columns and fields between two tables or other data entities.
Conflict Detection	A specific use case of error detection.
Conflict Resolution	A specific use case of error response.
Connections	Information used to attach to a data server or Oracle GoldenGate instance.
Consolidation	Name of a solution template where many sources map to a single target.
Credential Store	The Oracle GoldenGate credential store manages user IDs and their encrypted passwords (together known as credentials) that are used by Oracle GoldenGate processes to interact with a database.
Data Entity	Typically a table but any data object that can be replicated including a sequence but not replicated logic such as procedures.

Term	Description
Data Server	Most commonly a database but can be any external (to GoldenGate) source or target of data (e.g. JMS). They contain information about data entities that are replicated (e.g. tables) as well as procedural logic that affect data (e.g. triggers and procedures). Can be used as a source or target.
Data server login credentials	Username and password to access data server.
DDL	Data definition language statements that can be replicated between like databases.
Deployment	Physical architecture bound to a logical design that contains one or more profiles.
Deployment Assistant	A sequence of dialog boxes that leads the user through creating a physical deployment, then allows the user to assign GoldenGate instances to replication paths, and provides additional deployment options such as perform initial load.
Deployment History	Contains a historical manifest of deployments and can be viewed in the context of a project, solution, deployment or a single deployment profile.
Deployment Profile	The physical architecture plus the physical properties of specific processes (their names, behavior options, environmental settings) It contains the details that binds the logical design to the physical architecture.
Deployment Template	The physical relationship of data servers, GoldenGate instances, and hosts.
Description	Text field that contains the name and description for a Project, Solution or Deployment.
Distribution	Name of a solution template that has a single source and multiple targets.
Document Tab	Tabs along the top of the interface that display solutions, library mappings and library logic.
Editor Tab	Tab located at the bottom of the interface that is subordinate to the Document Tab.
Exception Mapping	One or more auxiliary mappings that are invoked only when the primary mapping encounters and error.
Filter	Component of mapping to define rules to omit rows.
Folder	An interface construct used to select and visually organize related objects such as, mappings, logic and connections.
Functions	Oracle GoldenGate built in logic constructs that can act on change data or metadata resulting in the transformation, inclusion, or exclusion of column data. Used in the expression editor.
Oracle GoldenGate Agent	Heavy weight agent designed to monitor Oracle GoldenGate instances with minimal management capabilities.

Term	Description
Oracle GoldenGate Gallery	A sequence of dialog boxes that leads the user through creating new Oracle GoldenGate Studio Projects, Solutions, Deployments and Connections.
Oracle GoldenGate Instances	The connection details for an Oracle GoldenGate Instance available in the Resources Navigator.
Oracle GoldenGate processes	Processes and services that are part of the GoldenGate instance used for capturing, transferring, modifying, and applying data.
Hub and Spoke	Name of a solution template. Distributed data model consisting of connections arranged like a wheel, in which all traffic moves along spokes connected to the hub at the center.
Initial Load	The copying of data between systems before changes to that data are applied.
Library	A collection of shared mappings or logic code that can be used in more than one solution or project.
Logic library	Logic code used in mapping and error handling that can be used in more than one solution or project.
Logical Design	One or more data servers with connected replication paths.
Mapping Library	A collection of maps that can be used in more than one solution or project.
Mapping/Map	The assignment of one or more data entities to another or one or more statements to a data server.
Mappings	First-level construct containing the mapping of data entities, statements, and associated logic that is not shared beyond the local solution.
Overview	Name of an editor level tab under solution that provides high level details of the solution as well as control over access privileges.
Parameters	The set of all configurable items relating to the runtime behavior of Oracle GoldenGate processes used in replicating and loading data. Broken down into several areas, the most significant relating to the mapping logic.
Project	The highest level object containing Oracle GoldenGate solutions.
Project Wizard	A sequence of dialog boxes that leads the user through creating a new project.
Projects Navigator	The interface used to select Oracle GoldenGate Studio projects.
Properties Inspector	Shows attributes of selected artifacts and provide a means to change, add, or remove those attributes.
Replication Path	The path denoting one direction of change data as it moves between data servers. Two data servers can have from zero to two direct replication path connections but only one path in each direction.
Replication Source	Data server from which data is read, copied and transmitted.

Term	Description
Resource	Data Server and Oracle GoldenGate connections and mapping library.
Resource Assignment	The act of assigning physical resources.
Resources Navigator	Interface used to select Oracle GoldenGate Studio resources.
Schema Mapping	The mapping of schemas and tables.
Security Navigator	The interface used to select Oracle GoldenGate Studio security options.
Solution	A deployable object representing a replication design. The design view describes data servers, replication paths, mappings and a logical design. The deployment profile describe the resource assignments involved in the physical design. Solutions can contain more than one deployment profiles. A single solution design can be deployed to any number of physical systems by creating a deployment profile for each.
Solution Wizard	A sequence of dialog boxes that leads the user through creating a new solution by providing a menu of common solution templates, and then allows the user to add existing mappings, bind data server connections to the logical design, and finally include mappings from the mapping library.
Solution Navigator	The interface used to select Oracle GoldenGate Studio solutions, mappings, logic, and deployments.
Solution Templates	Preconfigured solution templates are provided.
Structure Panel	Auxiliary navigator to show additional detail beyond what higher level navigators allow.
Target	Data server to where data is written.
Trail	Sequenced set of binary files used to queue and read captured transactions by Oracle GoldenGate.
Unidirectional	Name of a solution template that has one source replicating to one target.
Wallet	Digital Oracle wallet used to store encryption keys and managed and used by Oracle GoldenGate processes to encrypt and decrypt data at rest and in flight.

Relating Properties Inspector Options to Oracle GoldenGate Commands and Parameters

This appendix provides a correlation between the Oracle GoldenGate commands and parameters that are run when you select the various options in the Properties Inspector and includes the following sections:

- Commands with Options
- Parameter Category Names
- Units of Measure
- Opposites
- Other Oracle GoldenGate Parameters/Options

You can find information about all Oracle GoldenGate commands and parameters in the *Reference for Oracle GoldenGate for Windows and UNIX* and *Administering Oracle GoldenGate for Windows and UNIX* describes how they function.

B.1 Commands with Options

The Oracle GoldenGate commands with the specified options are listed in the following sections.

B.1.1 ADD EXTRACT Commands

For an explanation of the ADD EXTRACT command, see the *Reference for Oracle GoldenGate for Windows and UNIX*.

ADD EXTRACT Command	Oracle GoldenGate Studio Label
ADD EXTRACT	Add Extract
SOURCEISTABLE	Table
TRANLOG	Transaction Log
INTEGRATED TRANLOG	Integrated Capture Mode

ADD EXTRACT Command	Oracle GoldenGate Studio Label
VAM	Vendor Access Module
EXTFILESOURCE	Source File Name
EXTTRAILSOURCE	Source Trail Name
VAMTRAILSOURCE	VAM Trail Name
BEGINNOW	Now
EXTSEQNO	At Sequence Number
EXTRBA	Relative Byte Address
EOF	End of Log File
LSN	LSN
EXTRBA	Relative Byte Address
PAGE	Page
ROw	ROW
SEQNO	Sequence Number
SCN	System Change Number
THREADS	Threads
PASSIVE	Passive
PARAMS	Parameter File

ADD EXTRACT Command	Oracle GoldenGate Studio Label
REPORT	Report File
DESC	Description

B.1.2 ADD REPLICAT Commands

For an explanation of the ADD REPLICAT command, see the $\it Reference for Oracle Golden Gate for Windows and UNIX.$

ADD REPLICAT Options	Oracle GoldenGate Studio Label
ADD REPLICAT	Add Replicat
INTEGRATED	Integrated
COORDINATED	Coordinated
MAXTHREADS	Max Threads
SPECIALRUN	Special Run
EXTFILE	Extract File
EXTTRAIL	Extract Trail
BEGIN	Begin
NOW	Now
EXTSEQNO	Sequence Number
EXTRBA	Relative Byte Address
CHECKPOINTTABLE	Checkpoint Table
NODBCHECKPOINT	No Checkpoint Table

ADD REPLICAT Options	Oracle GoldenGate Studio Label
PARAMS	Parameter File
REPORT	Report File
DESC	Description

B.1.3 ADD EXTTRAIL Command

For an explanation of the ADD EXTRAIL command, see the *Reference for Oracle GoldenGate for Windows and UNIX*.

ADD EXTTRAIL Options	Oracle GoldenGate Studio Label
ADD EXT TRAIL	Add Extract Trail
EXTRACT	Extract
MEGABYTES	Megabytes
SEQNO	Sequence Number

B.1.4 ADD RMTTRAIL Command

For an explanation of the ADD RMTTRAIL command, see the *Reference for Oracle GoldenGate for Windows and UNIX*.

ADD RMTTRAIL Options	Oracle GoldenGate Studio Label
ADD RMTTRAIL	Add Remote Trail
EXTRACT	Extract
MEGABYTES	Megabytes
SEQNO	Sequence Number

B.1.5 REGISTER EXTRACT Command

For an explanation of the REGISTER EXTRACT command, see the *Reference for Oracle GoldenGate for Windows and UNIX*.

REGISTER EXTRACT Options	Oracle GoldenGate Studio Label
REGISTER EXTRACT	Register Extract
DATABASE	Database
CONTAINER	Container
ADD CONTAINER	Add Container
DROP CONTAINER	Drop Container
LOGRETENTION	Log Retention
SCN	System Change Number

B.1.6 START EXTRACT Command

For an explanation of the START EXTRACT command, see the *Reference for Oracle GoldenGate for Windows and UNIX*.

Start Extract
At CSN
After CSN

B.1.7 START REPLICAT Command

For an explanation of the START REPLICAT command, see the *Reference for Oracle GoldenGate for Windows and UNIX*.

Start Replicat Command	Oracle GoldenGate Studio Label
START REPLICAT	Start Replicat
SKIPTRANSACTION	Skip Transaction
ATCSN	At CSN
AFTERCSN	After CSN
FILTERDUPTRANSACTIONS	Filter duplicate Transactions
THREADS	Threads

B.1.8 ADD TRANDATA Command

For an explanation of the Trandata commands, see the *Reference for Oracle GoldenGate for Windows and UNIX*.

Add Supplemental Logging Command	Oracle GoldenGate Studio Label
ADD SCHEMATRANDATA	Enable Schema Supplemental Logging
ALLCOLS	Logging Columns
ALLOWNONVALIDATEDKEYS	Allow Non-Validated Keys
ADD TRANDATA	Enable Table Supplemental Logging
COLS	Logging Columns
NOKEY	Suppress primary key columns
INCLUDELONG	Include LONGVAR columns
EXCLUDELONG	Exclude LONGVAR columns

B.2 Parameter Category Names

Option	
Add Extract Options	
Add Replicat Options	
Extract Registration	
Globals	
General	
Environment Variables	
Include	
Port Management	
Process Management	
Event Management	
Maintenance	
Processing Method	
Selection, Converting and Mapping Data	
Routing Data	
Formatting Data	
Custom Processing	
Reporting	
Tuning	
Error Handling	
Rep Error	
Security	
Other	
Advanced	
Start Extract Options	
Start Replicat Options	
Supplemental Logging	

For more information parameter categories, see the Oracle GoldenGate Reference Guide.

B.3 Units of Measure

Unit	Option
MS	Millisecond
cs	Centisecond
CSEC	Centisecond
CSECS	Centiseconds
S	Second
SEC	Second
SECOND	Second
SECS	Seconds
SECONDS	Seconds
М	Minute
MIN	Minute
MINUTE	Minute
MINS	Minutes
MINUTES	Minutes
Н	Hour
HR	Hour

Unit	Option
HOUR	Hour
HOURS	Hours
D	Day
DAY	Day
DAYS	Days
WEEK	Week
WEEKS	Weeks
К	Kilobyte
КВ	Kilobyte
МВ	Megabyte
G	Gigabyte
GB	Gigabyte

B.4 Opposites

Oracle GoldenGate Parameters/Options	Oracle GoldenGate Studio Label
batchsql.nobatcherrormode	No Batch Error Mode
batchsql.nobypasspkcheck	Don't Bypass PK Check
batchsql.nocheckuniquekeys	Don't Check Unique Keys

Oracle GoldenGate Parameters/Options	Oracle GoldenGate Studio Label
batchsql.noerrorhandling	No Error Handling
bulkload.nologging	Disable Redo Logging
bulkload.noparallel	Disable Parallel Loading
dboptions.noallowlobdatatruncate	Disallow LOB Truncation
dboptions.noallowunusedcolumn	Disallow Unused Columns
dboptions.nocatalogconnect	No Separate Catalog Connection
dboptions.nofetchlobs	Disallow LOB Fetching
dboptions.nolimitrows	Don't Limit Rows
dboptions.noreparselobsql	Don't Reparse LOB SQL
dboptions.noshowwarnings	Don't Log Warnings
dboptions.noskiptemplob	Don't Skip Temp LOB
dboptions.nospthread	No Separate Connection For Stored Procedures
dboptions.nosuppresstriggers	Don't Suppress Triggers
ddloptions.CROSSRENAME	Cross Rename
ddloptions.ignoreapplops	Ignore Application Operations
ddloptions.ignorereplicates	Ignore Replicat Transactions
ddloptions.nomapderived	Disallow Derived Name Mapping

Oracle GoldenGate Parameters/Options	Oracle GoldenGate Studio Label
ddloptions.noreplicatepassword	Don't Replicate Password
ddloptions.noreport	Don't Log DDL Operations To Report File
disableheartbeat	Disable Heartbeat
disableheartbeattable	Disable Heartbeat Table
disablenewmanager	Disable New Manager
extfile.no_objectdefs	No Object Definitions
exttrail.no_objectdefs	No Object Definitions
fetchoptions.nodetaileddiagnostics	No Detailed Diagnostics
fetchoptions.nodiagnosticsonall	No Diagnostics On All
fetchoptions.nousediagnostics	Don't Use Diagnostics
fetchoptions.nousekey	Don't Use Key
fetchoptions.nouselatestversion	Don't Use Latest Version
fetchoptions.nouserowid	Don't Use Row ID
fetchoptions.nousesnapshot	Don't Use Snapshot
fetchoptions.suppressduplicates	Suppress Duplicates
formatasciinoind	No Ind
formatasciinoop	No Op

Oracle GoldenGate Parameters/Options	Oracle GoldenGate Studio Label
formatasciinots	No TS
formatascii.nonames	Exclude Column Names
Formatxml.noinlineproperties	Write Properties Outside XML Tal
formatxml.notrans	Exclude Commit Markers
gnorealters	Ignore Alters
gnoreapplops	Ignore Application Operations
gnorecreates	Ignore Creates
gnoredeletes	Ignore Deletes
gnoredrops	Ignore Drops
gnoreinserts	Ignore Inserts
gnorereplicates	Ignore Replicat Transactions
gnoretruncates	Ignore Truncates
gnoreupdateafters	Ignore Update After Images
gnoreupdatebefores	Ignore Update Before Images
gnoreupdates	Ignore Updates
ap.nohandlecollisions	Don't Handle Collisions
ap.noinsertappend	Don't Insert Append

Oracle GoldenGate Parameters/Options	Oracle GoldenGate Studio Label
map.noinsertmissingupdates	Don't Insert Missing Updates
map.nomapinvisiblecolumns	Don't Map Invisible Columns
map.notrimspaces	Don't Trim CHAR to VARCHAR Trailing Spaces
map.notrimvarspaces	Don't Trim VARCHAR to CHAR Trailing Spaces
no_use_traildefs	Don't Use Trail Definitions
noallowduptargetmap	Don't Allow Duplicate Target Map
noallowlargefloat	Don't Allow Large Float
noallownoopupdates	Don't Allow No-Operation Updates
noapplynoopupdates	Don't Apply No-Operation Updates
noassumetargetdefs	Don't Assume Target Definitions
noauditreps	Don't Audit Replicats
nobinarychars	Don't Use Binary Characters
nocachenullablecols	Don't Cache Nullable Columns
nocharsetconversion	Disable Character Set Conversion
nochecksequencevalue	Don't Check Sequence Values
nocomplexnullcond	No Complex Null Conditions
nocompressdeletes	No Compress Deletes

Oracle GoldenGate Parameters/Options	Oracle GoldenGate Studio Label
nocompressupdates	No Compress Updates
nodeletelogrecs	Don't Delete Log Records
nodynamicresolution	No Dynamic Resolution
nodynsql	No Dynamic SQL
nofilterdups	Don't Filter Duplicates
nohandlecollisions	Don't Handle Collisions
noinsertappend	No Insert Append
noinsertdeletes	Don't Insert Deletes
noinsertmissingupdates	Don't Convert Failed Updates To Inserts
noinsertupdates	Don't Insert Updates
nolist	Don't List Parameters in Report File
nologallsupcols	Don't Capture All Supplementally Logged Columns
nomapinvisiblecolumns	Don't Map Invisible Columns
nooverridedups	Don't Override Duplicates
nopassthru	Disable PassThru
nopassthrumessages	Disable PassThru Messages
norestartcollisions	Don't Restart Collisions

Oracle GoldenGate Parameters/Options	Oracle GoldenGate Studio Label
nospacestonull	Don't Convert Spaces to Null
notcpsourcetimer	Do Not Compensate For System Clock Differences
notrimspaces	Don't Trim CHAR to VARCHAR Spaces
notrimvarspaces	Don't Trim VARCHAR to CHAR Spaces
noupdatedeletes	Don't Convert Deletes To Updates
noupdateinserts	Don't Convert Inserts To Deletes
nouseansisqlquotes	Don't Use ANSI SQL Quotes
nousededicatedcoordinationthread	Don't Use Dedicated Coordination Thread
novarwidthnchar	Don't Treat NCHAR, NVARCHAR2, NCLOB As UTF-16
purgeoldextracts.no_use_checkpoints	Don't Use Checkpoints
reportcount.norate	Don't Report Rate
rmtfile.no_objectdefs	No Object Definitions
rmttrail.no_objectdefs	No Object Definitions
showsyntax.apply	Apply
statoptions.noreportdetail	No Operation Statistics
statoptions.noreportfetch	Don't Fetch Statistics
statoptions.noresetreportstats	Don't Reset Report Statistics

Oracle GoldenGate Parameters/Options	Oracle GoldenGate Studio Label
table.notrimspaces	Don't Trim CHAR to VARCHAR Spaces
table.notrimvarspaces	Don't Trim VARCHAR to CHAR Spaces
trail_seqlen_6d	Trail Sequence Length 6 digits
tranlogoptionsnoarchivedlogonly	Don't Read Only From Archived Logs
tranlogoptions.ignoremetadatafromvam	Ignore Metadata From VAM
tranlogoptions.noapifilter	No API Filter
tranlogoptions.nocompletearchivedlogonly	No Complete Archived Log
tranlogoptions.nogetctasdml	Don't Get CTAS DML
tranlogoptions.nomanagesecondarytruncationp oint	Manage Secondary Truncation Point
tranlogoptions.nominefromactivedg	Don't Mine From Active Data Guard
tranlogoptions.nominefromsnapshotstby	Don't Mine From Standby Snapshots
tranlogoptions.noprepareforupgradetoie	Don't Prepare For Upgrade To Integrated Extract
tranlogoptions.nopurgeorphanedtransactions	Don't Purge Orphaned Transactions
tranlogoptions.nousenativeobjsupport	Don't Use Native Object Support
tranlogoptions.nouseprevresetlogsid	Don't Use Previous Reset Log SID
tranlogoptions.nouserexit	No Userexit

B.5 Other Oracle GoldenGate Parameters/Options

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
a2e	ASCII to EBCDIC
accessrule	Access Rule
allocfiles	Allocate Memory Structures
allowduptargetmap	Allow Duplicate Target Map
allowinvisibleindexkeys	Allow Invisible Index Keys
allowlargefloat	Allow Large Float
allownonvalidatedkeys	Allow Non-Validated Keys
allownoopupdates	Allow No-Operation Updates
allowoutputdir	Allow Output Directory
applynoopupdates	Apply No-Operation Updates
asciimixedccsid	ASCII Mixed CCSID
asciitoebcdic	ASCII to EBCDIC
assumetargetdefs	Assume Target Definitions
assumetargetdefs.override	Override Target Defs
auditreps	Audit Replicats
autorestart	Auto Restart

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
autorestart.er	Extract/Replicat
autorestart.extract	Extract
autorestart.replicat	Replicat
autorestart.resetminutes	Reset Time (mins)
autorestart.retries	Retries
autorestart.waitminutes	Wait Time (mins)
autorestartinterval	Auto Restart Interval
autorestartmintime	Auto Restart Minimum Time
autostart	AutoStart
autostart.er	Extract/Replicat
autostart.extract	Extract
autostart.replicat	Replicat
batchsql	BatchSQL
batchsql.batcherrormode	Batch Error Mode
batchsql.batchesperqueue	Batches Per Queue
batchsql.batchtransops	Operations Per Transaction
batchsql.bypasspkcheck	Bypass PK Check

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
batchsql.bytesperqueue	Bytes Per Queue
batchsql.checkuniquekeys	Check Unique Keys
batchsql.errorhandling	Error Handling
batchsql.maxthreadqueuedepth	Max Thread Queue Depth
batchsql.numthreads	Number of Threads
batchsql.opsperbatch	Operations Per Batch
batchsql.opsperqueue	Operations Per Queue
batchsql.thread	Thread
batchsql.trace	Trace
begin	Begin
binarychars	Binary Characters
bootdelayminutes	Boot Delay (min)
bootdelayseconds	Boot Delay (secs)
br	Bounded Recovery
br.brdir	Directory
br.brfsoption	FS Option
br.brinterval	Interval

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
br.brkeepstalefiles	Keep Stale Files
br.broff	Off
br.broffonfailure	Off On Failure
bulkload	Bulk Load
bulkload.logging	Log To Redo
bulkload.noskipallindexes	Enable Index Maintenance
bulkload.parallel	Enable Parallel Loading
bulkload.skipallindexes	Skips Index Maintenance
bulkload.skipunusedindex	Skip Unusable Indexes
cachemgr	Cache Manager
cachemgr.cachebuffersize	Cache Buffer Size
cachemgr.cachedirectory	Cache Directory
cachemgr.cachefsoption	Cache File Sync Option
cachemgr.cachepageoutsize	Cache Page Outsize
cachemgr.cachesize	Cache Size
cachenullablecols	Cache Nullable Columns
catalogexclude	Catalog Exclude

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
catalogexclude.norename	No Rename
cdroptions	CDR Options
cdroptions.applymodcolonly	Apply Modified Columns Only
charmap	Character Map Override
charset	Parameter File Character Set
charsetconversion	Enable Character Set Conversion
checkminutes	Maintenance Check Minutes
checkparams	Check Parameter Syntax
checkpointsecs	Checkpoint Seconds
checkpointtable	Checkpoint Table
checksequencevalue	Check Sequence Values
cmdtrace	Command Trace
colmatch	Column Match
colmatch.names	Names
colmatch.prefix	Prefix
colmatch.reset	Reset
colmatch.suffix	Suffix

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
comment	Comment
complexnullcond	Complex Null Condition
compressdeletes	Compress Deletes
compressdeletes.fetchmissingcolumns	Fetch Missing Columns
compressupdates	Compress Updates
coordstatinterval	Coordinate Statistic Interval
coordtimer	Coordinate Timer
credentialstorelocation	Credential Store Location
cuserexit	C User Exit
cuserexit.includeupdatebefores	Include Update Before Images
cuserexit.params	Params
cuserexit.passthru	PassThru
dboptions	Database Options
dboptions.allowlobdatatruncate	Allow LOB Truncation
dboptions.allowunusedcolumn	Allow Unused Columns
dboptions.bindcharforbitaschar	Encode CCSID Data
dboptions.catalogconnect	Use Separate Catalog Connection

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
dboptions.catalogur	Catalog Uncommit Read
dboptions.connectionport	Connection Port
dboptions.decryptpassword	Decrypt Password
dboptions.decryptpassword.algorithm	Algorithm
dboptions.decryptpassword.aes128	AES128
dboptions.decryptpassword.aes192	AES192
dboptions.decryptpassword.aes256	AES256
dboptions.decryptpassword.blowfish	Blowfish
dboptions.decryptpassword.encryptkey	Encryption Key
dboptions.deferrefconst	Defer Referential Integrity Constraint
dboptions.disablecommitnowait	Disable Asynchronous Commits
dboptions.disablelobcaching	Disable LOB Caching
dboptions.emptylobstring	Empty LOB String
dboptions.enableinstantiationfiltering	Enable InstantiationCSN Filtering
dboptions.fetchbatchsize	Fetch Batch Size
dboptions.fetchcheckfreq	Fetch Check Freq
dboptions.fetchlobs	Fetch LOBs

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
dboptions.fetchretrycount	Fetch Retry Count
dboptions.fetchtimeout	Fetch Timeout
dboptions.host	Host
dboptions.integratedparams	Integrated Parameters
dboptions.integratedparams.ALLOW_DUPLICATE_ ROWS	Allow Duplicate Rows
dboptions.integratedparams.APPLY_SEQUENCE_N EXTVAL	Apply Sequence Next Value
dboptions.integratedparams.BATCHSQL_MODE	Batch SQL Mode
dboptions.integratedparams.CDGRANULARITY	Conflict Detection Granularity
dboptions.integratedparams.COMMIT_SERIALIZATION	Commit Serialization
dboptions.integratedparams.COMPARE_KEY_ONLY	Compare Key Only
dboptions.integratedparams.COMPUTE_LCR_DEP_ON_ARRIVAL	Compute LCR Dependency On Arrival
dboptions.integratedparams.DISABLE_ON_ERROR	Disable On Error
dboptions.integratedparams.DISABLE_ON_LIMIT	Disable On Limit
dboptions.integratedparams.EAGER_SIZE	Eager Size
dboptions.integratedparams.ENABLE_XSTREAM_T ABLE_STATS	Enable Table Statistics
dboptions.integratedparams.GROUPTRANSOPS	Group Transaction Operations

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
dboptions.integratedparams.HANDLECOLLISIONS	Handle Collisions
dboptions.integratedparams.IGNORE_TRANSACTI ON	Ignore Transaction
dboptions.integratedparams.MAXIMUM_SCN	Max SCN
dboptions.integratedparams.MAX_PARALLELISM	Max Parallelism
dboptions.integratedparams.MAX_SGA_SIZE	Max SGA Size
dboptions.integratedparams.MESSAGE_TRACKING _FREQUENCY	Message Tracking Frequency
dboptions.integratedparams.OPTIMIZE_PROGRES S_TABLE	Optimize Progress Table
dboptions.integratedparams.OPTIMIZE_SELF_UPDATES	Optimize Self Updates
dboptions.integratedparams.PARALLELISM	Parallelism
dboptions.integratedparams.PARALLELISM_INTE	Parallelism Interval
dboptions.integratedparams.PRESERVE_ENCRYPTION	Preserve Encryption
dboptions.integratedparams.RTRIM_ON_IMPLICI T_CONVERSION	RTRIM On Implicit Conversion
dboptions.integratedparams.STARTUP_SECONDS	Startup Seconds
dboptions.integratedparams.SUPPRESSTRIGGERS	Suppress Triggers
dboptions.integratedparams.TIME_LIMIT	Time Limit

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
dboptions.integratedparams.TRACE_LEVEL	Trace Level
dboptions.integratedparams.TRANSACTION_LIMI	Transaction Limit
dboptions.integratedparams.WRITE_ALERT_LOG	Write Alert Log
dboptions.legacylobreplication	Legacy LOB Replication
dboptions.limitrows	Limit Rows
dboptions.lobbufsize	LOB Buffer Size
dboptions.lobwritesize	LOB Write Size
dboptions.nofetchtimeout	No Fetch Timeout
dboptions.reparselobsql	Reparse LOB SQL
dboptions.sessionpoolincr	Session Pool Increase
dboptions.sessionpoolmax	Session Pool Max
dboptions.sessionpoolmin	Session Pool Min
dboptions.settag	Set Tag
dboptions.showinfomessages	Show Info Messages
dboptions.showwarnings	Show Warnings
dboptions.skiptemplob	Skip Temp LOB
dboptions.sourcedbname	Source DB Name

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
dboptions.sourcerootname	Source CDB Root Name
dboptions.spthread	SP Thread
dboptions.suppresstemporalupdates	Edit Temporal Updates
dboptions.suppresstriggers	Suppress Triggers
dboptions.tdspacketsize	TDS Packet Size
dboptions.trustedconnection	Trusted Connection
dboptions.useodbc	Use ODBC
dboptions.usereplicationuser	Use Replication User
dboptions.xmlbufsize	XML Buffer Size
ddl	DDL Operations
ddl.exclude	Exclude
ddl.exclude.all	All
ddl.exclude.allcatalogs	All Catalogs
ddl.exclude.allowemptyobject	Allow Empty Object
ddl.exclude.allowemptyowner	Allow Empty Owner
ddl.exclude.eventactions	EventActions
ddl.exclude.instr	Instring

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
ddl.exclude.instrcomments	Instring Comments
ddl.exclude.instrcommentswords	Instring Comments Words
ddl.exclude.instrwords	Instring Words
ddl.exclude.mapped	Mapped
ddl.exclude.objname	Object Name
ddl.exclude.objtype	Object Type
ddl.exclude.optype	Operation Type
ddl.exclude.other	Other
ddl.exclude.sourcecatalog	Source Catalog
ddl.exclude.staymetadata	Stay Metadata
ddl.exclude.unmapped	Unmapped
ddl.include	Include
ddl.include.all	All
ddl.include.allcatalogs	All Catalogs
ddl.include.allowemptyobject	Allow Empty Object
ddl.include.allowemptyowner	Allow Empty Owner
ddl.include.eventactions	EventActions

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
ddl.include.instr	Instring
ddl.include.instrcomments	Instring Comments
ddl.include.instrcommentswords	Instring Comment Words
ddl.include.instrwords	Instring Words
ddl.include.mapped	Mapped
ddl.include.objname	Object Name
ddl.include.objtype	Object Type
ddl.include.optype	Operation Type
ddl.include.other	Other
ddl.include.sourcecatalog	Source Catalog
ddl.include.staymetadata	Stay Metadata
ddl.include.unmapped	Unmapped
ddlerror	DDL Error
ddlerror.abendmissingobjects	Abend on Missing Objects
ddlerror.abendmissingtables	Abend on Missing Tables
ddlerror.error_code	Error Code
ddlerror.error_code.abend	Abend

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
ddlerror.error_code.discard	Discard
ddlerror.error_code.exclude	Exclude
ddlerror.error_code.exclude.all	All
ddlerror.error_code.exclude.allcatalogs	All Catalogs
ddlerror.error_code.exclude.allowemptyobjec	Allow Empty Object
ddlerror.error_code.exclude.allowemptyowner	Allow Empty Owner
ddlerror.error_code.exclude.eventactions	Event Actions
ddlerror.error_code.exclude.instr	Instring
ddlerror.error_code.exclude.instrcomments	Instring Comments
ddlerror.error_code.exclude.instrcommentswo rds	Instruction Comments Words
ddlerror.error_code.exclude.instrwords	Instruction Words
ddlerror.error_code.exclude.mapped	Mapped
ddlerror.error_code.exclude.objname	Object Name
ddlerror.error_code.exclude.objtype	Object Type
ddlerror.error_code.exclude.optype	Operation Type
ddlerror.error_code.exclude.other	Other
ddlerror.error_code.exclude.sourcecatalog	Source Catalog

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
ddlerror.error_code.exclude.staymetadata	Stay Metadata
ddlerror.error_code.exclude.unmapped	Unmapped
ddlerror.error_code.ignore	Ignore
ddlerror.error_code.include	Include
ddlerror.error_code.include.all	All
ddlerror.error_code.include.allcatalogs	All Catalogs
ddlerror.error_code.include.allowemptyobjec t	Allow Empty Object
ddlerror.error_code.include.allowemptyowner	Allow Empty Owner
ddlerror.error_code.include.eventactions	Event Actions
ddlerror.error_code.include.instr	Instring
ddlerror.error_code.include.instrcomments	Instring Comments
ddlerror.error_code.include.instrcommentswo rds	Instruction Comments Words
ddlerror.error_code.include.instrwords	Instruction Words
ddlerror.error_code.include.mapped	Mapped
ddlerror.error_code.include.objname	Object Name
ddlerror.error_code.include.objtype	Object Type
ddlerror.error_code.include.optype	Operation Type

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
ddlerror.error_code.include.other	Other
ddlerror.error_code.include.sourcecatalog	Source Catalog
ddlerror.error_code.include.staymetadata	Stay Metadata
ddlerror.error_code.include.unmapped	Unmapped
ddlerror.error_code.retryop	Retry Operation
ddlerror.error_code.retryop.maxretries	Max Retries
ddlerror.error_code.retryop.retrydelay	Retry Delay
ddlerror.ignoremissingobjects	Ignore Missing Objects
ddlerror.ignoremissingtables	Ignore Missing Tables
ddlerror.norestartcollisions	Do Not Restart With HandleCollisions
ddlerror.restartcollisions	Restart With HandleCollisions
ddlerror.restartskip	Restart And Skip
ddlerror.skiptriggererror	Skip Trigger Error
ddloptions	DDL Options
ddloptions.NOADDTRANDATA	No Add Trandata
ddloptions.NOCAPTUREGLOBALTEMPTABLE	No Capture Global Temp Table
ddloptions.NOCROSSRENAME	No Cross Rename

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
ddloptions.USEPASSWORDVERIFIERLEVEL	Use Password Verifier Level
ddloptions.addtrandata	Add Trandata
ddloptions.addtrandata.abend	Abend
ddloptions.addtrandata.retryop	Retry Operation
ddloptions.addtrandata.retryop.maxretries	Max Retries
ddloptions.addtrandata.retryop.retrydelay	Retry Delay
ddloptions.captureglobaltemptable	Capture Global Template
ddloptions.defaultuserpassword	Default User Password
ddloptions.defaultuserpassword.aes128	AES128
ddloptions.defaultuserpassword.aes192	AES192
ddloptions.defaultuserpassword.aes256	AES256
ddloptions.defaultuserpassword.blowfish	Blowfish
ddloptions.defaultuserpassword.encryptkey	Encrypt Key
ddloptions.defaultuserpasswordalias	Default User Password Alias
ddloptions.defaultuserpasswordalias.domain	Domain
ddloptions.getapplops	Get Application Operations
ddloptions.getreplicates	Get Replicat Transactions

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
ddloptions.ignoremapping	Ignore Mapping
ddloptions.mapderived	Map Derived
ddloptions.mapschemas	Map Schemas
ddloptions.mapsessionschema	Map Session Schema
ddloptions.noremovecomments	Don't Remove Comments
ddloptions.notag	No Tag
ddloptions.password	Password
ddloptions.password.aes128	AES128
ddloptions.password.aes192	AES192
ddloptions.password.aes256	AES256
ddloptions.password.blowfish	Blowfish
ddloptions.password.encryptkey	Encryption Key
ddloptions.removecomments	Remove Comments
ddloptions.replicatepassword	Replicate Password
ddloptions.report	Log DDL Operations To Report File
ddloptions.target	Target
ddloptions.updatemetadata	Update Metadata

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
ddloptions.useownerforsession	Use Owner for Session
ddlrulehint	DDL Rule Hint
ddlsubst	DDL Substitution
ddlsubst.allcatalogs	All Catalogs
ddlsubst.allowemptyobject	Allow Empty Object
ddlsubst.allowemptyowner	Allow Empty Owner
ddlsubst.eventactions	Event Actions
ddlsubst.exclude	Exclude
ddlsubst.exclude.all	All
ddlsubst.exclude.mapped	Mapped
ddlsubst.exclude.other	Other
ddlsubst.exclude.unmapped	Unmapped
ddlsubst.include	Include
ddlsubst.include.all	All
ddlsubst.include.mapped	Mapped
ddlsubst.include.other	Other
ddlsubst.include.unmapped	Unmapped

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
ddlsubst.instr	Apply to String
dlsubst.instrcomments	Comments
ldlsubst.instrcommentswords	Comment Words
dlsubst.instrwords	Apply to Instructions
dlsubst.objname	Object Name
ldlsubst.objtype	DB Object Type
ldlsubst.optype	DDL Operation Type
ddlsubst.sourcecatalog	Source Catalog
ddlsubst.staymetadata	Stay metadata
dlsubst.with	With
dltable	DDL Table Name Override
ecrypttrail	Decrypt Trail
decrypttrail.algorithm	Algorithm
decrypttrail.aes128	AES128
ecrypttrail.aes192	AES192
ecrypttrail.aes256	AES256
ecrypttrail.keyname	Key Name

Oracle GoldenGate Studio Label
Defer Apply Interval
DEFGEN Definition File
Append
Character Set
Format Release
Level
Release
Purge
Delete Log Records
Discard File
Append
Max Bytes
Megabytes
Purge
Discard Rollover
At
On

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
downcritical	Down Critical
downinfo	Down Info
downreporthours	Down Report Hours
downreportminutes	Down Report Minutes
dsoptions	Teradata Data Server Options
dsoptions.checkopcomplete	Check Op Complete
dsoptions.checktrandata	Check Trandata
dsoptions.committedtranlog	Committed Tranlog
dsoptions.createtranlog	Create Tranlog
dsoptions.excludetrans	Exclude Tranlog
dsoptions.excludeuser	Exclude User
dsoptions.excludeuserid	Exclude User ID
dsoptions.ignoremetadatafromvam	Ignore VAM Metadata
dsoptions.restartappend	Restart Append
dsoptions.sorttranlog	Sort Tranlog
dsoptions.vamcompatibility	VAM Compatibility
dumpddlcolumns	Dump DDL Columns

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
dumpddlloggroups	Dump DDL Log Groups
dumpddlobjects	Dump DDL Objects
dumpddlpartitions	Dump DDL Partitions
dumpddlprimarykeys	Dump DDL Primary Keys
dynamicportlist	Dynamic Port List
dynamicportreassigndelay	Dynamic Port Reassign Delay
dynamicresolution	Dynamic Resolution
dynsql	Dynamic SQL
ebcdicmixedccsid	EBCDIC Mixed CCSID
ebcdictoascii	EBCDIC to ASCII
enablecatalognames	Enable Catalog Names
enableheartbeat	Enable Heartbeat
enablemonitoring	Enable Monitoring
enablemonitoring.bdb	BDB (Berkeley DB)
enablemonitoring.lmdb	LMDB (Lightning DB)
enablemonitoring.shmid	SHMID (Shared Memory ID)
enablenewmanager	Enable New Manager

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Labe
encrypttrail.0	Encrypt Trail
encrypttrail.1	Algorithm
encrypttrail.keyname	Key Name
end	End
eofdelay	EOF Delay (seconds)
eofdelaycsecs	EOF Delay (centiseconds)
etoldformat	ET Old Format
excludetag	Exclude Tag
excludewildcardobjectsonly	Exclude Wildcard Objects Only
extfile	Extract File
extfile.format	Format Release
extfile.level	Format Level
extfile.maxfiles	Max Files
extfile.megabytes	Megabytes
extfile.objectdefs	Object Definitions
extfile.purge	Purge
extfile.release	Release

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
extfile.trailbyteorder	Trail Byte Order
extract	Extract
exttrail	Trail
exttrail.format	Format Release
exttrail.level	Format Level
exttrail.objectdefs	Object Definitions
exttrail.release	Format Release
exttrail.trailbyteorder	Trail Byte Order
fetchoptions	Fetch Options
fetchoptions.detaileddiagnostics	Detailed Diagnostics
fetchoptions.diagnosticsonall	Diagnostics On All
fetchoptions.fetchpkupdatecols	Fetch PK Updates Columns
fetchoptions.inconsistentrow	Inconsistent Row
fetchoptions.maxfetchstatements	Max Fetch Statements
fetchoptions.missingrow	Missing Row
fetchoptions.nofetch	No Fetch
fetchoptions.nosuppressduplicates	No Suppress Duplicates

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
fetchoptions.usediagnostics	Use Diagnostics
fetchoptions.usekey	Use Key
fetchoptions.uselatestversion	Use Latest Version
fetchoptions.userowid	Use Row ID
fetchoptions.usesnapshot	Use Snapshot
fetchuserid	Fetch User ID
fetchuserid.algorithm	Algorithm
fetchuserid.encryptkey	Encrypt Key
fetchuserid.password	Password
fetchuserid.sysdba	Sysdba
filterdups	Filter Duplicates
flushcsecs	Flush Memory Buffer (csecs)
flushsecs	Flush (secs)
formatascii	Format ASCII
formatascii.bcp	MSSQL Bulk Load
formatascii.charset	Character Set
formatascii.date	Date Time Format

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
formatascii.delimiter	Delimiter
formatascii.extracols	Extra Columns
formatascii.ind	Include Before and After Ind
formatascii.names	Include Columns Names
formatascii.nohdrfields	Suppress Header Fields
formatascii.noquote	Exclude Quotes
formatascii.nullisspace	Convert Null to Blank
formatascii.op	Include Operation Type
formatascii.placeholders	Placeholders
formatascii.sqlloader	Oracle SQL Loader
formatascii.time	Time
formatascii.ts	Timestamp
formatsql	Write SQL Format File
formatsql.nonames	Omit Column Names
formatsql.nopkupdates	No PK Updates
formatsql.oracle	Oracle Date-Times
formatxml	Format XML

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
formatxml.encoding	Encoding
formatxml.inlineproperties	Write Properties Inline With XML Tab
formatxml.trans	Include Commit Markers
functionstacksize	Function Stack Size
genloadfiles	Generate Load Files
genloadfiles.charset	Character Set
getalters	Get Alters
getapplops	Get Application Operations
getcreates	Get Creates
getdeletes	Get Deletes
getdrops	Get Drops
getenv	Get Environment
getinserts	Get Inserts
getreplicates	Get Replicat Transactions
gettruncates	Get Truncates
getupdateafters	Get Update After Images
getupdatebefores	Get Updates Before Images

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
getupdates	Get Updates
ggschema	Schema Name
grouptransops	Group Transaction Operations
handlecollisions	Handle Collisions
handlecollisions.thread	Threads
handletpkupdate	Handle Transient Primary-Key Update
haveudtwithnchar	User Data Type Contains NCHAR
heartbeat_table	Heartbeat Table
ignore_unrecognized	Ignore Unrecognized
include	Include
initializeheap	Initialize Heap
insertallrecords	Insert All Records
insertappend	Insert Append
insertdeletes	Insert Deletes
insertmissingupdates	Convert failed updates to inserts
insertupdates	Insert Updates
jvmadditionalopts	JVM Additional Options

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
jvmclasspath	JVM Classpath
jvmcompiler	JVM Compiler
jvmentryclass	JVM Entry Class
jvmentrymethod	JVM Entry Method
jvmentrymethodarguments	JVM Entry Method Arguments
jvmentrymethodsignature	JVM Entry Method Signature
jvmlibrarypath	JVM Library Path
lagcriticalhours	Critical Hours Lag Threshold
lagcriticalminutes	Critical Minutes Lag Threshold
lagcriticalseconds	Critical Seconds Lag Threshold
laginfohours	Info Hours Lag Threshold
laginfominutes	Info Minutes Lag Threshold
laginfoseconds	Lag Info Seconds
lagreporthours	Report Hours Lag Threshold
lagreportminutes	Report Minutes Lag Threshold
lfmmemory	LFM (Long Field Memory)
lfmmemory.directory	Directory

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
lfmmemory.inittransram	Init Trans RAM
lfmmemory.ram	RAM
lfmmemory.ramincrement	RAM Increment
lfmmemory.transallsources	Trans All Sources
lfmmemory.transram	Trans RAM
list	List
lobmemory	LOB Memory
lobmemory.directory	Directory
lobmemory.inittransram	Init Trans RAM
lobmemory.ram	RAM
lobmemory.ramincrement	RAM Increment
lobmemory.transallsources	Trans All Sources
lobmemory.transram	Trans RAM
logallsupcols	Capture All Supplementally Logged Columns
logfilesbehind	Log Files Behind
logfilesbehindinfo	Log Files Behind Message
macro	Macro

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
macro.begin	Body
macro.params	Parameters
macrochar	Macro Character
mapexclude	Map Exclude
mapexclude.norename	No Rename
mapinvisiblecolumns	Map Invisible Columns
mapinvisiblecolumns.thread	Thread
markertable	Marker Table
masterkeyname	Master Key Name
masterkeyname.version	Version
maxabendrestarts	Max Abend Restarts
maxdiscardrecs	Max Discard Records
maxetcheckptsecs	Max Checkpoint Seconds
maxfetchstatements	Max Fetch Statements
maxfieldlen	Max Field Length
maxgroups	Max Process Groups
maxsqlstatements	Max SQL Statements

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
maxtaclrestarts	Max Tacl Restarts
maxtransops	Max Transaction Operations
maxtraprestarts	Max Trap Restarts
mgrservname	Manager Server Name
monitoring_heartbeat_timeout	Monitoring Heartbeat Timeout (secs)
nameccsid	DB Name CCSID
namematchexact	Exact Match
namematchignorecase	Ignore Case
namematchnowarning	No Name Match Warning
noasciiformat	No ASCII Format
nocatalog	Remove Catalog Name
nodiscardfile	Disallow Discard File
nodupmsgsuppression	Disallow Duplicate Message Suppression
noencrypttrail	Disallow Encrypt Trail
nosqlformat	No SQL Format
nostats	Disable Performance Statistics
notracetable	Disallow Trace Table

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
nouserid	No User ID
nousethreads	Disallow Use Threads
numfiles	Memory Structures Initial Number
obey	Obey
outputfileumask	Output File umask
overridedups	Override Duplicates
param_parse_error	Parameter Parsing Error
param_parse_error.force	Force
passthru	Enable PassThru
passthrumessages	Enable PassThru Messages
port	Port
preservetargettimezone	Preserve Target Timezone
ptkcapturebatchsql	Capture Batch SQL Statistics
ptkcapturecachemgr	Capture Cache Statistics
ptkcaptureift	Capture Inflight Transactions
ptkcapturenetwork	Capture Network Statistics
ptkcaptureprocstats	Enable Process/Thread Statistics

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
ptkcapturequeuestats	Capture Queue Statistics
ptkcapturetablestats	Capture Table Statistics
ptkirstatsfrequency	Statistics Frequency
ptkmaxtables	Max Tables for Statistics
ptkmonitorfrequency	Monitoring Collection Frequency (sec)
ptkspstats	Capture Superpool Statistics
ptktablepollfrequency	Poll Interval for Table Statistics
purgeddlhistory	Purge DDL_HISTORY
purgeddlhistory.frequencyhours	Frequency Hours
purgeddlhistory.frequencyminutes	Frequency Minutes
purgeddlhistory.maxkeepdays	Max Keep Days
purgeddlhistory.maxkeephours	Max Keep Hours
purgeddlhistory.minkeepdays	Minimum Keep Days
purgeddlhistory.minkeephours	Minimum Keep Hours
purgeddlhistoryalt	Purge DDL_HISTORY_ALT
purgeddlhistoryalt.frequencyhours	Frequency Hours
purgeddlhistoryalt.frequencyminutes	Frequency Minutes

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
purgeddlhistoryalt.maxkeepdays	Max Keep Days
purgeddlhistoryalt.maxkeephours	Max Keep Hours
purgeddlhistoryalt.minkeepdays	Minimum Keep Days
purgeddlhistoryalt.minkeephours	Minimum Keep Hours
purgemarkerhistory	Purge MARKER_HISTORY table
purgemarkerhistory.frequencyhours	Frequency Hours
purgemarkerhistory.frequencyminutes	Frequency Minutes
purgemarkerhistory.maxkeepdays	Max Keep Days
purgemarkerhistory.maxkeephours	Max Keep Hours
purgemarkerhistory.minkeepdays	Minimum Keep Days
purgemarkerhistory.minkeephours	Minimum Keep Hours
purgeoldextracts	Purge Old Extracts
purgeoldextracts.frequencyhours	Frequency Hours
purgeoldextracts.frequencyminutes	Frequency Minutes
purgeoldextracts.maxkeepdays	Max Keep Days
purgeoldextracts.maxkeepfiles	Max Keep Files
purgeoldextracts.maxkeephours	Max Keep Hours

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
purgeoldextracts.minkeepdays	Minimum Keep Days
purgeoldextracts.minkeepfiles	Minimum Keep Files
purgeoldextracts.minkeephours	Minimum Keep Hours
purgeoldextracts.usecheckpoints	Use Checkpoints
purgeoldhistory	Purge Old History
purgeoldhistory.maxkeepdays	Max Keep Days
purgeoldhistory.maxkeephours	Max Keep Hours
purgeoldhistory.minkeepdays	Minimum Keep Days
purgeoldhistory.minkeephours	Minimum Keep Hours
purgeoldtasks	Purge Old Tasks
purgeoldtasks.after	After
purgeoldtasks.er	Extract/Replicat
purgeoldtasks.extract	Extract
purgeoldtasks.replicat	Replicat
purgeoldtasks.usestopstatus	Use Top Status
randomrollbacks	Random Rollbacks
recoveryoptions	Recovery Options

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
recoveryoptions.appendmode	Append Mode
recoveryoptions.overwritemode	Overwrite Mode
reperror	Replicat Error
reperror.reset	Reset
repfetchedcoloptions	Replicat Fetched Column Options
repfetchedcoloptions.inconsistentrow	Inconsistent Row
repfetchedcoloptions.latestrowversion	Latest Row Version
repfetchedcoloptions.missingrow	Missing Row
repfetchedcoloptions.nofetch	Prevent Fetch
repfetchedcoloptions.redundantrow	Redundant Row
repfetchedcoloptions.setifmissing	Set If Missing
repfetchedcoloptions.snapshotrow	Snapshot Row
replacebadchar	Replaces Invalid Character
replacebadchar.abort	Abort
replacebadchar.enablefallback	Enable Fallback
replacebadchar.escape	Escape
replacebadchar.forcecheck	Force Check

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
replacebadchar.nowarning	No Warning
replacebadchar.null	Null
replacebadchar.skip	Skip
replacebadchar.space	Space
replacebadchar.substitute	Substitute
replacebadchar.unprintable	Unprintable
replacebadnum	Replace Invalid Numbers
replicat	Replicat
repobackupdir	Repository Backup Directory
repobackupfrequency	Repository Backup Frequency
reponumbackupsbeforefullbackup	Repository Backups Before Full Backup
report	Report
report.AT	At
report.ON	On
reportcount	Transaction Record Report Count
reportcount.every	Every
reportcount.rate	Report Rate

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
reportformatnoremote	Report Format No Remote
reportrollover	Report Rollover
reportrollover.AT	At
reportrollover.ON	On
restartcollisions	Restart Collisions
restartinterval	Restart Interval
retrydelay	Retry Delay
rmtfile	Remote File
rmtfile.append	Append
rmtfile.format	Format Release
rmtfile.level	Format Level
rmtfile.maxfiles	Max Files
rmtfile.megabytes	Megabytes
rmtfile.objectdefs	Object Definitions
rmtfile.purge	Purge
rmtfile.release	Format Release
rmtfile.trailbyteorder	Trail Byte Order

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
rmthost	Remote Host
rmthost.compress	Compress
rmthost.compressthreshold	Compress Threshold
rmthost.cpu	CPU
rmthost.encrypt	Encrypt
rmthost.hometerm	Device
rmthost.keyname	Key Name
rmthost.mgrport	Manager Port
rmthost.nostreaming	No Streaming
rmthost.params	Parameters
rmthost.password	Password
rmthost.port	Collector Port
rmthost.pri	Priority
rmthost.processname	Process Name
rmthost.socksproxy	Socks Proxy
rmthost.socksproxy.proxycsalias	Proxy Credential Store Alias
rmthost.socksproxy.proxycsdomain	Proxy Credential Store Domain

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
rmthost.streaming	Streaming
rmthost.tcpbufsize	TCP Buffer Size
rmthost.tcpflushbytes	TCP Flush Bytes
rmthost.timeout	Timeout
rmthost.user	User ID
rmthostoptions	Remote Host Options
rmthostoptions.compress	Compress
rmthostoptions.compressthreshold	Compress Threshold
rmthostoptions.encrypt	Encrypt
rmthostoptions.keyname	Key Name
rmthostoptions.nostreaming	No Streaming
rmthostoptions.params	Parameters
rmthostoptions.streaming	Streaming
rmthostoptions.tcpbufsize	TCP Buffer Size
rmthostoptions.tcpflushbytes	TCP Flush Bytes
rmthostoptions.timeout	Timeout
rmttask	Remote Task

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
rmttask.format	Format Release
rmttask.group	Group
rmttask.level	Format Level
rmttask.params	Parameters
rmttask.release	Format Release
rmttrail	Remote Trail
rmttrail.format	Format Release
rmttrail.level	Format Level
rmttrail.objectdefs	Object Definitions
rmttrail.release	Format Release
rmttrail.trailbyteorder	Trail Byte Order
rollover	Rollover
rollover.at	At
rollover.on	On
rollover.report	Report
schemaexclude	Exclude Replicat Schema
schemaexclude.norename	No Rename

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
sequence	Sequence
sessioncharset	Session Character Set
setenv	Set Environment
showsyntax	Show SQL Syntax
showsyntax.all	All
showsyntax.includelob	Include LOB
showsyntax.noapply	No Apply
sourcecatalog	Source Catalog
sourcecharset	Source Character Set
sourcecharset.character_set_name	Character Set Name
sourcecharset.db2zos	DB2 On z/OS
sourcecharset.override	Override
sourcecharset.passthru	PassThru
sourcedb	Source DB
sourcedb.credentialgroup	Credential Group
sourcedb.domain	Domain
sourcedb.encryptkey	Encrypt Key

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
sourcedb.password	Password
sourcedb.password.aes128	AES128
sourcedb.password.aes192	AES192
sourcedb.password.aes256	AES256
sourcedb.password.blowfish	Blowfish
sourcedb.sessioncharset	Session Character Set
sourcedb.sqlid	
sourcedb.sysdba	Sysdba
sourcedb.thread	Threads
sourcedb.userid	User ID
sourcedb.useridalias	User Alias
sourcedefs	Source Definitions
sourcedefs.override	Override
sourceisfile	Source Is File
sourceistable	Source Is Table
sourcetimezone	Source Timezone
spacestonull	Convert Spaces to Null

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
specialrun	Special Run
sqlduperr	SQL Duplicate Error
sqlexec	SQL Execution
sqlexec.every	Every
sqlexec.onexit	On Exit
sqlexec.thread	Thread
startupvalidationdelay	Startup Validation Delay (secs)
startupvalidationdelaycsecs	Startup Validation Delay (csecs)
statoptions	Statistic Options
statoptions.reportcharconv	Report Character Conversion
statoptions.reportdetail	Operation Statistics
statoptions.reportfetch	Fetch Statistics
statoptions.resetreportstats	Reset Report Statistics
statoptions.thread	Thread
syslog	Sys Log
syslog.all	All
syslog.error	Error

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
syslog.info	Info
syslog.none	None
syslog.warn	Warning
tableexclude	Exclude Table
tableexclude.norename	No Rename
targetdb	Target DB
targetdb.domain	Domain
targetdb.dsn	DSN
targetdb.encryptkey	Encrypt Key
targetdb.libfile	Library File
targetdb.password	Password
targetdb.password.aes128	AES128
targetdb.password.aes192	AES192
targetdb.password.aes256	AES256
targetdb.password.blowfish	Blowfish
targetdb.sessioncharset	Session Character Set
targetdb.set	Set

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
targetdb.sqlid	SQL ID
targetdb.sysdba	Sysdba
targetdb.thread	Threads
targetdb.userid	User ID
targetdb.useridalias	User Alias
targetdefs	Target Definitions
targetdefs.override	Override
tcpsourcetimer	Compensate For System Clock Differences
threadoptions	Thread Options
threadoptions.eofdelaycsecs	EOF Delay Centiseconds
threadoptions.eofdelayms	EOF Delay (ms)
threadoptions.except	Except
threadoptions.inqueuesize	Input Queue Size
threadoptions.outqueuesize	Output Queue Size
threadoptions.processthreads	Process Threads
threadoptions.select	Select
threadoptions.stacksize	Stack Size

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
tltrace	Transaction Log Trace
tltrace.data	Use Raw Format
tltrace.ddl	DDL
tltrace.debug	Debug
tltrace.file	File
tltrace.level	Level
tltrace.pause	Pause
trace	Trace
trace2	Trace2
traceapi	Trace API
tracetable.0	Trace Table
tracetable.1	Name
trail_seqlen_9d	Trail Sequence Length 9 digits
trailbyteorder	Trail Byte Order
trailcharset	Trail Character Set
trailcharset.replacebadchar	Replace Bad Character
trailcharsetascii	Trail Character Set ASCII

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
trailcharsetebcdic	Trail Character Set EBCDIC
trailcharsetunicode	Unicode Trail Character Set
tranlogoptions	Transaction Log Options
tranlogoptions.USE_ROOT_CONTAINER_TIMEZONE	Use Root Container Timezone
tranlogoptionsallowtablecompression	Allow Table Compression
tranlogoptions.activationidpadlen	Activation ID Pad Length
tranlogoptions.activesecondarytruncationpoint	Active Secondary Truncation
tranlogoptions.adgapplycheckfreq	ADG Apply Check Frequency
tranlogoptions.adgretrycount	ADG Retry Count
tranlogoptions.adgtimeout	ADG Timeout
tranlogoptions.allowdataloss	Allow Data Loss
tranlogoptions.allowtablecompression	Allow Table Compression
tranlogoptions.altarchivedlogformat	Alt Archive Log Format
tranlogoptions.altarchivelogdest	Alt Archive Log Destination
tranlogoptions.altlogdest	Alt Log Destination
tranlogoptions.altonlinelogs	Alt Online Logs
tranlogoptions.apifilter	API Filter

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
tranlogoptions.archivedlogonly	Archived Log Only
tranlogoptions.archiverestoreexecutable	Archive Restore Executable
ranlogoptions.archiverestoreparams	Archive Restore Parameters
tranlogoptions.asmbufsize	ASM Buffer Size
tranlogoptions.asmuser	ASM User
tranlogoptions.asmuser.aes128	AES128
tranlogoptions.asmuser.aes192	AES192
tranlogoptions.asmuser.aes256	AES256
tranlogoptions.asmuser.asmpassword	ASM Password
tranlogoptions.asmuser.blowfish	Blowfish
tranlogoptions.asmuser.encryptkey	Encrypt Key
tranlogoptions.asmuser.sysdba	Sysdba
tranlogoptions.asmuseralias	ASM User Alias
tranlogoptions.asmuseralias.domain	Domain
tranlogoptions.asynctransprocessing	Async Transaction Processing
tranlogoptions.bufsize	Buffer Size
tranlogoptions.checkpointretentiontime	Checkpoint Retention

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
tranlogoptions.checkpointtable	Checkpoint Table
tranlogoptions.checkposition	Check Position
tranlogoptions.checktablelevelsupplog	Checktable Level Suppl Log
tranlogoptions.completearchivedlogonly	Complete Archived Log
tranlogoptions.completearchivedlogtimeout	Complete Archived Log Timeout
tranlogoptions.convertucs2clobs	Convert UCS to CLOBS
tranlogoptions.createtranlog	Create Transaction Log
tranlogoptions.databaseidpadlen	Database ID Pad Len
tranlogoptions.dblogreader	DB Log Reader
tranlogoptions.dblogreaderbufsize	DB Log Reader Buffer Size
tranlogoptions.excludetag	Exclude Tag
tranlogoptions.excludetrans	Exclude Transaction
tranlogoptions.excludeuser	Exclude User
tranlogoptions.excludeuserid	Exclude User ID
tranlogoptions.failovertargetdestid	Failover Target Destination ID
tranlogoptions.fetchinlinesflob	Fetch Inline FS Lob
tranlogoptions.fetchlobonerror	Fetch LOB On Error

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
tranlogoptions.fetchpartiallob	Fetch Partial LOB
tranlogoptions.fetchpartialxml	Fetch Partial XML
tranlogoptions.fetchxmlonerror	Fetch XML On Error
tranlogoptions.filtertable	Filter Table
tranlogoptions.flush	Flush
tranlogoptions.forcefetchlob	Force Fetch LOB
tranlogoptions.getctasdml	Get CTAS DML
tranlogoptions.getmetadatafromvam	Get Metadata From VAM
tranlogoptions.handledlfailover	Handled Failover
tranlogoptions.iflockseconds	If Lock (secs)
tranlogoptions.ignoredatacapturechanges	Ignore Data Capture Changes
tranlogoptions.ignoredirectloadinserts	Ignore Direct Load Inserts
tranlogoptions.ignoregap	Ignore Gap
tranlogoptions.ignorekeyerror	Ignore Key Error
tranlogoptions.includeaux	Include AUX
tranlogoptions.includeregionid	Include Region ID
tranlogoptions.includeregionidwithoffset	Include Region ID With Offset

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
tranlogoptions.integratedparams	Integrated Parameters
tranlogoptions.legacylobreading	Legacy LOB Reading
tranlogoptions.logretention	Log Retention
tranlogoptions.logretention.days	Days
tranlogoptions.logsource	Log Source
tranlogoptions.logswitchmsg	Log Switch Message
tranlogoptions.managesecondarytruncationpoint	Manage Secondary Truncation Point
tranlogoptions.maxparallelrec	Max Parallel Records
tranlogoptions.maxreadsize	Max Read Size
tranlogoptions.maxwarneof	Max Warn EOF
tranlogoptions.minefromactivedg	Mine From Active DG
tranlogoptions.minefromsnapshotstby	Mine From Snapshots
tranlogoptions.mininguser	Mining User
tranlogoptions.mininguser.algorithm	Algorithm
tranlogoptions.mininguser.aes128	AES128
tranlogoptions.mininguser.aes192	AES192
tranlogoptions.mininguser.aes256	AES256

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
tranlogoptions.mininguser.blowfish	Blowfish
tranlogoptions.mininguser.encryptkey	Encrypt Key
tranlogoptions.mininguser.miningpassword	Mining Password
tranlogoptions.mininguser.sysdba	Sysdba
tranlogoptions.mininguseralias	Mining User Alias
tranlogoptions.mininguseralias.domain	Domain
tranlogoptions.noadgtimeout	No ADG Timeout
tranlogoptions.noasynctransprocessing	No Async Transaction Processing
tranlogoptions.noddlchangewarning	No DDL Change Warning
tranlogoptions.noflush	No Flush
tranlogoptions.noignoredatacapturechanges	Do Not Ignore Data Capture
tranlogoptions.norequirelongdatacapturechan ges	Do Not Require Long Data Capture
tranlogoptions.onephase	One Phase
tranlogoptions.pathmap	Path Map
tranlogoptions.pollinterval	Poll Interval
tranlogoptions.prepareforupgradetoie	Prepare For Upgrade To IE
tranlogoptions.purgeorphanedtransactions	Purge Orphaned Transactions

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
tranlogoptions.queryretrycount	Query Retry Count
tranlogoptions.readqueuesize	Read Queue Size
tranlogoptions.requirelongdatacapturechange s	Require Long Data Capture
tranlogoptions.resetlogsidpadlen	Reset Logs ID Pad Length
tranlogoptions.restartappend	Restart Append
tranlogoptions.seqpadlen	Sequence Pad Length
tranlogoptions.server	Server
tranlogoptions.skipdirloadinsert	Skip DIR Load Insert
tranlogoptions.startatactivelsn	Start At Active LSN
tranlogoptions.threadpadlen	Thread Pad Length
tranlogoptions.transcleanupfrequency	Trans Cleanup Frequency (min)
tranlogoptions.truncpointoff	Truncation Point Off
tranlogoptions.tslookupbeginlri	Timestamp Lookup Start
tranlogoptions.tslookupendlri	Timestamp Lookup Stop
tranlogoptions.unprivileged	Unprivileged
tranlogoptions.usenativeobjsupport	Use Native Object Support
tranlogoptions.useocithreads	Use OCI Threads

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
tranlogoptions.useprevresetlogsid	Use Previous Reset Log SID
tranlogoptions.userexit	User Exit
tranlogoptions.validateinlinesflob	Validate Inline FS Lob
tranlogoptions.vamcompatibility	VAM Compatibility
transactiontimeout	Transaction Timeout
transmemory	Transaction Memory
transmemory.directory	Directory
transmemory.inittransram	Initial Trans RAM
transmemory.ram	RAM
transmemory.ramincrement	RAM Increment
transmemory.transallsources	Trans All Sources
transmemory.transram	Trans RAM
trimspaces	Trim CHAR to VARCHAR Spaces
trimvarspaces	Trim VARCHAR to CHAR Spaces
unlockedtrailfiles	Unlocked Trail Files
updatedeletes	Update Deletes
updateinserts	Update Inserts

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
updaterecordformat	Update Record Format
upreporthours	Up Report Hours
upreportminutes	Up Report Minutes
use_traildefs	Use Trail Definitions
useansisqlquotes	ANSI SQL Quotes
usedateprefix	Use Date Prefix
usededicatedcoordinationthread	Use Dedicated Coordination Thread
useipv4	IPV4
useipv6	IPV6
userid	Userid
userid.password	Password
userid.password.algorithm	Algorithm
userid.password.aes128	AES128
userid.password.aes192	AES192
userid.password.aes256	AES256
userid.password.blowfish	Blowfish
userid.password.encryptkey	Encrypt Key

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
userid.sysdba	Sysdba
userid.thread	Threads
useridalias	User Alias
useridalias.domain	Domain
useridalias.sysdba	Sysdba
useridalias.thread	Threads
usethreads	Use Threads
usetimeprefix	Use Time Prefix
usetimestampprefix	Use Timestamp Prefix
vam	Vendor Access Module
vam.params	Parameters
varwidthnchar	Treat NCHAR, NVARCHAR2, NCLOB As UTF-16
veridatareportage	Veridata Report Age
walletlocation	Wallet Location
warnlongtrans	Warn Long Transaction
warnlongtrans.checkinterval	Check Interval
warnlongtrans.nousethreads	No Use Threads

Oracle GoldenGate Parameter/Option	Oracle GoldenGate Studio Label
warnlongtrans.uselastreadtime	Use Last Read Time
warnrate	Warn Rate
wildcardresolve	Resolve Wildcard
wildcardresolve.both	Intermediate and Dynamic Resolve
wildcardresolve.dynamic	Dynamic Resolve
wildcardresolve.ignoremissing	Ignore Missing
wildcardresolve.immediate	Immediate Resolve
xagenable	XAG Integration